

Amazon Virtual Private Cloud



Amazon Virtual Private Cloud: IP Address Manager

Table of Contents

| | |
|--|-----------|
| What is IPAM? | 1 |
| How IPAM works | 2 |
| Getting started with IPAM | 4 |
| Access IPAM | 4 |
| Configure permissions for your IPAM | 5 |
| Integrate IPAM with accounts in an Amazon Organization | 5 |
| Integrate IPAM with accounts outside of your organization | 8 |
| Use IPAM with a single account | 11 |
| Create an IPAM | 11 |
| Plan for IP address provisioning | 14 |
| Example IPAM pool plans | 15 |
| Create IPv4 pools | 17 |
| Create IPv6 pools | 26 |
| Allocate CIDRs | 33 |
| Create a VPC that uses an IPAM pool CIDR | 34 |
| Manually allocate a CIDR to a pool to reserve IP address space | 34 |
| Managing IP address space in IPAM | 36 |
| Enforce IPAM use for VPC creation | 36 |
| Enforce IPAM when creating VPCs | 37 |
| Enforce an IPAM pool when creating VPCs | 37 |
| Enforce IPAM for all but a given list of OUs | 38 |
| Share an IPAM pool using Amazon RAM | 39 |
| Provision CIDRs to a pool | 41 |
| Deprovision CIDRs from a pool | 43 |
| Edit a pool | 44 |
| Delete a pool | 45 |
| Work with resource discoveries | 46 |
| Create a resource discovery | 46 |
| View resource discovery details | 48 |
| Share a resource discovery | 50 |
| Associate a resource discovery with an IPAM | 52 |
| Disassociate a resource discovery | 53 |
| Delete a resource discovery | 54 |
| Create additional scopes | 55 |

| | |
|--|-----------|
| Move VPC CIDRs between scopes | 56 |
| Change the monitoring state of VPC CIDRs | 57 |
| Delete a scope | 59 |
| Release an allocation | 60 |
| Modify an IPAM | 62 |
| Modify IPAM tier | 62 |
| Modify IPAM operating Regions | 63 |
| Delete an IPAM | 64 |
| Tracking IP address usage in IPAM | 67 |
| Monitor CIDR usage with the IPAM dashboard | 67 |
| Monitor CIDR usage by resource | 70 |
| Monitor IPAM with Amazon CloudWatch | 73 |
| IPAM pool and scope metrics | 74 |
| Resource utilization metrics | 76 |
| View IP address history | 81 |
| View public IP insights | 84 |
| Tutorials | 89 |
| Create an IPAM and pools using the console | 89 |
| Prerequisites | 90 |
| How Amazon Organizations integrates with IPAM | 90 |
| Step 1: Delegate an IPAM administrator | 91 |
| Step 2: Create an IPAM | 93 |
| Step 3: Create a top-level IPAM pool | 95 |
| Step 4: Create Regional IPAM pools | 100 |
| Step 5: Create a pre-production development pool | 104 |
| Step 6: Share the IPAM pool | 108 |
| Step 7: Create a VPC with a CIDR allocated from an IPAM pool | 113 |
| Step 8: Cleanup | 117 |
| Create an IPAM and pools using the Amazon CLI | 119 |
| Step 1: Enable IPAM in your organization | 120 |
| Step 2: Create an IPAM | 120 |
| Step 3: Create an IPv4 address pool | 122 |
| Step 4: Provision a CIDR to the top-level pool | 124 |
| Step 5: Create a Regional pool with CIDR sourced from the top-level pool | 125 |
| Step 6: Provision a CIDR to the Regional pool | 127 |
| Step 7: Create a RAM share for enabling IP assignments across accounts | 128 |

| | |
|--|------------|
| Step 8. Create a VPC | 129 |
| Step 9. Cleanup | 130 |
| View IP address history using the Amazon CLI | 131 |
| Overview | 131 |
| Scenarios | 132 |
| Bring your ASN to IPAM | 139 |
| Onboarding prerequisites for your ASN | 140 |
| Tutorial steps | 141 |
| Bring your IP addresses to IPAM | 145 |
| Amazon console and CLI | 146 |
| Amazon CLI only | 171 |
| Transfer a BYOIP IPv4 CIDR to IPAM | 214 |
| Step 1: Create Amazon CLI named profiles and IAM roles | 215 |
| Step 2: Get your IPAM's public scope ID | 215 |
| Step 3: Create an IPAM pool | 216 |
| Step 4: Share the IPAM pool using Amazon RAM | 218 |
| Step 5: Transfer an existing BYOIP IPV4 CIDR to IPAM | 221 |
| Step 6: View the CIDR in IPAM | 223 |
| Step 7: Cleanup | 224 |
| Plan VPC IP address space for subnet IP allocations | 227 |
| Step 1: Create a VPC | 228 |
| Step 2: Create a resource planning pool | 229 |
| Step 3: Create subnet pools | 230 |
| Step 4: Create subnets | 231 |
| Step 5: Cleanup | 232 |
| Identity and access management in IPAM | 233 |
| Service-linked roles for IPAM | 233 |
| Permissions granted to the service-linked role | 233 |
| Create the service-linked role | 234 |
| Edit the service-linked role | 235 |
| Delete the service-linked role | 235 |
| Managed policies for IPAM | 235 |
| Updates to the Amazon managed policy | 237 |
| Example policy | 239 |
| Quotas | 241 |
| Pricing | 243 |

| | |
|--|------------|
| View pricing information | 243 |
| View your current costs and usage using Amazon Cost Explorer | 243 |
| Related information | 244 |
| Document history | 245 |

What is IPAM?

Amazon VPC IP Address Manager (IPAM) is a VPC feature that makes it easier for you to plan, track, and monitor IP addresses for your Amazon workloads. You can use IPAM automated workflows to more efficiently manage IP addresses.

You can use IPAM to do the following:

- Organize IP address space into routing and security domains
- Monitor IP address space that's in use and monitor resources that are using space against business rules
- View the history of IP address assignments in your organization
- Automatically allocate CIDRs to VPCs using specific business rules
- Troubleshoot network connectivity issues
- Enable cross-region and cross-account sharing of your Bring Your Own IP (BYOIP) addresses
- Provision Amazon-provided contiguous IPv6 CIDR blocks to pools for VPC creation


This guide consists of the following sections:

- [How IPAM works](#): IPAM concepts and terminology.
- [Getting started with IPAM](#): Steps to enable company-wide IP address management with Amazon Organizations, create an IPAM, and plan IP address usage.
- [Managing IP address space in IPAM](#): Steps to manage your IPAM, scopes, pools, and allocations.
- [Tracking IP address usage in IPAM](#): Steps to monitor and track IP address usage with IPAM.
- [Tutorials for Amazon VPC IP Address Manager](#): Detailed step-by-step tutorials for creating an IPAM and pools, allocating VPC CIDRs, and bringing your own public IP address CIDRs to IPAM.

How IPAM works

This topic explains some of the key concepts to help you get started with IPAM.

The following diagram shows an IPAM pool hierarchy for multiple Amazon Regions within a top-level IPAM pool. Each Amazon Regional pool has two IPAM development pools within it, one pool for pre-production and one pool production resources. For more information about IPAM concepts, see the descriptions below the diagram.



To use Amazon VPC IP Address Manager, you first create an IPAM.

When you create the IPAM, you choose which Amazon Region to create it in. When you create an IPAM, Amazon VPC IPAM automatically creates two scopes for the IPAM. The scopes, together with pools and allocations, are key components of your IPAM.

- A **scope** is the highest-level container within IPAM. An IPAM contains two default scopes. Each scope represents the IP space for a single network. The **private scope** is intended for all private space. The **public scope** is intended for all public space. Scopes enable you to reuse IP addresses across multiple unconnected networks without causing IP address overlap or conflict. Within a scope, you create IPAM pools.
- A **pool** is a collection of contiguous IP address ranges (or CIDRs). IPAM pools enable you to organize your IP addresses according to your routing and security needs. You can have multiple pools within a top-level pool. For example, if you have separate routing and security needs for development and production applications, you can create a pool for each. Within IPAM pools, you allocate CIDRs to Amazon resources.
- An **allocation** is a CIDR assignment from an IPAM pool to another resource or IPAM pool. When you create a VPC and choose an IPAM pool for the VPC's CIDR, the CIDR is allocated from the CIDR provisioned to the IPAM pool. You can monitor and manage the allocation with IPAM.

IPAM can manage and monitor private IPv4 CIDRs, public IPv4/IPv6 CIDRs that you own, and Amazon-owned public IPv6 space.

To get started and create an IPAM, see [Getting started with IPAM](#).

Getting started with IPAM

Follow the steps in this section to get started with IPAM. You'll begin by accessing IPAM and deciding if you want to delegate an IPAM account. By the end of this section, you will have created an IPAM, created multiple pools of IP addresses, and allocated a CIDR in a pool to a VPC.

Contents

- [Access IPAM](#)
- [Configure permissions for your IPAM](#)
- [Create an IPAM](#)
- [Plan for IP address provisioning](#)
- [Allocate CIDRs](#)

Access IPAM

As with other Amazon services, you can create, access, and manage your IPAM using the following methods:

- **Amazon Management Console:** Provides a web interface that you can use to create and manage your IPAM. See <https://console.amazonaws.cn/ipam/>.
- **Amazon Command Line Interface (Amazon CLI):** Provides commands for a broad set of Amazon services, including Amazon VPC. The Amazon CLI is supported on Windows, macOS, and Linux. To get the Amazon CLI, see [Amazon Command Line Interface](#).
- **Amazon SDKs:** Provide language-specific APIs. The Amazon SDKs take care of many of the connection details, such as calculating signatures, handling request retries, and handling errors. For more information, see [Amazon SDKs](#).
- **Query API:** Provides low-level API actions that you call using HTTPS requests. Using the Query API is the most direct way to access IPAM. However, it requires your application to handle low-level details such as generating the hash to sign the request, and handling errors. For more information, see Amazon IPAM actions in the [Amazon EC2 API Reference](#).

This guide primarily focuses on using the Amazon Management Console to create, access, and manage your IPAM. In each description of how to complete a process in the console, we include

links to the Amazon CLI documentation that shows you how to do the same thing by using the Amazon CLI.

If you are a first-time user of IPAM, review [How IPAM works](#) to learn about the role of IPAM in Amazon VPC and then continue with the instructions in [Configure permissions for your IPAM](#).

Configure permissions for your IPAM

Before you begin using IPAM, you must choose one of the options in this section to enable IPAM to monitor CIDRs associated with EC2 networking resources and store metrics:

- To enable IPAM to integrate with Amazon Organizations to enable the Amazon VPC IPAM service to manage and monitor networking resources created by all Amazon Organizations member accounts, see [Integrate IPAM with accounts in an Amazon Organization](#).
- After you integrate with Amazon Organizations, to integrate IPAM with accounts outside of your organization, see [Integrate IPAM with accounts outside of your organization](#).
- To use a single Amazon account with IPAM and enable the Amazon VPC IPAM service to manage and monitor the networking resources you create with the single account, see [Use IPAM with a single account](#).

If you do not choose one of these options, you can still create IPAM resources, such as pools, but you won't see metrics in your dashboard and you will not be able to monitor the status of resources.

Contents

- [Integrate IPAM with accounts in an Amazon Organization](#)
- [Integrate IPAM with accounts outside of your organization](#)
- [Use IPAM with a single account](#)

Integrate IPAM with accounts in an Amazon Organization

Optionally, you can follow the steps in this section to integrate IPAM with Amazon Organizations and delegate a member account as the IPAM account.

The IPAM account is responsible for creating an IPAM and using it to manage and monitor IP address usage.

Integrating IPAM with Amazon Organizations and delegating an IPAM admin has the following benefits:

- **Share your IPAM pools with your organization:** When you delegate an IPAM account, IPAM enables other Amazon Organizations member accounts in the organization to allocate CIDRs from IPAM pools that are shared using Amazon Resource Access Manager (RAM). For more information on setting up an organization, see [What is Amazon Organizations?](#) in the *Amazon Organizations User Guide*.
- **Monitor IP address usage in your organization:** When you delegate an IPAM account, you give IPAM permission to monitor IP usage across all of your accounts. As a result, IPAM automatically imports CIDRs that are used by existing VPCs across other Amazon Organizations member accounts into IPAM.

If you do not delegate an Amazon Organizations member account as an IPAM account, IPAM will monitor resources only in the Amazon account that you use to create the IPAM.

Important

- You must enable integration with Amazon Organizations by using IPAM in the Amazon management console or the [enable-ipam-organization-admin-account](#) Amazon CLI command. This ensures that the `AWSServiceRoleForIPAM` service-linked role is created. If you enable trusted access with Amazon Organizations by using the Amazon Organizations console or the [register-delegated-administrator](#) Amazon CLI command, the `AWSServiceRoleForIPAM` service-linked role isn't created, and you can't manage or monitor resources within your organization.

Note

When integrating with Amazon Organizations:

- IPAM charges you for each active IP address that it monitors in your organization's member accounts. For more information about pricing, see [IPAM pricing](#).
- You must have an account in Amazon Organizations and a management account set up with one or more member accounts. For more information about account types, see [Terminology and concepts](#) in the *Amazon Organizations User Guide*. For more information on setting up an organization, see [Getting started with Amazon Organizations](#).

- The IPAM account must be an Amazon Organizations member account. You cannot use the Amazon Organizations management account as the IPAM account.
- The IPAM account must use an IAM role that has an IAM policy attached to it that permits the `iam:CreateServiceLinkedRole` action. When you create the IPAM, you automatically create the `AWSServiceRoleForIPAM` service-linked role.
- The user associated with the Amazon Organizations management account must use an IAM role that has the following IAM policy actions attached:
 - `ec2:EnableIpamOrganizationAdminAccount`
 - `organizations:EnableAwsServiceAccess`
 - `organizations:RegisterDelegatedAdministrator`
 - `iam:CreateServiceLinkedRole`

For more information on creating IAM roles, see [Creating a role to delegate permissions to an IAM user](#) in the *IAM User Guide*.

- The user associated with the Amazon Organizations management account may use an IAM role that has the following IAM policy actions attached to list your current AWS Orgs delegated administrators: `organizations:ListDelegatedAdministrators`

Amazon Management Console

To select an IPAM account

1. Using the Amazon Organizations management account, open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the Amazon Management Console, choose the Amazon Region in which you want to work with IPAM.
3. In the navigation pane, choose **Organization settings**.
4. The **Delegate** option is only available if you've logged in to the console as the Amazon Organizations management account. Choose **Delegate**.
5. Enter the Amazon account ID for an IPAM account. The IPAM administrator must be an Amazon Organizations member account.
6. Choose **Save changes**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- To delegate an IPAM admin account using Amazon CLI, use the following command: [enable-ipam-organization-admin-account](#)

When you delegate an Organizations member account as an IPAM account, IPAM automatically creates a service-linked IAM role in all member accounts in your organization. IPAM monitors the IP address usage in these accounts by assuming the service-linked IAM role in each member account, discovering the resources and their CIDRs, and integrating them with IPAM. The resources within all member accounts will be discoverable by IPAM regardless of their Organizational Unit. If there are member accounts that have created a VPC, for example, you'll see the VPC and its CIDR in the Resources section of the IPAM console.

Important

The role of the Amazon Organizations management account that delegated the IPAM admin is now complete. To continue using IPAM, the IPAM admin account must log into Amazon VPC IPAM and create an IPAM.

Integrate IPAM with accounts outside of your organization

This section describes how to integrate your IPAM with Amazon accounts outside of your organization. To complete steps in this section, you must have already completed the steps in [Integrate IPAM with accounts in an Amazon Organization](#) and delegated an IPAM account.

Integrating IPAM with Amazon accounts outside of your organization enables you to do the following:

- Manage IP addresses outside of your organization from a single IPAM account.
- Share IPAM pools with third-party services hosted by other Amazon accounts in other Amazon Organizations.

After you integrate IPAM with Amazon accounts outside of your organization, you can share an IPAM pool directly with the desired accounts of other organizations.

Contents

- [Considerations and limitations](#)
- [Process overview](#)

Considerations and limitations

This section contains considerations and limitations for integrating IPAM with accounts outside of your organization:

- When you share a resource discovery with another account, the only data that is exchanged is IP address and account status monitoring data. You can view this data before sharing using the [get-ipam-discovered-resource-cidrs](#) and [get-ipam-discovered-accounts](#) CLI commands or [GetIpamDiscoveredResourceCidrs](#) and [GetIpamDiscoveredAccounts](#) APIs. For resource discoveries that monitor resources across an organization, no organization data (such as the names of Organizational Units in your organization) are shared.
- When you create a resource discovery, the resource discovery monitors all visible resources in the owner account. If the owner account is a third-party service Amazon account that creates resources for multiple of their own customers, those resources will be discovered by the resource discovery. If the third-party Amazon service account shares the resource discovery with an end-user Amazon account, the end-user will have visibility into the resources of the other customers of the third-party Amazon service. For that reason, the third-party Amazon service should exercise caution creating and sharing resource discoveries or use a separate Amazon account for each customer.

Process overview

This section explains how to integrate your IPAM with Amazon accounts outside of your organization. It refers to topics that are covered in other sections of this guide. Keep this page visible, and open the topics linked below in a new window so that you can return to this page for guidance.

When you integrate IPAM with Amazon accounts outside of your organization, there are 4 Amazon accounts involved in the process:

- **Primary Org Owner** - The Amazon Organizations management account for organization 1.
- **Primary Org IPAM Account** - The IPAM delegated administrator account for organization 1.
- **Secondary Org Owner** - The Amazon Organizations management account for organization 2.
- **Secondary Org Admin Account** - The IPAM delegated administrator account for organization 2.

Steps

1. Primary Org Owner delegates a member of their organization as the Primary Org IPAM Account (see [Integrate IPAM with accounts in an Amazon Organization](#)).
2. Primary Org IPAM Account creates an IPAM (see [Create an IPAM](#)).
3. Secondary Org Owner delegates a member of their organization as the Secondary Org Admin Account (see [Integrate IPAM with accounts in an Amazon Organization](#)).
4. Secondary Org Admin Account creates a resource discovery and shares it with the Primary Org IPAM Account using Amazon RAM (see [Create a resource discovery](#) and [Share a resource discovery](#)). The resource discovery must be created in the same home Region as the Primary Org IPAM.
5. Primary Org IPAM Account accepts the resource share invitation using Amazon RAM (see [Accepting and rejecting resource share invitations](#) in the *Amazon RAM User Guide*).
6. Primary Org IPAM Account associates the resource discovery with their IPAM (see [Associate a resource discovery with an IPAM](#)).
7. Primary Org IPAM Account can now monitor and/or manage IPAM resources created by the accounts in Secondary Org.
8. (Optional) Primary Org IPAM Account shares IPAM pools with member accounts in Secondary Org (see [Share an IPAM pool using Amazon RAM](#)).
9. (Optional) If Primary Org IPAM Account wants to stop discovering resources in Secondary Org, it can disassociate the resource discovery from the IPAM (see [Disassociate a resource discovery](#)).
10. (Optional) If the Secondary Org Admin Account wants to stop participating in the Primary Org's IPAM, they can unshare the shared resource discovery (see [Update a resource share in Amazon RAM](#) in the *Amazon RAM User Guide*) or delete the resource discovery (see [Delete a resource discovery](#)).

Use IPAM with a single account

If you choose not to [Integrate IPAM with accounts in an Amazon Organization](#), you can use IPAM with a single Amazon account.

When you create an IPAM in the next section, a service-linked role is automatically created for the Amazon VPC IPAM service in Amazon Identity and Access Management. IPAM uses the service-linked role to monitor and store metrics for CIDRs associated with EC2 networking resources. For more information on the service-linked role and how IPAM uses it, see [Service-linked roles for IPAM](#).

Important

If you use IPAM with a single Amazon account, you must ensure that the Amazon account you use to create the IPAM uses a IAM role with a policy attached to it that permits the `iam:CreateServiceLinkedRole` action. When you create the IPAM, you automatically create the `AWSServiceRoleForIPAM` service-linked role. For more information on managing IAM policies, see [Editing IAM policies](#) in the *IAM User Guide*.

Once the single Amazon account has permission to create the IPAM service-linked role, go to [Create an IPAM](#).

Create an IPAM

Follow the steps in this section to create your IPAM. If you have delegated an IPAM administrator, these steps should be completed by the IPAM account.

Important

When you create an IPAM, you will be asked to allow IPAM to replicate data from source accounts into an IPAM delegate account. To integrate IPAM with Amazon Organizations, IPAM needs your permission to replicate resource and IP usage details across accounts (from member accounts to the delegated IPAM member account) and across Amazon Regions (from operating Regions to the home Region of your IPAM). For single account IPAM users, IPAM needs your permission to replicate resource and IP usage details across operating Regions to the home Region of your IPAM.

When you create the IPAM, you choose the Amazon Regions where the IPAM is allowed to manage IP address CIDRs. These Amazon Regions are called *operating Regions*. IPAM discovers and monitors resources only in the Amazon Regions that you select as operating Regions. IPAM doesn't store any data outside of the operating Regions that you select.

The following example hierarchy shows how the Amazon Regions that you assign when you create the IPAM will impact the Regions that will be available for pools that you create later.

- **IPAM operating in Amazon Region 1 and Amazon Region 2**

- Private scope
 - Top-level IPAM pool
 - Regional IPAM pool in **Amazon Region 2**
 - Development pool
 - Allocation for a VPC in **Amazon Region 2**


You can only create one IPAM. For more information about increasing quotas related to IPAM, see [Quotas for your IPAM](#).

Amazon Management Console

To create an IPAM

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the Amazon Management Console, choose the Amazon Region in which you want to create the IPAM. Create the IPAM in your main Region of operations.
3. On the service home page, choose **Create IPAM**.
4. Select **Allow Amazon VPC IP Address Manager to replicate data from source account(s) into the IPAM delegate account**. If you do not select this option, you cannot create an IPAM.
5. Choose an **IPAM tier**. For more information about the features available in each tier and the costs associated with the tiers, see the IPAM tab on the [Amazon VPC pricing page](#).
6. Under **Operating regions**, select the Amazon Regions in which this IPAM can manage and discover resources. The Amazon Region in which you are creating your IPAM is selected as one of the operating Regions by default. For example, if you're creating this IPAM in Amazon Region us-east-1 but you want to create Regional IPAM pools later that provide

CIDRs to VPCs in us-west-2, select us-west-2 here. If you forget an operating Region, you can return at a later time and edit your IPAM settings.

 **Note**

If you are creating an IPAM in the Free Tier, you can select multiple operating Regions for your IPAM, but the only IPAM feature that will be available across operating Regions is [Public IP insights](#). You cannot use other features in the Free Tier, like BYOIP, across the IPAM's operating Regions. You can only use them in the IPAM's home Region. To use all IPAM features across operating Regions, [create an IPAM in the Advanced Tier](#).

7. Choose **Create IPAM**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create, modify, and view details related to your IPAM:

1. Create the IPAM: [create-ipam](#)
2. View the IPAM that you've created: [describe-ipams](#)
3. View the scopes that are created automatically: [describe-ipam-scopes](#)
4. Modify an existing IPAM: [modify-ipam](#)

When you have completed these steps, IPAM has done the following:

- Created your IPAM. You can see the IPAM and the currently selected operating Regions by choosing IPAMs in the left navigation pane of the console.
- Created one private and one public scope. You can see the scopes by choosing **Scopes** in the navigation pane. For more information about scopes, see [How IPAM works](#).

Plan for IP address provisioning

Follow the steps in this section to plan for IP address provisioning by using IPAM pools. If you have configured an IPAM account, these steps should be completed by that account.

Important

To use IPAM pools across Amazon accounts, you must integrate IPAM with Amazon Organizations or some features may not work properly. For more information, see [Integrate IPAM with accounts in an Amazon Organization](#).

In IPAM, a pool is a collection of contiguous IP address ranges (or CIDRs). Pools enable you to organize your IP addresses according to your routing and security needs. You can create pools for Amazon Regions outside of your IPAM Region. For example, if you have separate routing and security needs for development and production applications, you can create a pool for each.

In the first step in this section, you'll create a top-level pool. Then, you'll create a Regional pool within the top-level pool. Within the Regional pool, you can create additional pools as needed, such as a production and development environment pools. By default, you can create pools up to a depth of 10. For information on IPAM quotas, see [Quotas for your IPAM](#).

Note

The terms *provision* and *allocate* are used throughout this user guide and the IPAM console. *Provision* is used when you add a CIDR to an IPAM pool. *Allocate* is used when you associate a CIDR from an IPAM pool with a resource.

The following is an example hierarchy of the pool structure that you will create by completing the steps in this section:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Private scope
 - Top-level pool
 - Regional pool in Amazon Region 1
 - Development pool

- Allocation for a VPC

This structure serves as an example of how you might want to use IPAM, but you can use IPAM to suit the needs of your organization. For more information on best practices, see [Amazon VPC IP Address Manager Best Practices](#).

If you are creating a single IPAM pool, complete the steps in [Create a top-level IPv4 pool](#) and then skip to [Allocate CIDRs](#).

Contents


- [Example IPAM pool plans](#)
- [Create IPv4 pools](#)
- [Create IPv6 pools](#)

Example IPAM pool plans

You can use IPAM to suit the needs of your organization. This section provides examples of how you might organize your IP addresses.


IPv4 pools in multiple Amazon Regions

The following example shows an IPAM pool hierarchy for multiple Amazon Regions within a top-level pool. Each Amazon Regional pool has two IPAM development pools within it, one pool for development resources and one pool for production resources.




IPv4 pools for multiple lines of business

The following example shows an IPAM pool hierarchy for multiple lines of business within a top-level pool. Each pool for each line of business contains three Amazon Regional pools. Each Regional pool has two IPAM development pools within it, one pool for pre-production resources and one pool for production resources.




IPv6 pools in an Amazon Region

The following example shows an IPAM IPv6 pool hierarchy for multiple lines of business within a Regional pool. Each Regional pool has three IPAM pools within it, one pool for sandbox resources, one pool for development resources, and one pool for production resources.



Subnet pools for multiple lines of business

The following example shows a resource planning pool hierarchy for multiple lines of business and dev/ prod subnet pools. For more information on subnet IP address space planning using IPAM, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).



Create IPv4 pools

Follow the steps in this section to create an IPv4 IPAM pool hierarchy.

The following example shows the hierarchy of the pool structure that you can create with instructions in this guide. In this section, you are creating an IPv4 IPAM pool hierarchy:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Private scope
 - Top-level pool (10.0.0.0/8)
 - Regional pool in Amazon Region 2 (10.0.0.0/16)
 - Development pool (10.0.0.0/24)
 - Allocation for a VPC (10.0.0.0/25)

In the preceding example, the CIDRs that are used are examples only. They illustrate that each pool within the top-level pool is provisioned with a portion of the top-level CIDR.

Contents

- [Create a top-level IPv4 pool](#)
- [Create a Regional IPv4 pool](#)
- [Create a development IPv4 pool](#)

Create a top-level IPv4 pool

Follow the steps in this section to create an IPv4 top-level IPAM pool. When you create the pool, you provision a CIDR for the pool to use. You then assign that space to an allocation. An allocation is a CIDR assignment from an IPAM pool to another IPAM pool or to a resource.

The following example shows the hierarchy of the pool structure that you can create with instructions in this guide. At this step, you are creating the top-level IPAM pool:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Private scope
 - **Top-level pool (10.0.0.0/8)**
 - Regional pool in Amazon Region 1 (10.0.0.0/16)
 - Development pool for non-production VPCs (10.0.0.0/24)
 - Allocation for a VPC (10.0.0.0/25)

In the preceding example, the CIDRs that are used are examples only. They illustrate that each pool within the top-level pool is provisioned with a portion of the top-level CIDR.

When you create an IPAM pool, you can configure rules for the allocations that are made within the IPAM pool.

Allocation rules enable you to configure the following:

- Whether IPAM should automatically import CIDRs into the IPAM pool if it finds them within this pool's CIDR range
- The required netmask length for allocations within the pool
- The required tags for resources within the pool
- The required locale for resources within the pool. The locale is the Amazon Region where an IPAM pool is available for allocations.

Allocation rules determine whether resources are compliant or noncompliant. For additional information about compliance, see [Monitor CIDR usage by resource](#).

⚠ Important

There is an additional implicit rule that is not displayed in the allocation rules. If the resource is in an IPAM pool that is a shared resource in Amazon Resource Access Manager (RAM), the resource owner must be configured as a principal in Amazon RAM. For more information about sharing pools with RAM, see [Share an IPAM pool using Amazon RAM](#).

The following example shows how you might use allocation rules to control access to an IPAM pool:

Example

When you create your pools based on routing and security needs, you might want to allow only certain resources to use a pool. In such cases, you can set an allocation rule stating that any resource that wants a CIDR from this pool must have a tag that matches the allocation rule tag requirements. For example, you could set an allocation rule stating that only VPCs with the tag *prod* can get CIDRs from an IPAM pool. You could also set a rule stating that CIDRs allocated from this pool can be no larger than /24. In this case, a resource could still be created using a CIDR larger than /24 from this pool if the space is available, but because doing so violates an allocation rule on the pool, IPAM flags this resource as noncompliant.

⚠ Important

This topic covers how to create a top-level IPv4 pool with an IP address range provided by Amazon. If you want to bring your own IPv4 address range to Amazon (BYOIP), there are prerequisites. For more information, see [Tutorial: Bring your IP addresses to IPAM](#).

Amazon Management Console**To create a pool**

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose **Create pool**.
4. Under **IPAM scope**, choose the private scope you want to use. For more information about scopes, see [How IPAM works](#).

By default, when you create a pool, the default private scope is selected. Pools in the private scope must be IPv4 pools. Pools in the public scope can be IPv4 or IPv6 pools. The public scope is intended for all public space.

5. (Optional) Add a **Name tag** for the pool and a description for the pool.
6. Under **Source**, choose **IPAM scope**.
7. Under **Address family**, choose **IPv4**.
8. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
9. For the **Locale**, choose **None**. You will set the locale on the Regional pool.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

10. (Optional) You can create a pool without a CIDR, but you won't be able to use the pool for allocations until you've provisioned a CIDR for it. To provision a CIDR, choose **Add new CIDR**. Enter an IPv4 CIDR to provision for the pool. If you want to bring your own IPv4 or IPv6 IP address range to Amazon there are prerequisites. For more information, see [Tutorial: Bring your IP addresses to IPAM](#).
11. Choose optional allocation rules for this pool:
 - **Automatically import discovered resources:** This option is not available if the **Locale** is set to **None**. If selected, IPAM will continuously look for resources within the CIDR range of this pool and automatically import them as allocations into your IPAM. Note the following:
 - The CIDRs that will be allocated for these resources must not already be allocated to other resources in order for the import to succeed.
 - IPAM will import a CIDR regardless of its compliance with the pool's allocation rules, so a resource might be imported and subsequently marked as noncompliant.
 - If IPAM discovers multiple CIDRs that overlap, IPAM will import the largest CIDR only.

- If IPAM discovers multiple CIDRs with matching CIDRs, IPAM will randomly import one of them only.

⚠ Warning

- After you create an IPAM, when you create a VPC, choose the IPAM-allocated CIDR block option. If you do not, the CIDR you choose for your VPC may overlap with an IPAM CIDR allocation.
 - If you have a VPC already allocated in an IPAM pool, a VPC with an overlapping CIDR cannot be automatically imported. For example, if you have a VPC with a 10.0.0.0/26 CIDR allocated in an IPAM pool, a VPC with a 10.0.0.0/23 CIDR (that would cover the 10.0.0.0/26 CIDR) cannot be imported.
 - It takes some time for existing VPC CIDR allocations to be auto-imported into IPAM.
- **Minimum netmask length:** The minimum netmask length required for CIDR allocations in this IPAM pool to be compliant and the largest size CIDR block that can be allocated from the pool. The minimum netmask length must be less than the maximum netmask length. Possible netmask lengths for IPv4 addresses are 0 - 32. Possible netmask lengths for IPv6 addresses are 0 - 128.
 - **Default netmask length:** A default netmask length for allocations added to this pool. For example, if the CIDR that's provisioned to this pool is **10.0.0.0/8** and you enter **16** here, any new allocations in this pool will default to a netmask length of /16.
 - **Maximum netmask length:** The maximum netmask length that will be required for CIDR allocations in this pool. This value dictates the smallest size CIDR block that can be allocated from the pool.
 - **Tagging requirements:** The tags that are required for resources to allocate space from the pool. If the resources have their tags changed after they have allocated space or if the allocation tagging rules are changed on the pool, the resource may be marked as noncompliant.
 - **Locale:** The locale that will be required for resources that use CIDRs from this pool. Automatically imported resources that do not have this locale will be marked noncompliant. Resources that are not automatically imported into the pool will not be allowed to allocate space from the pool unless they are in this locale.

12. (Optional) Choose **Tags** for the pool.

13. Choose **Create pool**.
14. See [Create a Regional IPv4 pool](#).

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create or edit a top-level pool in your IPAM:

1. Create a pool: [create-ipam-pool](#).
2. Edit the pool after you create it to modify the allocation rules: [modify-ipam-pool](#).

Create a Regional IPv4 pool

Follow the steps in this section to create a Regional pool within your top-level pool. If you need only a top-level pool, and don't need additional Regional and development pools, skip to [Allocate CIDRs](#).

The following example shows the hierarchy of the pool structure that you create by following the instructions in this guide. At this step, you are creating the Regional IPAM pool:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Private scope
 - Top-level pool (10.0.0.0/8)
 - **Regional pool in Amazon Region 1 (10.0.0.0/16)**
 - Development pool for non-production VPCs (10.0.0.0/24)
 - Allocation for a VPC (10.0.0.0/25)

In the preceding example, the CIDRs that are used are examples only. They illustrate that each pool within the top-level pool is provisioned with a portion of the top-level CIDR.

Amazon Management Console

To create a Regional pool within a top-level pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose **Create pool**.
4. Under **IPAM scope**, choose the same scope that you used when you created the top-level pool. For more information about scopes, see [How IPAM works](#).
5. (Optional) Add a **Name tag** for the pool and a description for the pool.
6. Under **Source**, choose **IPAM pool**. Then choose the top-level pool that you created in the previous section.
7. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
8. Choose the locale for the pool. Choosing a locale ensures there are no cross-region dependencies between your pool and the resources allocating from it. The available options come from the operating Regions that you chose when you created your IPAM.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

Note

If you are creating a pool in the Free Tier, you can only choose the locale that matches the home Region of your IPAM. To use all IPAM features across locales, [upgrade to the Advanced Tier](#).

9. (Optional) Choose a CIDR to provision for the pool. You can create a pool without a CIDR, but you won't be able to use the pool for allocations until you've provisioned a CIDR for it. You can add CIDRs to a pool at any time by editing the pool.

10. You have the same allocation rule options here as you did when you created the top-level pool. See [Create a top-level IPv4 pool](#) for an explanation of the options that are available when you create pools. The allocation rules for the Regional pool are not inherited from the top-level pool. If you do not apply any rules here, there will be no allocation rules set for the pool.
11. (Optional) Choose **Tags** for the pool.
12. When you've finished configuring your pool, choose **Create pool**.
13. See [Create a development IPv4 pool](#).

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create a Regional pool in your IPAM:

1. Get the ID of the scope that you want to create the pool in: [describe-ipam-scopes](#)
2. Get the ID of the pool that you want to create the pool in: [describe-ipam-pools](#)
3. Create the pool: [create-ipam-pool](#)
4. View the new pool: [describe-ipam-pools](#)

Repeat these steps to create additional pools within the top-level pool, as needed.

Create a development IPv4 pool

Follow the steps in this section to create a development pool within your Regional pool. If you need only a top-level and Regional pool, and don't need development pools, skip to [Allocate CIDRs](#).

The following example shows the hierarchy of the pool structure that you can create with the instructions in this guide. At this step, you are creating a development IPAM pool:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Private scope
 - Top-level pool (10.0.0.0/8)

- Regional pool in Amazon Region 1 (10.0.0.0/16)
 - **Development pool for non-production VPCs (10.0.0.0/24)**
 - Allocation for a VPC (10.0.1.0/25)

In the preceding example, the CIDRs that are used are examples only. They illustrate that each pool within the top-level pool is provisioned with a portion of the top-level CIDR.

Amazon Management Console

To create a development pool within a Regional pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose **Create pool**.
4. Under **IPAM scope**, choose the same scope that you used when you created the top-level and Regional pools. For more information about scopes, see [How IPAM works](#).
5. (Optional) Add a **Name tag** for the pool and a description for the pool.
6. Under **Source**, choose **IPAM pool**. Then choose the Regional pool.
7. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
8. (Optional) Choose a CIDR to provision for the pool. You can only provision a CIDR that was provisioned to the top-level pool. You can create a pool without a CIDR, but you won't be able to use the pool for allocations until you've provisioned a CIDR for it. You can add CIDRs to a pool at any time by editing the pool.
9. You have the same allocation rule options here as you did when you created the top-level and Regional pool. See [Create a top-level IPv4 pool](#) for an explanation of the options that are available when you create pools. The allocation rules for the pool are not inherited from the pool above it in the hierarchy. If you do not apply any rules here, no allocation rules will be set for the pool.
10. (Optional) Choose **Tags** for the pool.
11. When you've finished configuring your pool, choose **Create pool**.
12. See [Allocate CIDRs](#).

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create a Regional pool in your IPAM:

1. Get the ID of the scope that you want to create the pool in: [describe-ipam-scopes](#)
2. Get the ID of the pool that you want to create the pool in: [describe-ipam-pools](#)
3. Create the pool: [create-ipam-pool](#)
4. View the new pool: [describe-ipam-pools](#)

Repeat these steps to create additional development pools within the Regional pool, as needed.

Create IPv6 pools

Follow the steps in this section to create an IPAM IPv6 pool hierarchy. When you create the pool, you can provision a CIDR for the pool to use. The pool assigns space within that CIDR to allocations within the pool. An allocation is a CIDR assignment from an IPAM pool to another resource or IPAM pool.

The following example shows the hierarchy of the pool structure that you can create with instructions in this guide. In this section, you are creating an IPv6 IPAM pool hierarchy:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Public scope
 - Regional pool in Amazon Region 1 (2001:db8::/52)
 - Development pool (2001:db8::/54)
 - Allocation for a VPC (2001:db8::/56)

Contents

- [Create a Regional IPv6 pool](#)
- [Create a development IPv6 pool](#)

Create a Regional IPv6 pool

Follow the steps in this section to create an IPv6 regional IPAM pool. When you provision an Amazon-provided IPv6 CIDR block to a pool, it must be provisioned to a pool with a locale (Amazon Region) selected. When you create the pool, you can provision a CIDR for the pool to use or add it later. You then assign that space to an allocation. An allocation is a CIDR assignment from an IPAM pool to another IPAM pool or to a resource.

The following example shows the hierarchy of the pool structure that you can create with instructions in this guide. At this step, you are creating the IPv6 regional IPAM pool:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Public scope
 - **Regional pool in Amazon Region 1 (2001:db8::/52)**
 - Development pool (2001:db8::/54)
 - Allocation for a VPC (2001:db8::/56)

In the preceding example, the CIDRs that are used are examples only. They illustrate that each pool within the IPv6 regional pool is provisioned with a portion of the IPv6 regional CIDR.

When you create an IPAM pool, you can configure rules for the allocations that are made within the IPAM pool.

Allocation rules enable you to configure the following:

- The required netmask length for allocations within the pool
- The required tags for resources within the pool
- The required locale for resources within the pool. The locale is the Amazon Region where an IPAM pool is available for allocations.

Allocation rules determine whether resources are compliant or noncompliant. For additional information about compliance, see [Monitor CIDR usage by resource](#).

Important

There is an additional implicit rule that is not displayed in the allocation rules. If the resource is in an IPAM pool that is a shared resource in Amazon Resource Access Manager

(RAM), the resource owner must be configured as a principal in Amazon RAM. For more information about sharing pools with RAM, see [Share an IPAM pool using Amazon RAM](#).

The following example shows how you might use allocation rules to control access to an IPAM pool:

Example

When you create your pools based on routing and security needs, you might want to allow only certain resources to use a pool. In such cases, you can set an allocation rule stating that any resource that wants a CIDR from this pool must have a tag that matches the allocation rule tag requirements. For example, you could set an allocation rule stating that only VPCs with the tag *prod* can get CIDRs from an IPAM pool.

Important

This topic covers how to create an IPv6 regional pool with either an IP address range provided by Amazon. If you want to bring your own IPv4 or IPv6 IP address ranges to Amazon (BYOIP), there are prerequisites. For more information, see [Tutorial: Bring your IP addresses to IPAM](#).

Amazon Management Console

To create a pool


1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose **Create pool**.
4. Under **IPAM scope**, choose the public scope. For more information about scopes, see [How IPAM works](#).

By default, when you create a pool, the default private scope is selected. Pools in the private scope must be IPv4 pools. Pools in the public scope can be IPv4 or IPv6 pools. The public scope is intended for all space that can be or is currently advertised by Amazon to the internet.

5. (Optional) Add a **Name tag** for the pool and a description for the pool.
6. Under **Source**, choose **IPAM scope**.

7. For **Address family**, select **IPv6**. The toggle **Allow CIDRs in this pool to be publicly advertisable** appears. By default, all CIDRs in this pool will be publicly advertisable. You cannot enable or disable this option.
8. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
9. Choose the **Locale** for the pool. When you provision an Amazon-provided IPv6 CIDR block to a pool, it must be provisioned to a pool with a locale (Amazon Region) selected. Choosing a locale ensures there are no cross-region dependencies between your pool and the resources allocating from it. The available options come from the operating Regions that you chose for the IPAM when you created it. You can add additional operating Regions at any time.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

 **Note**

If you are creating a pool in the Free Tier, you can only choose the locale that matches the home Region of your IPAM. To use all IPAM features across locales, [upgrade to the Advanced Tier](#).

10. Under **Service**, choose **EC2 (EIP/VPC)**. The service you select determines the Amazon service where the CIDR will be advertisable. Currently, the only option is **EC2 (EIP/VPC)**, which means that the CIDRs allocated from this pool will be advertisable for the Amazon EC2 service (for Elastic IP addresses) and the Amazon VPC service (for CIDRs associated with VPCs).
11. Under **Public IP source** option, choose **Amazon owned** to have Amazon provide an IPv6 address range for this pool. As noted at the top of this page, this topic covers how to create an IPv6 regional pool with an IP address range provided by Amazon. If you want to bring your own IPv4 or IPv6 address range to Amazon (BYOIP), there are prerequisites. For more information, see [Tutorial: Bring your IP addresses to IPAM](#).

12. For pools in the public scope that use the public IP source BYOIP, you can control if Amazon can publicly advertise the CIDRs in this pool with **Allow CIDRs in this pool to be publicly advertisable**. By default this option is enabled. Disable this option if you don't want to allow Amazon to publicly advertise CIDRs in this pool.
13. (Optional) You can create a pool without a CIDR, but you won't be able to use the pool for allocations until you've provisioned a CIDR for it. To provision a CIDR, choose **Add Amazon-owned CIDR** and choose the netmask size between /40 and /52 for the CIDR.

 **Note**

Note the following:

- By default, you can add one Amazon-provided IPv6 CIDR block to the Regional pool. For information on increasing the default limit, see [Quotas for your IPAM](#).
- When you choose a netmask length in the dropdown menu, you see the netmask length as well as the number of /56 CIDRs that the netmask represents.

14. Choose optional allocation rules for this pool:
 - **Minimum netmask length:** The minimum netmask length required for CIDR allocations in this IPAM pool to be compliant and the largest size CIDR block that can be allocated from the pool. The minimum netmask length must be less than the maximum netmask length. Possible netmask lengths for IPv6 addresses are 0 - 128.
 - **Default netmask length:** A default netmask length for allocations added to this pool. For example, if the CIDR that's provisioned to this pool is 2001:db8::/52 and you enter 56 here, any new allocations in this pool will default to a netmask length of /56.
 - **Maximum netmask length:** The maximum netmask length that will be required for CIDR allocations in this pool. This value dictates the smallest size CIDR block that can be allocated from the pool. For example, if you enter /56 here, the smallest netmask length that can be allocated for CIDRs from this pool is /56.
 - **Tagging requirements:** The tags that are required for resources to allocate space from the pool. If the resources have their tags changed after they have allocated space or if the allocation tagging rules are changed on the pool, the resource may be marked as noncompliant.
 - **Locale:** The locale that will be required for resources that use CIDRs from this pool. Automatically imported resources that do not have this locale will be marked

noncompliant. Resources that are not automatically imported into the pool will not be allowed to allocate space from the pool unless they are in this locale.

15. (Optional) Choose **Tags** for the pool.
16. Choose **Create pool**.
17. See [Create a development IPv6 pool](#).

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create or edit an IPv6 regional pool in your IPAM:

1. Create a pool: [create-ipam-pool](#).
2. Edit the pool after you create it to modify the allocation rules: [modify-ipam-pool](#).

Create a development IPv6 pool

Follow the steps in this section to create a development pool within your IPv6 Regional pool. If you only need a Regional pool and don't need development pools, skip to [Allocate CIDRs](#).

The following example shows the hierarchy of the pool structure that you can create with the instructions in this guide. At this step, you are creating a development IPAM pool:

- IPAM operating in Amazon Region 1 and Amazon Region 2
 - Public scope
 - Regional pool in Amazon Region 1 (2001:db8::/52)
 - **Development pool (2001:db8::/54)**
 - Allocation for a VPC (2001:db8::/56)

In the preceding example, the CIDRs that are used are examples only. They illustrate that each pool within the top-level pool is provisioned with a portion of the top-level CIDR.

Amazon Management Console

To create a development pool within an IPv6 Regional pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose **Create pool**.
4. Under **IPAM scope**, choose the public scope. For more information about scopes, see [How IPAM works](#).

By default, when you create a pool, the default private scope is selected. Pools in the private scope must be IPv4 pools. Pools in the public scope can be IPv4 or IPv6 pools. The public scope is intended for all space that can be or is currently advertised by Amazon to the internet.

5. (Optional) Add a **Name tag** for the pool and a description for the pool.
6. Under **Source**, choose **IPAM pool**. Then, under **Source pool**, choose the IPv6 Regional pool.
7. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
8. (Optional) Choose a CIDR to provision for the pool. You can only provision a CIDR that was provisioned to the top-level pool. You can create a pool without a CIDR, but you won't be able to use the pool for allocations until you've provisioned a CIDR for it. You can add CIDRs to a pool at any time by editing the pool.
9. You have the same allocation rule options here as you did when you created the IPv6 Regional pool. See [Create a Regional IPv6 pool](#) for an explanation of the options that are available when you create pools. The allocation rules for the pool are not inherited from the pool above it in the hierarchy. If you do not apply any rules here, no allocation rules will be set for the pool.
10. (Optional) Choose **Tags** for the pool.
11. When you've finished configuring your pool, choose **Create pool**.
12. See [Allocate CIDRs](#).

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create an IPv6 Regional pool in your IPAM:

1. Get the ID of the scope that you want to create the pool in: [describe-ipam-scopes](#)
2. Get the ID of the pool that you want to create the pool in: [describe-ipam-pools](#)
3. Create the pool: [create-ipam-pool](#)
4. View the new pool: [describe-ipam-pools](#)

Repeat these steps to create additional development pools within the IPv6 Regional pool, as needed.

Allocate CIDRs

Follow the steps in this section to allocate a CIDR from an IPAM pool to a resource.

Note

The terms *provision* and *allocate* are used throughout this user guide and the IPAM console. *Provision* is used when you add a CIDR to an IPAM pool. *Allocate* is used when you associate a CIDR from an IPAM pool with a resource.

You can allocate CIDRs from an IPAM pool in the following ways:

- Use an Amazon service that's integrated with IPAM, such as Amazon VPC, and select the option to use an IPAM pool for the CIDR. IPAM automatically creates the allocation in the pool for you.
- Manually allocate a CIDR within an IPAM pool to reserve it for later use with an Amazon service that's integrated with IPAM, such as Amazon VPC.

This section walks you through both options: how to use the Amazon services integrated with IPAM to provision an IPAM pool CIDR, and how to manually reserve IP address space.

Contents

- [Create a VPC that uses an IPAM pool CIDR](#)
- [Manually allocate a CIDR to a pool to reserve IP address space](#)

Create a VPC that uses an IPAM pool CIDR

Follow the steps in [Creating a VPC](#) in the *Amazon VPC User Guide*. When you reach the step to choose a CIDR for the VPC, you will have an option to use a CIDR from an IPAM pool.

If you choose the option to use an IPAM pool when you create the VPC, Amazon allocates a CIDR in the IPAM pool. You can view the allocation in IPAM by choosing a pool in the content pane of the IPAM console and viewing the Resources tab for the pool.

Note

For complete instructions using the Amazon CLI, including creating a VPC, see the [Tutorials for Amazon VPC IP Address Manager](#) section.

Manually allocate a CIDR to a pool to reserve IP address space

Follow the steps in this section to manually allocate a CIDR to a pool. You might do this in order to reserve a CIDR within an IPAM pool for later use. You can also reserve space in your IPAM pool to represent an on-premises network. IPAM will manage that reservation for you and indicate if any CIDRs overlap with your on-premises IP space.

Amazon Management Console

To manually allocate a CIDR

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. In the content pane, choose a pool.
5. Choose **Actions > Create custom allocation**.

6. Choose whether to add a specific CIDR to allocate (for example, `10.0.0.0/24` for IPv4 or `2001:db8::/52` for IPv6) or add a CIDR by size by choosing the netmask length only (for example, `/24` for IPv4 or `/52` for IPv6).
7. Choose **Allocate**.
8. You can view the allocation in IPAM by choosing **Pools** in the navigation pane, choosing a pool, and viewing the **Allocations** tab for the pool.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to manually allocate a CIDR to a pool:

1. Get the ID of the IPAM pool that you want to create the allocation in: [describe-ipam-pools](#).
2. Create the allocation: [allocate-ipam-pool-cidr](#).
3. View the allocation: [get-ipam-pool-allocations](#).

To release a manually allocated CIDR, see [Release an allocation](#).

Managing IP address space in IPAM

The tasks in this section are optional. If you want to complete the tasks in this section, and you have delegated an IPAM account, the tasks should be completed by the IPAM administrator.

Follow the steps in this section to manage your IP address space in IPAM.

Contents

- [Enforce IPAM use for VPC creation](#)
- [Share an IPAM pool using Amazon RAM](#)
- [Provision CIDRs to a pool](#)
- [Deprovision CIDRs from a pool](#)
- [Edit a pool](#)
- [Delete a pool](#)
- [Work with resource discoveries](#)
- [Create additional scopes](#)
- [Move VPC CIDRs between scopes](#)
- [Change the monitoring state of VPC CIDRs](#)
- [Delete a scope](#)
- [Release an allocation](#)
- [Modify an IPAM](#)
- [Delete an IPAM](#)

Enforce IPAM use for VPC creation

Note

This section is only applicable to you if you've enabled IPAM to integrate with Amazon Organizations. For more information, see [Integrate IPAM with accounts in an Amazon Organization](#).

This section describes how to create a service control policy in Amazon Organizations that requires members in your organization to use IPAM when they create a VPC. Service control policies (SCPs)

are a type of organization policy that enable you to manage permissions in your organization. For more information, see [Service control policies](#) in the *Amazon Organizations User Guide*.

Enforce IPAM when creating VPCs

Follow the steps in this section to require members in your organization to use IPAM when creating VPCs.

To create an SCP and restrict VPC creation to IPAM

1. Follow the steps in [Creating an SCP](#) in the *Amazon Organizations User Guide* and enter the following text in the JSON editor:

```
{
  "Version": "2012-10-17",
  "Statement": [{
    "Effect": "Deny",
    "Action": ["ec2:CreateVpc", "ec2:AssociateVpcCidrBlock"],
    "Resource": "arn:aws:ec2:*:*:vpc/*",
    "Condition": {
      "Null": {
        "ec2:Ipv4IpamPoolId": "true"
      }
    }
  }]
}
```

2. Attach the policy to one or more organizational units in your organization. For more information, see [Attaching and detaching service control policies](#) in the *Amazon Organizations User Guide*.

Enforce an IPAM pool when creating VPCs

Follow the steps in this section to require members in your organization to use a specific IPAM pool when creating VPCs.

To create an SCP and restrict VPC creation to an IPAM pool

1. Follow the steps in [Creating an SCP](#) in the *Amazon Organizations User Guide* and enter the following text in the JSON editor:

```
{
  "Version": "2012-10-17",
  "Statement": [{
    "Effect": "Deny",
    "Action": ["ec2:CreateVpc", "ec2:AssociateVpcCidrBlock"],
    "Resource": "arn:aws:ec2:*:*:vpc/*",
    "Condition": {
      "StringNotEquals": {
        "ec2:Ipv4IpamPoolId": "ipam-pool-0123456789abcdefg"
      }
    }
  }]
}
```

2. Change the `ipam-pool-0123456789abcdefg` example value to the IPv4 pool ID you would like to restrict users to.
3. Attach the policy to one or more organizational units in your organization. For more information, see [Attaching and detaching service control policies](#) in the *Amazon Organizations User Guide*.

Enforce IPAM for all but a given list of OUs

Follow the steps in this section to enforce IPAM for all but a given list of Organizational Units (OUs). The policy described in this section requires OUs in the organization *except for* the OUs that you specify in `aws:PrincipalOrgPaths` to use IPAM to create and expand VPCs. The listed OUs can either use IPAM when creating VPCs or specify an IP address range manually.

To create an SCP and enforce IPAM for all but a given list of OUs

1. Follow the steps in [Creating an SCP](#) in the *Amazon Organizations User Guide* and enter the following text in the JSON editor:

```
{
  "Version": "2012-10-17",
  "Statement": [{
    "Effect": "Deny",
    "Action": ["ec2:CreateVpc", "ec2:AssociateVpcCidrBlock"],
    "Resource": "arn:aws:ec2:*:*:vpc/*",
    "Condition": {
      "Null": {
```

```
    "ec2:Ipv4IpamPoolId": "true"
  },
  "ForAllValues:StringNotLike": {
    "aws:PrincipalOrgPaths": [
      "o-a1b2c3d4e5/r-ab12/ou-ab12-11111111/ou-ab12-22222222/",
      "o-a1b2c3d4e5/r-ab12/ou-ab13-22222222/ou-ab13-33333333/"
    ]
  }
}]]
}
```

2. Remove the example values (like `o-a1b2c3d4e5/r-ab12/ou-ab12-11111111/ou-ab12-22222222/`) and add the Amazon Organizations entity paths of the OUs that you want to have the option (but not require) to use IPAM. For more information about entity path, see [Understand the Amazon Organizations entity path](#) and [aws:PrincipalOrgPaths](#) in the *Amazon Identity and Access Management User Guide*.
3. Attach the policy to your organization root. For more information, see [Attaching and detaching service control policies](#) in the *Amazon Organizations User Guide*.

Share an IPAM pool using Amazon RAM

Follow the steps in this section to share an IPAM pool using Amazon Resource Access Manager (RAM). When you share an IPAM pool with RAM, “principals” can allocate CIDRs from the pool to Amazon resources, such as VPCs, from their respective accounts. A principal is a concept in RAM that means any Amazon account, IAM role or organizational unit in Amazon Organizations. For more information, see [Sharing your Amazon resources](#) in the *Amazon RAM User Guide*.

Note

- You can only share an IPAM pool with Amazon RAM if you've integrated IPAM with Amazon Organizations. For more information, see [Integrate IPAM with accounts in an Amazon Organization](#). You cannot share an IPAM pool with Amazon RAM if you are a single account IPAM user.
- You must enable resource sharing with Amazon Organizations in Amazon RAM. For more information, see [Enable resource sharing within Amazon Organizations](#) in the *Amazon RAM User Guide*.

- RAM sharing is only available in the home Amazon Region of your IPAM. You must create the share in the Amazon Region that the IPAM is in, not in the Region of the IPAM pool.
- The account that creates and deletes IPAM pool resource shares must have the following permissions in the IAM policy attached to their IAM role:
 - `ec2:PutResourcePolicy`
 - `ec2>DeleteResourcePolicy`
- You can add multiple IPAM pools to a RAM share.

Amazon Management Console

To share an IPAM pool using RAM

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. In the content pane, choose the pool you want to share and choose **Actions** > **View details**.
5. Under **Resource sharing**, choose **Create resource share**. As a result, the Amazon RAM console opens. You'll create the shared pool in Amazon RAM.
6. Choose **Create a resource share**.
7. Add a **Name** for the shared resource.
8. Under **Select resource type**, select IPAM pools and choose one or more IPAM pools.
9. Choose **Next**.
10. Choose one of the permissions for the resource share:
 - **AWSRAMDefaultPermissionsIpamPool**: Choose this permission to allow principals to view the CIDRs and allocations in the shared IPAM pool and allocate/release CIDRs in the pool.
 - **AWSRAMPermissionIpamPoolByoipCidrImport**: Choose this permission to allow principals to import BYOIP CIDRs into the shared IPAM pool. You will need this permission only if you have existing BYOIP CIDRs and you want to import them to IPAM and share them with principals. For additional information on BYOIP CIDRs to IPAM, see [Tutorial: Transfer a BYOIP IPv4 CIDR to IPAM](#).

11. Choose the principals that are allowed to access this resource. If principals will be importing existing BYOIP CIDRs to this shared IPAM pool, add the BYOIP CIDR owner account as principal.
12. Review the resource share options and the principals you'll be sharing with and choose **Create**.

Command line

The command(s) in this section link to the Amazon CLI Reference documentation. There you'll find detailed descriptions of the options you can use when you run the command(s).

Use the following Amazon CLI commands to share an IPAM pool using RAM:

1. Get the ARN of the IPAM: [describe-ipam-pools](#)
2. Create the resource share: [create-resource-share](#)
3. View the resource share: [get-resource-shares](#)

As a result of creating the resource share in RAM, other principals can now allocate CIDRs to resources using the IPAM pool. For information on monitoring resources created by principals, see [Monitor CIDR usage by resource](#). For more information on how to create a VPC and allocate a CIDR from a shared IPAM pool, see [Creating a VPC](#) in the *Amazon VPC User Guide*.

Provision CIDRs to a pool

Follow the steps in this section to provision CIDRs to a pool. If you already provisioned a CIDR when you created the pool, you might need to provision additional CIDRs if a pool is nearing full allocation. To monitor pool usage, see [Monitor CIDR usage with the IPAM dashboard](#).

Note

The terms *provision* and *allocate* are used throughout this user guide and the IPAM console. *Provision* is used when you add a CIDR to an IPAM pool. *Allocate* is used when you associate a CIDR from an IPAM pool with a VPC or Elastic IP address.

Amazon Management Console

To provision CIDRs to a pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. In the content pane, choose the pool that you want to add a CIDR to.
5. Choose **Actions > Provision CIDRs**.
6. Enter the CIDR that you want to add, and then choose **Add new CIDR** for additional CIDRs.

Note

- By default, you can add one Amazon-provided IPv6 CIDR block to a Regional pool. For information on increasing the default limit, see [Quotas for your IPAM](#).
- The CIDR you want to provision must be available in the scope.
- If you are provisioning CIDRs to a pool within a pool, then the CIDR space you want to provision must be available in the pool.

7. Choose **Request provisioning**.
8. You can view the CIDR in IPAM by choosing **Pools** in the navigation pane, choosing a pool, and viewing the CIDRs tab for the pool.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to provision CIDRs to a pool:

1. Get the ID of an IPAM pool: [describe-ipam-pools](#)
2. Get the CIDRs that are provisioned to the pool: [get-ipam-pool-cidrs](#)
3. Provision a new CIDR to the pool: [provision-ipam-pool-cidr](#)

4. Get the CIDRs that are provisioned to the pool and view the new CIDR: [get-ipam-pool-cidrs](#)

Deprovision CIDRs from a pool

Follow the steps in this section to deprovision CIDRs from an IPAM pool. When you deprovision all pool CIDRs, the pool can no longer be used for allocations. You must first provision a new CIDR to the pool before you can use the pool for allocations.

Important

You cannot deprovision the CIDR if there are allocations in the pool. To remove allocations, see [Release an allocation](#).

Amazon Management Console

To deprovision a pool CIDR

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. From the dropdown menu at the top of the content pane, choose the scope that you want to use. For more information about scopes, see [How IPAM works](#).
4. In the content pane, choose the pool whose CIDRs you want to deprovision.
5. Choose the **CIDRs** tab.
6. Select one or more CIDRs and choose **Deprovision CIDRs**.
7. Choose **Deprovision CIDR**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to deprovision a pool CIDR:

1. Get an IPAM pool ID: [describe-ipam-pools](#)

2. View your current CIDRs for the pool: [get-ipam-pool-cidrs](#)
3. Deprovision CIDRs: [deprovision-ipam-pool-cidr](#)
4. View your updated CIDRs: [get-ipam-pool-cidrs](#)

To provision a new CIDR to the pool, see [Deprovision CIDRs from a pool](#). If you want to delete the pool, see [Delete a pool](#).

Edit a pool

Follow the steps in this section to edit an IPAM pool. You may want to edit a pool to change the allocation rules in the pool. For more information about allocation rules, see [Create a top-level IPv4 pool](#).

Amazon Management Console

To edit a pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#)
4. In the content pane, choose the pool whose CIDR you want to edit.
5. Choose **Actions > Edit**.
6. Make any changes you need to the pools. For information about pool configuration options, see [Create a top-level IPv4 pool](#).
7. Choose **Update**.

Command line

Use the following Amazon CLI commands to edit a pool:

1. Get an IPAM pool ID: [describe-ipam-pools](#)
2. Modify the pool: [modify-ipam-pool](#)

Delete a pool

Follow the steps in this section to delete an IPAM pool.

Important

You cannot delete an IP address pool if there are allocations in it. You must first release the allocations and [Deprovision CIDRs from a pool](#) before you can delete the pool.

Amazon Management Console

To delete a pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. From the dropdown menu at the top of the content pane, choose the scope that you want to use. For more information about scopes, see [How IPAM works](#).
4. In the content pane, choose the pool whose CIDR you want to delete.
5. Choose **Actions > Delete pool**.
6. Enter **delete** and then choose **Delete**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to delete a pool:

1. View pools and get an IPAM pool ID: [describe-ipam-pools](#)
2. Delete a pool: [delete-ipam-pool](#)
3. View your pools: [describe-ipam-pools](#)

To create a new pool, see [Create a top-level IPv4 pool](#).

Work with resource discoveries

A resource discovery is an IPAM component that enables IPAM to manage and monitor resources that belong to the owning account. A resource discovery is created by default when you create an IPAM. You can also create a resource discovery independently of an IPAM and integrate it with an IPAM owned by another account or organization. If the resource discovery owner is the delegated administrator of an organization, IPAM will monitor resources for all members of the organization.

Note

Creating, sharing, and associating resource discoveries is part of the process of integrating IPAM with accounts outside of your organizations (see [Integrate IPAM with accounts outside of your organization](#)). If you are not creating an IPAM and integrating it with accounts outside your organization, you do not need to create, share, or associate resource discoveries.

Contents

- [Create a resource discovery](#)
- [View resource discovery details](#)
- [Share a resource discovery](#)
- [Associate a resource discovery with an IPAM](#)
- [Disassociate a resource discovery](#)
- [Delete a resource discovery](#)

Create a resource discovery

This section describes how to create a resource discovery. A resource discovery is created by default when you create an IPAM. The default quota for resource discoveries per Region is 1. For more information about IPAM quotas, see [Quotas for your IPAM](#).

Note

Creating, sharing, and associating resource discoveries is part of the process of integrating IPAM with accounts outside of your organizations (see [Integrate IPAM with accounts](#)

[outside of your organization](#)). If you are not creating an IPAM and integrating it with accounts outside your organization, you do not need to create, share, or associate resource discoveries.

If you are integrating an IPAM with accounts outside of your organizations, this is a required step that must be completed by the **Secondary Org Admin Account**. For more information about the roles involved in this process, see [Process overview](#).

Amazon Management Console

To create a resource discovery

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Resource discoveries**.
3. Choose **Create resource discovery**.
4. Select **Allow Amazon VPC IP Address Manager to replicate data from source account(s) into the IPAM delegate account**. If you do not select this option, you cannot create a resource discovery.
5. (Optional) Add a **Name** tag to the resource discovery. A tag is a label that you assign to an Amazon resource. Each tag consists of a key and an optional value. You can use tags to search and filter your resources or track your Amazon costs.
6. (Optional) Add a description.
7. Under **Operating regions**, select the Amazon Regions in which resources will be discovered. The current Region will automatically be set as one of the operating Regions. If you're creating the resource discovery so that you can share it with an IPAM in operating Region us-east-1, make sure you select us-east-1 here. If you forget an operating Region, you can return at a later time and edit your resource discovery settings.

Note

In most cases, the resource discovery should have the same operating Regions as the IPAM or you will only get resource discovery in that one Region.

8. (Optional) Choose any additional **Tags** for the pool.
9. Choose **Create**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- Create a resource discovery: [create-ipam-resource-discovery](#)

View resource discovery details

This section describes how to view the details for a resource discovery. These include the resource CIDRs and discovery statuses of accounts monitored under your resource discovery.

Amazon Management Console

To view resource discovery details

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Resource discoveries**.
3. Choose a resource discovery.
4. Under **Resource discovery details**, view details related to the resource discovery, such as **Default**, which indicates whether the resource discovery is the default. The default resource discovery is the resource discovery automatically created when you create an IPAM.
5. In the tabs, view the details of a resource discovery:
 - **Discovered resources** - Resources monitored under a resource discovery. IPAM monitors CIDRs from the following resource types VPCs, Public IPv4 pools, VPC subnets, and Elastic IP addresses.
 - **Name (Resource ID)** – Resource discovery ID.
 - **IP usage** – The percentage of IP address space in use. To convert the decimal to a percentage, multiply the decimal by 100. Note the following –
 - For resources that are VPCs, this is the percentage of IP address space in the VPC that's taken up by subnet CIDRs.
 - For resources that are subnets, if the subnet has an IPv4 CIDR provisioned to it, this is the percentage of IPv4 address space in the subnet that's in use. If the subnet has an IPv6 CIDR provisioned to it, the percentage of IPv6 address space in use is

not represented. The percentage of IPv6 address space in use cannot currently be calculated.

- For resources that are public IPv4 pools, this is the percentage of IP address space in the pool that's been allocated to Elastic IP addresses (EIPs).
- **CIDR** – Resource CIDR.
- **Region** – Resource Region.
- **Owner ID** – Resource owner ID.
- **Sample time** – The last successful resource discovery time.
- **Discovered accounts:** Amazon accounts being monitored under a resource discovery. If you have integrated IPAM with Amazon Organizations, all accounts in the organization are discovered accounts.
 - **Account ID** – The account ID.
 - **Region** – The Amazon Region that the account information is returned from.
 - **Last attempted discovery time** – The last attempted resource discovery time.
 - **Last successful discovery time** – The last successful resource discovery time.
 - **Status** – Resource discovery failure reason.
- **Operating regions** – The operating Regions for the resource discovery.
- **Resource sharing** – If the resource discovery has been shared, the resource share ARN is listed.
 - **Resource share ARN** – Resource share ARN.
 - **Status** – The current status of the resource share. Possible values are:
 - **Active** – Resource share is active and available for use.
 - **Deleted** – Resource share is deleted and is no longer available for use.
 - **Pending** – An invitation to accept the resource share is waiting for a response.
 - **Created at** – When the resource share was created.
- **Tags** – A tag is a label that you assign to an Amazon resource. Each tag consists of a key and an optional value. You can use tags to search and filter your resources or track your Amazon costs.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- View resource discovery details: [describe-ipam-resource-discovery](#)

Share a resource discovery

Follow the steps in this section to share a resource discovery using Amazon Resource Access Manager. For more information about Amazon RAM, see [Sharing your Amazon resources](#) in the *Amazon RAM User Guide*.

Note

Creating, sharing, and associating resource discoveries is part of the process of integrating IPAM with accounts outside of your organizations (see [Integrate IPAM with accounts outside of your organization](#)). If you are not creating an IPAM and integrating it with accounts outside your organization, you do not need to create, share, or associate resource discoveries.

When you create an IPAM that monitors accounts outside your organization, the Secondary Org Admin Account shares their resource discovery with the Primary Org IPAM Account using Amazon RAM. You must first share a resource discovery with the Primary Org IPAM Account before the Primary Org IPAM Account can associate the resource discovery with their IPAM. For more information about the roles involved in this process, see [Process overview](#).

Note

- When you create a resource share using Amazon RAM to share a resource discovery, you must create the resource share in the home Region of the Primary Org IPAM.
- The account that creates and deletes a resource share for a resource discovery must have the following permissions in their IAM policy:
 - `ec2:PutResourcePolicy`

- ec2:DeleteResourcePolicy

If you are integrating an IPAM with accounts outside of your organizations, this is a required step that must be completed by the **Secondary Org Admin Account**.

Amazon Management Console

To share a resource discovery

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Resource discoveries**.
3. Choose the **Resource sharing** tab.
4. Choose **Create resource share**. The Amazon RAM console opens, which is where you will create the resource share.
5. In the Amazon RAM console, choose **Settings**.
6. Choose **Enable sharing with Amazon Organizations**, and then choose **Save settings**.
7. Choose **Create a resource share**.
8. Add a **Name** for the shared resource.
9. Under **Select resource type**, select **IPAM Resource Discovery**, and choose the resource discovery.
10. Choose **Next**.
11. Under **Associate permissions**, you can view the default permission that will be enabled for principals that are granted access to this resource share:
 - AWSRAMPermissionIpamResourceDiscovery
 - Actions allowed by this permission:
 - ec2:AssociateIpamResourceDiscovery
 - ec2:GetIpamDiscoveredAccounts
 - ec2:GetIpamDiscoveredPublicAddresses
 - ec2:GetIpamDiscoveredResourceCidrs
12. Specify the principals that are allowed access to the shared resource. For **Principals**, choose the Primary Org IPAM Account, and then choose **Add**.
13. Choose **Next**.

14. Review the resource share options and the principals that you'll be sharing with. Then choose **Create resource share**.
15. After a resource discovery is shared, it must be accepted by the Primary Org IPAM Account and then associated with an IPAM by the Primary Org IPAM Account. For more information, see [Associate a resource discovery with an IPAM](#).

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

1. Create the resource share: [create-resource-share](#)
2. View the resource share: [get-resource-shares](#)

Associate a resource discovery with an IPAM

This section describes how to associate a resource discovery with an IPAM. When you associate a resource discovery with an IPAM, the IPAM monitors all resources CIDRs and accounts discovered under the resource discovery. When you create an IPAM, a default resource discovery is created for your IPAM and automatically associated with your IPAM.

The default quota for resource discovery associations is 5. For more information (including how to adjust this quota), see [Quotas for your IPAM](#).

Note

Creating, sharing, and associating resource discoveries is part of the process of integrating IPAM with accounts outside of your organizations (see [Integrate IPAM with accounts outside of your organization](#)). If you are not creating an IPAM and integrating it with accounts outside your organization, you do not need to create, share, or associate resource discoveries.

If you are integrating an IPAM with accounts outside of your organizations, this is a required step that must be completed by the **Primary Org IPAM Account**. For more information about the roles involved in this process, see [Process overview](#).

Amazon Management Console

To associate a resource discovery

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **IPAMs**.
3. Select **Associated discoveries**, and then choose **Associate resource discoveries**.
4. Under **IPAM resource discoveries**, choose a resource discovery that's been shared with you by the **Secondary Org Admin Account**.
5. Choose **Associate**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- Associate a resource discovery: [associate-ipam-resource-discovery](#)

Disassociate a resource discovery

This section describes how to disassociate a resource discovery from an IPAM. When you disassociate a resource discovery from an IPAM, the IPAM no longer monitors all resources CIDRs and accounts discovered under the resource discovery.

Note

You cannot disassociate a default resource discovery association. A default resource discovery association is one that is created automatically when you create an IPAM. The default resource discovery association is deleted, however, if you delete the IPAM.

This step must be completed by the **Primary Org IPAM Account**. For more information about the roles involved in this process, see [Process overview](#).

Amazon Management Console

To disassociate a resource discovery

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **IPAMs**.
3. Select **Associated discoveries**, and then choose **Disassociate resource discoveries**.
4. Under **IPAM resource discoveries**, choose a resource discovery that's been shared with you by the **Secondary Org Admin Account**.
5. Choose **Disassociate**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- To disassociate a resource discovery: [disassociate-ipam-resource-discovery](#)

Delete a resource discovery

This section describes how to delete a resource discovery.

Note

You cannot delete a default resource discovery. A default resource discovery is one that is created automatically when you create an IPAM. The default resource discovery is deleted, however, if you delete the IPAM.

This step must be completed by the **Secondary Org Admin Account**. For more information about the roles involved in this process, see [Process overview](#).

Amazon Management Console

To delete a resource discovery

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.

2. In the navigation pane, choose **Resource discoveries**.
3. Select a resource discovery and choose **Actions > Delete resource discovery**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- To delete a resource discovery: [delete-ipam-resource-discovery](#)

Create additional scopes

Follow the steps in this section to create an additional scope.

A scope is the highest-level container within IPAM. When you create an IPAM, IPAM creates two default scopes for you. Each scope represents the IP space for a single network. The private scope is intended for all private space. The public scope is intended for all public space. Scopes enable you to reuse IP addresses across multiple unconnected networks without causing IP address overlap or conflict.

When you create an IPAM, default scopes (one private and one public) are created for you. You can create additional private scopes. You cannot create additional public scopes.

You can create additional private scopes if you require support for multiple disconnected private networks. Additional private scopes allow you to create pools and manage resources that use the same IP space.

Important

If IPAM discovers resources with private IPv4 CIDRs, the resource CIDRs are imported into the default private scope and do not appear in any additional private scopes you create. You can move CIDRs from the default private scope to another private scope. For information, see [Move VPC CIDRs between scopes](#).

Amazon Management Console

To create an additional private scope

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Scopes**.
3. Choose **Create scope**.
4. Choose the IPAM that you want to add the scope to.
5. Add a description for the scope.
6. Choose **Create scope**.
7. You can view the scope in IPAM by choosing **Scopes** in the navigation pane.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to create an additional private scope:

1. View your current scopes: [describe-ipam-scopes](#)
2. Create a new private scope: [create-ipam-scope](#)
3. View your current scopes to view the new scope: [describe-ipam-scopes](#)

Move VPC CIDRs between scopes

Follow the steps in this section to move a VPC CIDR from one scope to another.

Important

- You can only move VPC CIDRs. When you move a VPC CIDR, the VPC's subnet CIDRs are moved automatically as well.
- You can only move VPC CIDRs from one private scope to another. You cannot move VPC CIDRs out of a public scope to a private scope or from a private scope to a public scope.
- The same Amazon account must own both scopes.

- If a VPC CIDR is currently allocated from a pool in a private scope, the move request succeeds, but the VPC CIDR will not be moved until you release the VPC CIDR allocation from the current pool. For information on releasing an allocation, see [Release an allocation](#).

Amazon Management Console

To move a CIDR allocated to a VPC

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Resources**.
3. From the dropdown menu at the top of the content pane, choose the scope you want to use.
4. In the content pane, choose a VPC and view the details of the VPC.
5. Under **VPC CIDRs**, select one of the CIDRs allocated to the resource and choose **Actions > Move CIDR to different scope**.
6. Select the scope you want to move the VPC CIDR to.
7. Choose **Move CIDR to different scope**.

Command line

Use the following Amazon CLI commands to move a VPC CIDR:

1. Get a VPC CIDR in current scope: [get-ipam-resource-cidrs](#)
2. Move a VPC CIDR: [modify-ipam-resource-cidr](#)
3. Get a VPC CIDR in the other scope: [get-ipam-resource-cidrs](#)

Change the monitoring state of VPC CIDRs

Follow the steps in this section to change the monitoring state of a VPC CIDR. You may want to change a VPC CIDR from monitored to ignored if you do not want IPAM to manage or monitor the VPC and allow the CIDR allocated to the VPC to be available for use. You may want to change a VPC CIDR from ignored to monitored if you want IPAM to manage and monitor the VPC CIDR.

Note

- You cannot ignore VPC CIDRs in the public scope.
- If a CIDR is ignored, you are still charged for the active IP addresses in the CIDR. For more information, see [Pricing for IPAM](#).
- If a CIDR is ignored, you can still view the history of IP addresses in the CIDR. For more information, see [View IP address history](#).

You can change the monitoring state of a VPC CIDR to monitored or ignored:

- **Monitored:** The VPC CIDR has been detected by IPAM and is being monitored for overlap with other CIDRs and allocation rule compliance.
- **Ignored:** The VPC CIDR has been chosen to be exempt from monitoring. Ignored VPC CIDRs are not evaluated for overlap with other CIDRs or Allocation rule compliance. Once a VPC CIDR is chosen to be ignored, any space allocated to it from an IPAM pool is returned to the pool and the VPC CIDR will not be imported again via auto-import (if the auto-import Allocation rule is set on the pool).

Amazon Management Console

To change the monitoring status of a CIDR allocated to a VPC

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Resources**.
3. From the dropdown menu at the top of the content pane, choose the private scope you want to use.
4. In the content pane, choose the VPC and view the details of the VPC.
5. Under **VPC CIDRs**, select one of the CIDRs allocated to the VPC and choose **Actions > Mark as ignored** or **Unmark as ignored**.
6. Choose **Mark as ignored** or **Unmark as ignored**.

Command line

Use the following Amazon CLI commands to change the monitoring state of a VPC CIDR:

1. Get a scope ID: [describe-ipam-scopes](#)
2. View the current monitoring state for the VPC CIDR: [get-ipam-resource-cidrs](#)
3. Change the state of the VPC CIDR: [modify-ipam-resource-cidr](#)
4. View the new monitoring state for the VPC CIDR: [get-ipam-resource-cidrs](#)

Delete a scope

Follow the steps in this section to delete an IPAM scope.

Important

You can't delete a scope if either of the following is true:

- The scope is a default scope. When you create an IPAM, two default scopes (one public, one private) are created automatically, and cannot be deleted. To see if a scope is a default scope, view the **Scope type** in the details of the scope.
- There are one or more pools in the scope. You must first [Delete a pool](#) before you can delete the scope.

Amazon Management Console

To delete a scope

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Scopes**.
3. In the content pane, choose the scope that you want to delete.
4. Choose **Actions > Delete scope**.
5. Enter **delete** and then choose **Delete**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to delete a scope:

1. View scopes: [describe-ipam-scopes](#)
2. Delete a scope: [delete-ipam-scope](#)
3. View updated scopes: [describe-ipam-scopes](#)

To create a new scope, see [Create additional scopes](#). To delete the IPAM, see [Delete an IPAM](#).

Release an allocation

Follow the steps in this section to release a CIDR allocation from an IPAM pool. An allocation is a CIDR assignment from an IPAM pool to another resource or IPAM pool.

If you are planning to delete a pool, you might need to release a pool allocation. You cannot delete pools if the pools have CIDRs provisioned, and you cannot deprovision CIDRs if the CIDRs are allocated to resources.

Note

- To release a manual allocation, use the steps in this section or call the [ReleaseIpamPoolAllocation API](#).
- To release an allocation in a private scope, you must ignore or delete the resource CIDR. For more information, see [Change the monitoring state of VPC CIDRs](#). After some time, Amazon VPC IPAM will automatically release the allocation on your behalf.

Example

Example

If you have a VPC CIDR in a private scope, to release the allocation you must either ignore or delete the VPC CIDR. After some time, Amazon VPC IPAM will automatically release the VPC CIDR allocation from the IPAM pool.

- To release an allocation in a public scope, you must delete the resource CIDR. You cannot ignore public resource CIDRs. For more information, see *Cleanup* in [Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI](#) or *Cleanup* in [Bring your own IPv6 CIDR to IPAM using only the Amazon CLI](#). After some time, Amazon VPC IPAM will automatically release the allocation on your behalf.

For Amazon VPC IPAM to release allocations on your behalf, all account permissions must be properly configured for either [single-account use](#) or [multi-account use](#).

When you release a CIDR that's managed by your IPAM, Amazon VPC IPAM recycles the CIDR back into an IPAM pool. It takes a few minutes for the CIDR to become available for future allocations. For more information about pools and allocations, see [How IPAM works](#).

Amazon Management Console

To release a pool allocation

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. From the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. In the content pane, choose the pool that the allocation is in.
5. Choose the **Allocations** tab.
6. Select one or more allocations. You can identify allocations by their **Resource type**:
 - **custom**: A custom allocation.
 - **vpc**: A VPC allocation.
 - **ipam-pool**: An IPAM pool allocation.
 - **ec2-public-ipv4-pool**: A public IPv4 pool allocation.
7. Choose **Actions > Release custom allocation**.
8. Choose **Deallocate CIDR**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to release a pool allocation:

1. Get an IPAM pool ID: [describe-ipam-pools](#)
2. View your current allocations in the pool: [get-ipam-pool-allocations](#)
3. Release an allocation: [release-ipam-pool-allocation](#)
4. View your updated allocations: [get-ipam-pool-allocations](#)

To add a new allocation, see [Allocate CIDRs](#). To delete the pool after releasing allocations, you must first [Deprovision CIDRs from a pool](#).

Modify an IPAM

Follow the steps in this section to modify an IPAM.

Contents

- [Modify IPAM tier](#)
- [Modify IPAM operating Regions](#)

Modify IPAM tier

Follow the steps in this section to modify the IPAM tier. IPAM offers two tiers: Free Tier and Advanced Tier. For more information about the features available in the Free Tier and the costs associated with the Advanced Tier, see the IPAM tab in the [Amazon VPC pricing page](#).

Important

Before you can switch from the Advanced Tier to the Free Tier, you must:

- Delete private scope pools.
- Delete non-default private scopes.
- Delete pools with locales different than the IPAM home Region.
- Delete non-default resource discovery associations.
- Delete pool allocations to accounts that are not the IPAM owner.

Amazon Management Console

To modify the IPAM tier

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **IPAMs**.
3. In the content pane, select your IPAM.
4. Choose **Actions > Edit**.
5. Choose the **IPAM tier** you want to use for the IPAM.
6. Choose **Save changes**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to view and modify an IPAM tier:

1. View current IPAMs: [describe-ipams](#)
2. Modify the IPAM tier: [modify-ipam](#)
3. View your updated IPAMs: [describe-ipams](#)

Modify IPAM operating Regions

Follow the steps in this section to modify the IPAM operating Regions. Operating Regions are Amazon Regions where the IPAM is allowed to manage IP address CIDRs. IPAM only discovers and monitors resources in the Amazon Regions you select as operating Regions.

Amazon Management Console

To modify the IPAM operating Regions

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **IPAMs**.
3. In the content pane, select your IPAM.

4. Choose **Actions > Edit**.
5. Under **IPAM settings**, choose the **Operating Regions** you want to use for the IPAM.
6. Choose **Save changes**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to view and modify IPAM operating Regions:

1. View current IPAMs: [describe-ipams](#)
2. Add or remove IPAM operating Regions: [modify-ipam](#)
3. View your updated IPAMs: [describe-ipams](#)

Delete an IPAM

Follow the steps in this section to delete an IPAM. For information on increasing the default number of IPAMs you can have rather than deleting an existing IPAM, see [Quotas for your IPAM](#).

Important

Deleting an IPAM removes all monitored data associated with the IPAM including the historical data for CIDRs.

Amazon Management Console

To delete an IPAM

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **IPAMs**.
3. In the content pane, select your IPAM.
4. Choose **Actions > Delete IPAM**.
5. Do one of the following:

- Choose **Cascade delete** to delete the IPAM, private scopes, pools in private scopes, and any allocations in the pools in private scopes. You cannot delete the IPAM with this option if there is a pool in your public scope. If you use this option, IPAM does the following:
 - Deallocates any CIDRs allocated to VPC resources (such as VPCs) in pools in private scopes.

 **Note**

No VPC resources are deleted as a result of enabling this option. The CIDR associated with the resource will no longer be allocated from an IPAM pool, but the CIDR itself will remain unchanged.

- Deprovisions all IPv4 CIDRs provisioned to IPAM pools in private scopes.
- Deletes all IPAM pools in private scopes.
- Deletes all non-default private scopes in the IPAM.
- Deletes the default public and private scopes and the IPAM.
- If you don't choose the **Cascade delete** checkbox, before you can delete an IPAM, you must do the following:
 - Release allocations within the IPAM pools. For more information, see [Release an allocation](#).
 - Deprovision CIDRs provisioned to pools within the IPAM. For more information, see [Deprovision CIDRs from a pool](#).
 - Delete any additional non-default scopes. For more information, see [Delete a scope](#).
 - Delete your IPAM pools. For more information, see [Delete a pool](#).

6. Enter **delete** and then choose **Delete**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to delete an IPAM:

1. View current IPAMs: [describe-ipams](#)
2. Delete an IPAM: [delete-ipam](#)
3. View your updated IPAMs: [describe-ipams](#)

To create a new IPAM, see [Create an IPAM](#).

Tracking IP address usage in IPAM

The tasks described in this section are optional. If you want to complete the tasks in this section, and you have delegated an IPAM account, the tasks should be completed by the IPAM account.

Follow the steps in this section to track IP address usage with IPAM.

Contents

- [Monitor CIDR usage with the IPAM dashboard](#)
- [Monitor CIDR usage by resource](#)
- [Monitor IPAM with Amazon CloudWatch](#)
- [View IP address history](#)
- [View public IP insights](#)

Monitor CIDR usage with the IPAM dashboard

Follow the steps in this section to access the IPAM dashboard and view the status of all CIDRs within a particular IPAM scope.

Amazon Management Console

To monitor CIDR usage using the IPAM dashboard

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Dashboard**.
3. By default, when you view the dashboard, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. The dashboard presents an overview of your IPAM pools and CIDRs within a scope. You can add, remove, resize, and move widgets to customize the dashboard.
 - **Scope:** The details for this scope. A scope is the highest-level container within IPAM. An IPAM contains two default scopes, one private and one public. Each scope represents the IP space for a single network. You may have multiple private scopes, but you can only have one public scope.

- **Scope ID:** The ID for this scope.
- **Scope type:** The type of scope.
- **IPAM ID:** The ID of the IPAM that the scope is in.
- **IPAM pools in this scope:** The ID of the IPAM that the scope is in.
- **View networking resources in this scope:** Takes you to the **Resources** section of the IPAM console.
- **Search the history of an IP address in this scope:** Takes you to the **Search IP history** section of the IPAM console.
- **Resource CIDR types:** The types of resource CIDRs in the scope.
 - **Subnet:** The number of CIDRs for subnets.
 - **VPC:** The number of CIDRs for VPCs.
 - **EIPs:** The number of CIDRs for Elastic IP addresses.
 - **Public IPv4 pools:** The number of CIDRs for public IPv4 pools.
- **Management state:** The management state of the CIDRs.
 - **Unmanaged CIDRs:** The number of resource CIDRs for unmanaged resources in this scope.
 - **Ignored CIDRs:** The number of resource CIDRs that you have chosen to be exempt from monitoring with IPAM in the scope. IPAM does not evaluate ignored resources for overlap or compliance within a scope. When a resource is chosen to be ignored, any space that's allocated to it from an IPAM pool is returned to the pool, and the resource will not be imported again through automatic import (if the automatic import allocation rule is set on the pool).
 - **Managed CIDRs:** The number of resource CIDRs for manageable resources (VPCs or public IPv4 pools) that are allocated from an IPAM pool in the scope.
- **Overlapping resource CIDRs:** The number of overlapping and nonoverlapping CIDRs. Overlapping CIDRs can lead to incorrect routing in your VPCs.
 - **Overlapping CIDRs:** The number of CIDRs that currently overlap within the IPAM pools in this scope. Overlapping CIDRs can lead to incorrect routing in your VPCs.
 - **Nonoverlapping CIDRs:** The number of resource CIDRs that do not overlap within the IPAM pools in this scope.
- **Compliant resource CIDRs:** The number of compliant resource CIDRs.

- **Compliant CIDRs:** The number of resource CIDRs that comply with the allocation rules for IPAM pools in the scope.
- **Noncompliant CIDRs:** The number of resource CIDRs that do not comply with the allocation rules for the IPAM pools in the scope.
- **Overlap status:** The number of CIDRs that overlap over time.
 - **OverlappingResourceCidrs:** The number of CIDRs that overlap within the IPAM pools in this scope. Overlapping CIDRs can lead to incorrect routing in your VPCs.
- **Compliance status:** The number of CIDRs that comply versus do not comply with the allocation rules for IPAM pools in the scope over time.
 - **CompliantResourceCidrs:** The number of resource CIDRs that comply with the allocation rules.
 - **NoncompliantResourceCidrs:** The number of resource CIDRs that do not comply with the allocation rules.
- **VPC utilization:** VPCs (IPv4 and IPv6) with the highest or lowest IP utilization. You can use this information to configure Amazon CloudWatch alarms to be alerted if an IP utilization threshold is breached. For more information, see [Resource utilization metrics](#).
- **Subnet utilization:** Subnets (IPv4 only) with the highest or lowest IP utilization. You can use this information to decide if you want to keep or delete resources that are underutilized. For more information, see [Resource utilization metrics](#).
- **VPCs with highest IPs allocated:** The VPCs that have the highest percentage of IP address space allocated to subnets. This is useful to show you if you need to provision additional IP address space to the VPCs.
- **Subnets with highest IPs allocated:** The subnets that have the highest percentage of IP address space allocated to resources. This is useful to show you if you need to provision additional IP address space to the subnets.
- **Pool assignment:** The percentage of IP space that has been assigned to resources and manual allocations in the scope over time.
- **Pool allocation:** The percentage of a pool's IP space that has been allocated to other pools in the scope over time.

Command line

The information displayed in the dashboard comes from metrics stored in Amazon CloudWatch. For more information about the metrics stored in Amazon CloudWatch, see [Monitor IPAM with](#)

[Amazon CloudWatch](#). Use the Amazon CloudWatch options in the [Amazon CLI Reference](#) to view metrics for allocations in your IPAM pools and scopes.

If you find that the CIDR that's provisioned for a pool is almost fully allocated, you might need to provision additional CIDRs. For more information, see [Provision CIDRs to a pool](#).

Monitor CIDR usage by resource

In IPAM, a resource is an Amazon service entity that is assigned an IP address or CIDR block. IPAM manages some resources, but only monitors other resources.

- **Managed resource:** A managed resource has a CIDR allocated from an IPAM pool. IPAM monitors the CIDR for potential IP address overlap with other CIDRs in the pool, and monitors the CIDR's compliance with a pool's allocation rules. IPAM supports managing the following type of resources:
 - VPCs
 - Public IPv4 pools

Important

Public IPv4 pools and IPAM pools are managed by distinct resources in Amazon. Public IPv4 pools are single account resources that enable you to convert your publicly-owned CIDRs to Elastic IP addresses. IPAM pools can be used to allocate your public space to public IPv4 pools.

- **Monitored resource:** If a resource is monitored by IPAM, the resource has been detected by IPAM and you can view details about the resource's CIDR when you use `get-ipam-resource-cidrs` with the Amazon CLI, or when you view **Resources** in the navigation pane. IPAM supports monitoring the following resources:
 - VPCs
 - Public IPv4 pools
 - VPC subnets
 - Elastic IP addresses

The following steps show you how to monitor CIDR usage and allocation rule compliance by resource.

Amazon Management Console

To monitor CIDR usage by resource

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Resources**.
3. From the dropdown menu at the top of the content pane, choose the scope that you want to use. For more information about scopes, see [How IPAM works](#).
4. Use the resource CIDR map to view available, allocated, and overlapping IP address space in a scope:
 - **Available:** An IP address range is available for allocation.
 - **Compliant and nonoverlapping :** An IP address range is allocated to a resource managed by IPAM.
 - **Occupied:** An IP address range is allocated to a resource.
 - **Overlapping:** An IP address range has been allocated to multiple resources and is overlapping.
 - **Noncompliant:** An IP address range is not compliant. There is a resource using the IP address range that is not compliant with the allocation rules set up for the pool.

In the CIDR map, choose an IP address block at the bottom of the map to view the resources in smaller CIDR blocks. Choose an IP address block at the top of the map to view the resources in larger CIDR blocks.

5. In the table, you can view the following details about resources in the scope:
 - **Name (Resource ID):** The name and resource ID of the resource.
 - **CIDR:** The CIDR associated with the resource.
 - **Management state:** The state of the resource.
 - **Managed:** The resource has a CIDR allocated from an IPAM pool and is being monitored by IPAM for potential CIDR overlap and compliance with pool allocation rules.
 - **Unmanaged:** The resource does not have a CIDR allocated from an IPAM pool and is not being monitored by IPAM for potential CIDR compliance with pool allocation rules. The CIDR is monitored for overlap.

- **Ignored:** The resource has been chosen to be exempt from monitoring. Ignored resources are not evaluated for overlap or allocation rule compliance. When a resource is chosen to be ignored, any space allocated to it from an IPAM pool is returned to the pool and the resource will not be imported again through automatic import (if the automatic import allocation rule is set on the pool).
- -: This resource is not one of the types of resources that IPAM can manage.
- **Compliance status:** The compliance status of the CIDR.
 - **Compliant:** A managed resource complies with the allocation rules of the IPAM pool.
 - **Noncompliant:** The resource CIDR does not comply with one or more of the allocation rules of the IPAM pool.

Example

If a VPC has a CIDR that does not meet the netmask length parameters of the IPAM pool, or if the resource is not in the same Amazon Region as the IPAM pool, it will be flagged as noncompliant.

- **Unmanaged:** The resource does not have a CIDR allocated from an IPAM pool and is not being monitored by IPAM for potential CIDR compliance with pool allocation rules. The CIDR is monitored for overlap.
- **Ignored:** The resource has been chosen to be exempt from monitoring. Ignored resources are not evaluated for overlap or allocation rule compliance. When a resource is chosen to be ignored, any space allocated to it from an IPAM pool is returned to the pool and the resource will not be imported again through automatic import (if the automatic import allocation rule is set on the pool).
- -: This resource is not one of the types of resources that IPAM can manage.
- **Overlap status:** The overlap status of CIDR.
 - **Nonoverlapping:** The resource CIDR does not overlap with another CIDR in the same scope.
 - **Overlapping:** The resource CIDR overlaps with another CIDR in the same scope. Note that if a resource CIDR is overlapping, it could be overlapping with a manual allocation.
 - **Ignored:** The resource has been chosen to be exempt from monitoring. IPAM does not evaluate ignored resources for overlap or allocation rule compliance. When a resource is chosen to be ignored, any space allocated to it from an IPAM pool is returned to the pool and the resource will not be imported again through automatic import (if the automatic import allocation rule is set on the pool).

- -: This resource is not one of the types of resources that IPAM can manage.
 - **IP usage:** For resources that are VPCs, this is the percentage of IP address space in the VPC that's taken up by subnet CIDRs. For resources that are subnets, if the subnet has an IPv4 CIDR provisioned to it, this is the percentage of IPv4 address space in the subnet that's in use. If the subnet has an IPv6 CIDR provisioned to it, the percentage of IPv6 address space in use is not represented. The percentage of IPv6 address space in use cannot currently be calculated. For resources that are public IPv4 pools, this is the percentage of IP address space in the pool that's been allocated to Elastic IP addresses (EIPs).
 - **Region:** The Amazon Region of the resource.
 - **Owner ID:** The Amazon account ID of the person that created this resource.
 - **Resource type:** Whether the resource is a VPC, subnet, Elastic IP address, or public IPv4 pool.
 - **Pool ID:** The ID of the IPAM pool that the resource is in.
6. Use **Filter resources** to filter the resources table by column property, like VPC ID or compliance status.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

Use the following Amazon CLI commands to monitor CIDR usage by resource:

1. Get the scope ID: [describe-ipam-scopes](#)
2. Request resource information: [get-ipam-resource-cidrs](#)

Monitor IPAM with Amazon CloudWatch

IPAM automatically stores metrics related to IP address usage (such as the IP address space available in your IPAM pools and the number of resource CIDRs that comply with allocation rules) and resource utilization in the AWS/IPAM [Amazon CloudWatch namespace](#) in the home Region of your IPAM.

Contents

- [IPAM pool and scope metrics](#)
- [Resource utilization metrics](#)

IPAM pool and scope metrics

IPAM publishes data about your IPAM pools and scopes to Amazon CloudWatch. You can use these metrics to create alarms for IPAM pools to notify you if the address pools are nearing exhaustion or if resources fail to comply with allocation rules set on a pool. Creating alarms and setting up notifications with Amazon CloudWatch is outside the scope of this section. For more information, see [Using Amazon CloudWatch alarms](#) in the *Amazon CloudWatch User Guide*.

The metrics and dimensions that IPAM sends to Amazon CloudWatch are listed below.

IPAM pool metrics

| Metric name | Description |
|---------------------------|---|
| CompliantResourceCidrs | The number of managed resource CIDRs that comply with the allocation rules of the IPAM pool. For more information about allocation rules, see Create a top-level IPv4 pool . |
| NoncompliantResourceCidrs | The number of managed resource CIDRs that do not comply with the allocation rules of the IPAM pool. For more information about allocation rules, see Create a top-level IPv4 pool . |
| PercentAllocated | The percentage of a pool's IP space that has been allocated to other pools. |
| PercentAssigned | The percentage of a pool's IP space that has been allocated to resources, including manual allocations. |
| PercentAvailable | The percentage of a pool's IP space that has not been allocated to other pools or resources. |

IPAM scope metrics

| Metric name | Description |
|---------------------------|--|
| CompliantResourceCidrs | The number of resource CIDRs that comply with the allocation rules for IPAM pools in the scope. |
| ManagedResourceCidrs | The number of resource CIDRs for manageable resources (VPCs or public IPv4 pools) that are allocated from an IPAM pool in the scope. |
| NoncompliantResourceCidrs | The number of resource CIDRs that do not comply with the allocation rules for the IPAM pools in the scope. |
| OverlappingResourceCidrs | The number of resource CIDRs that overlap in the scope. |
| UnmanagedResourceCidrs | The number of resource CIDRs in the scope that are currently associated with manageable resources but are not managed by IPAM. |

The dimensions you can use to filter IPAM metrics are listed below.

| Dimension | Description |
|---------------|--|
| AddressFamily | The IP address family for resource CIDRs (IPv4 or IPv6). |
| Locale | The Amazon Region where an IPAM pool is available for allocations. |
| PoolID | The ID of a pool. |
| ScopeID | The ID of a scope. |

For information about monitoring VPCs with Amazon CloudWatch, see [CloudWatch metrics for your VPCs](#) in the *Amazon Virtual Private Cloud User Guide*.

Resource utilization metrics

IPAM publishes IP utilization metrics for resources that the IPAM monitors to Amazon CloudWatch. These resources include:

- VPCs (IPv4 and IPv6)
- Subnets (IPv4)
- Public IPv4 pools

IPAM calculates and publishes IP utilization metrics separately by IP address family (IPv4 or IPv6). The IP utilization of a resource is calculated across all of its CIDRs of the same address family.

For each resource type and address family combination, IPAM uses three rules to determine which metrics to publish:

- Up to 50 resources with the highest IP utilization. You can use this information to configure alarms to be alerted if an IP utilization threshold is breached.
- Up to 50 resources with the lowest IP utilization. You can use this information to decide if you want to keep or delete resources that are underutilized.
- Up to 50 other resources. You can use this information to consistently track the IP utilization of resources that may not be captured within the high or low utilization group.
 - Up to 50 VPCs containing a CIDR allocated from an IPAM pool (prioritized by total size of CIDR blocks).
 - Up to 50 subnets whose VPC contains a CIDR allocated from an IPAM pool (prioritized by total size of CIDR blocks).
 - Up to 50 public IPv4 pools containing a CIDR allocated from an IPAM pool (prioritized by total size of CIDR blocks).

After applying each rule, the metrics are aggregated and published under the same metric name for each resource type. See below for detailed information on the metric names and their dimensions.

Important

There is a unique limit for each resource type, address family, and rule combination. The default value of each limit is 50. You can adjust these limits by contacting the Amazon

Support Center as described in [Amazon service quotas](#) in the *Amazon Web Services General Reference*.

Example Example

Let's say that your IPAM monitors 2,500 VPCs and 10,000 subnets, all with IPv4 and IPv6 CIDRs. IPAM publishes the following IP utilization metrics:

- Up to 150 metrics for VPC IPv4 IP utilization, including:
 - The 50 VPCs with the highest IPv4 IP utilization
 - The 50 VPCs with the lowest IPv4 utilization
 - Up to 50 VPCs containing an IPv4 CIDR allocated from an IPAM pool
- Up to 150 metrics for VPC IPv6 utilization, including:
 - The 50 VPCs with the highest IPv6 IP utilization
 - The 50 VPCs with the lowest IPv6 utilization
 - Up to 50 VPCs containing an IPv6 CIDR allocated from an IPAM pool
- Up to 150 metrics for subnet IPv4 utilization, including:
 - The 50 subnets with the highest IPv4 IP utilization
 - The 50 subnets with the lowest IPv4 IP utilization
 - Up to 50 subnets whose VPC contains an IPv4 CIDR allocated from an IPAM pool

VPC metrics

The VPC metric name and description is listed below.

| Metric name | Description |
|-------------|--|
| VpcIPUsage | The total IPs covered by CIDRs in the VPC's subnets divided by the total IPs covered by CIDRs in the VPC. This is calculated across all VPC CIDRs in the same IPAM Scope and separately for IPv4 and IPv6 CIDRs. |

The dimensions you can use to filter VPC metrics are listed below.

| Dimension | Description |
|---------------|--|
| AddressFamily | The IP address family for resource CIDRs (IPv4 or IPv6). |
| OwnerID | The ID of the VPC owner. |
| Region | The Amazon Region where the VPC is located. |
| ScopelD | The ID of the IPAM scope that the VPC belongs to. |
| VpcID | The ID of the VPC. |

Subnet metrics

The subnet metric name and description is listed below.

| Metric name | Description |
|---------------|--|
| SubnetIPUsage | The number of active IPs divided by total IPs in the subnet's IPv4 CIDR. |

The dimensions you can use to filter subnet metrics are listed below.

| Dimension | Description |
|---------------|---|
| AddressFamily | The IP address family for resource CIDRs (IPv4 only). |
| OwnerID | The ID of the subnet owner. |
| Region | The Amazon Region where the subnet is located. |
| ScopelD | The ID of the IPAM scope that the subnet belongs to. |
| SubnetID | The ID of the subnet. |
| VpcID | The ID of the VPC that the subnet belongs to. |

Public IPv4 pool metrics

The public IPv4 pool metric name and description is listed below.

| Metric name | Description |
|-----------------------|--|
| PublicIPv4PoolIPUsage | The number of EIPs from the public IPv4 Pool divided by total IPs in the pool. |

The dimensions you can use to filter the public IPv4 pool metrics are listed below.

| Dimension | Description |
|------------------|--|
| OwnerID | The ID of the public IPv4 pool owner. |
| PublicIPv4PoolID | The ID of the public IPv4 pool. |
| Region | The Amazon Region where the public IPv4 pool is located. |
| ScopeID | The ID of the IPAM scope that the public IPv4 pool belongs to. |

Public IP insight metrics

The [public IP insight](#) metric names and descriptions are listed below.

| Metric name | Description |
|---------------------------------|--|
| AmazonOwnedElasticIPs | The number of Amazon-owned Elastic IP addresses that you have provisioned or assigned to resources in your Amazon account. |
| AssociatedAmazonOwnedElasticIPs | The number of Amazon-owned Elastic IP addresses that you have associated with resources in your Amazon account. |
| AssociatedBringYourOwnIPs | The number of public IPv4 addresses that you have brought to Amazon using Bring your own IP addresses (BYOIP) and have associated with resources in your Amazon account. |

| Metric name | Description |
|-----------------------------------|---|
| BringYourOwnIPs | The number of public IPv4 addresses that you have brought to Amazon using Bring your own IP addresses (BYOIP). |
| EC2PublicIPs | The number of public IPv4 addresses assigned to EC2 instances when the instances were launched into a default subnet or into a subnet configured to automatically assign a public IPv4 address. |
| ServiceManagedBringYourOwnIPs | The number of public IPv4 addresses that you have brought to Amazon using Bring your own IP addresses (BYOIP) that are provisioned and managed by an Amazon service. |
| ServiceManagedIPs | The number of public IPv4 addresses provisioned and managed by an Amazon service. |
| UnassociatedAmazonOwnedElasticIPs | The number of Amazon-owned Elastic IP addresses that you have not associated with resources in your Amazon account. |
| UnassociatedBringYourOwnIPs | The number of public IPv4 addresses that you have brought to Amazon using Bring your own IP addresses (BYOIP) and have not associated with any resources in your Amazon account. |

The dimensions you can use to filter the public IP insight metrics are listed below.

| Dimension | Description |
|-----------|---|
| IpamId | The ID of the IPAM that the IP address belongs to. |
| Region | The Amazon Region where the public IP address is located. |

Quick tip for creating alarms

To quickly create an Amazon CloudWatch alarm for resources with high IP address utilization, open the CloudWatch console, choose **Metrics**, **All metrics**, choose the **Query** tab, choose the **Namespace** AWS/IPAM > VPC IP Usage Metrics, AWS/IPAM > Subnet IP Usage

Metrics, or AWS/IPAM > Public IPv4 Pool IP Usage Metrics, choose the **Metric name** `MAX(VpcIPUsage)`, `MAX(SubnetIPUsage)`, or `MAX(PublicIPv4PoolIPUsage)`, and choose **Create alarm**. For more information, see [Create alarms on Metrics Insights queries](#) in the *Amazon CloudWatch User Guide*.

View IP address history

Follow the steps in this section to view the history of an IP address or CIDR in an IPAM scope. You can use the historical data to analyze and audit your network security and routing policies. IPAM automatically retains IP address monitoring data for up to three years.

You can use the IP historical data to search for the status change of IP addresses or CIDRs for the following types of resources:

- VPCs
- VPC subnets
- Elastic IP addresses
- EC2 instances
- EC2 network interfaces attached to instances

Important

Although IPAM doesn't monitor Amazon EC2 instances or EC2 network interfaces that are attached to instances, you can use the Search IP history feature to search for historical data on EC2 instance and network interface CIDRs.

Note

- If you move a resource from one IPAM scope to another, the previous history record ends and a new history record is created under the new scope. For more information, see [Move VPC CIDRs between scopes](#).
- If you delete or transfer a resource to an Amazon account that's not monitored by your IPAM, any new history related to the resource will not be visible and your IPAM won't monitor the resource. The IP address of the resource, however, will still be searchable.

- If you [Integrate IPAM with accounts outside of your organization](#), the IPAM owner can view the IP address history of all resource CIDRs owned by those accounts.

Amazon Management Console

To view the history of a CIDR

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Search IP history**.
3. Enter an IPv4 or IPv6 IP address or CIDR. This must be a specific CIDR for the resource.
4. Choose an IPAM scope ID.
5. Choose a date/time range.
6. If you want to filter the results by VPC, enter a VPC ID. Use this option if the CIDR appears in multiple VPCs.
7. Choose **Search**.

Command line

The commands in this section link to the Amazon CLI Reference documentation. The documentation provides detailed descriptions of the options that you can use when you run the commands.

- View the history of a CIDR: [get-ipam-address-history](#)

To see examples of how you can use the Amazon CLI to analyze and audit IP address usage, see [Tutorial: View IP address history using the Amazon CLI](#).

The results of the search are organized into the following columns:

- **Sampled end time:** Sampled end time of the resource-to-CIDR association within the IPAM scope. Changes are picked up in periodic snapshots, so the end time might have occurred before this specific time.
- **Sampled start time:** Sampled start time of the resource-to-CIDR association within the IPAM scope. Changes are picked up in periodic snapshots, so the start time might have occurred before this specific time.

Example

To help explain the times that you see under Sampled start time and Sampled end time, let's look at an example use case:

At 2:00 PM, a VPC was created with CIDR 10.0.0.0/16. At 3:00 PM, you create an IPAM and IPAM pool with CIDR 10.0.0.0/8, and select the auto-import option to allow IPAM to discover and import any CIDRs that fall within the 10.0.0.0/8 IP address range. Because IPAM picks up changes to CIDRs in periodic snapshots, it doesn't discover the existing VPC CIDR until 3:05 PM. When you search for the ID of this VPC using the Search IP history feature, the Sampled start time for your VPC is 3:05 PM, which is when IPAM discovered it, not 2:00 PM, which is when you created the VPC. Now, let's say that you decide to delete the VPC at 5:00 PM. When the VPC is deleted, the CIDR 10.0.0.0/16 that was allocated to the VPC is recycled back into the IPAM pool. IPAM takes its periodic snapshot at 5:05 PM and picks up the change. When you search for the ID of this VPC in Search IP history, 5:05 PM is the Sampled end time for the VPC's CIDR, not 5:00 PM, which is when the VPC was deleted.

- **Resource ID:** The ID generated when the resource was associated with the CIDR.
- **Name:** The name of the resource (if applicable).
- **Compliance status:** The compliance status of the CIDR.
 - **Compliant:** A managed resource complies with the allocation rules of the IPAM pool.
 - **Noncompliant:** The resource CIDR does not comply with one or more of the allocation rules of the IPAM pool.

Example

If a VPC has a CIDR that does not meet the netmask length parameters of the IPAM pool, or if the resource is not in the same Amazon Region as the IPAM pool, it will be flagged as noncompliant.

- **Unmanaged:** The resource does not have a CIDR allocated from an IPAM pool and is not being monitored by IPAM for potential CIDR compliance with pool allocation rules. The CIDR is monitored for overlap.
- **Ignored:** The managed resource has been chosen to be exempt from monitoring. Ignored resources are not evaluated for overlap or allocation rule compliance. When a resource is chosen to be ignored, any space allocated to it from an IPAM pool is returned to the pool and the resource will not be imported again through automatic import (if the automatic import allocation rule is set on the pool).

- -: This resource is not one of the types of resources that IPAM can monitor or manage.
- **Overlap status:** The overlap status of CIDR.
 - **Nonoverlapping:** The resource CIDR does not overlap with another CIDR in the same scope.
 - **Overlapping:** The resource CIDR overlaps with another CIDR in the same scope. Note that if a resource CIDR is overlapping, it could be overlapping with a manual allocation.
 - **Ignored:** The managed resource has been chosen to be exempt from monitoring. IPAM does not evaluate ignored resources for overlap or allocation rule compliance. When a resource is chosen to be ignored, any space allocated to it from an IPAM pool is returned to the pool and the resource will not be imported again through automatic import (if the automatic import allocation rule is set on the pool).
- -: This resource is not one of the types of resources that IPAM can monitor or manage.
- **Resource type**
 - **vpc:** The CIDR is associated with a VPC.
 - **subnet:** The CIDR is associated with a VPC subnet.
 - **eip:** The CIDR is associated with an Elastic IP address.
 - **instance:** The CIDR is associated with an EC2 instance.
 - **network-interface:** The CIDR is associated with a network interface.
- **VPC ID:** The ID of the VPC that this resource belongs to (if applicable).
- **Region:** The Amazon Region of this resource.
- **Owner ID:** The Amazon account ID of the user that created this resource (if applicable).

View public IP insights

A public IPv4 address is an IPv4 address that is routable from the internet. A public IPv4 address is necessary for a resource to be directly reachable from the internet over IPv4.

Note

Amazon charges for all public IPv4 addresses, including public IPv4 addresses associated with running instances and Elastic IP addresses. For more information, see the **Public IPv4 Address** tab on the [Amazon VPC pricing page](#).

You can view insights into the following public IPv4 address types:

- **Elastic IP addresses (EIPs):** Static, public IPv4 addresses provided by Amazon that you can associate with an EC2 instance, elastic network interface, or Amazon resource.
- **EC2 public IPv4 addresses:** Public IPv4 addresses assigned to an EC2 instance by Amazon (if the EC2 instance is launched into a default subnet or if the instance is launched into a subnet that's been configured to automatically assign a public IPv4 address).
- **BYOIPv4 addresses:** Public IPv4 addresses in the IPv4 address range that you've brought to Amazon using [Bring your own IP addresses \(BYOIP\)](#).
- **Service-managed IPv4 addresses:** Public IPv4 addresses automatically provisioned on Amazon resources and managed by an Amazon service. For example, public IPv4 addresses on Amazon ECS, Amazon RDS, or Amazon Workspaces.

You can use Public IP insights to see the following:

- If your IPAM is [integrated with accounts in an Amazon Organization](#), you can view all public IPv4 addresses used by services across all Amazon Regions for your entire Amazon Organization.
- If your IPAM is [integrated with a single account](#), you can view all public IPv4 addresses used by services across all Amazon Regions in your account.

Public IP insights shows you all public IPv4 addresses used by services across Regions. You can use these insights to identify public IPv4 address usage and view recommendations to release unused Elastic IP addresses.

- **Public IP types:** The number of public IPv4 addresses organized by type.
 - **Amazon-owned EIPs:** Elastic IP addresses that you have provisioned or assigned to resources in your Amazon account.
 - **EC2 public IPs:** Public IPv4 addresses assigned to EC2 instances when the instances were launched into a default subnet or into a subnet that's been configured to automatically assign a public IPv4 address.
 - **BYOIP:** Public IPv4 addresses that you have brought to Amazon using Bring your own IP addresses (BYOIP).
 - **Service managed IPs:** Public IPv4 addresses provisioned and managed by an Amazon service.
- **EIP usage:** The number of Elastic IP addresses organized by how they are used.

- **Associated Amazon-owned EIPs:** Elastic IP addresses that you have provisioned in your Amazon account and that you have associated with an EC2 instance, network interface, or Amazon resource.
- **Associated BYOIP:** Public IPv4 addresses you have brought to Amazon using BYOIP that you have associated with a network interface.
- **Unassociated Amazon-owned EIPs:** Elastic IP addresses that you have provisioned in your Amazon account but you have not associated with a network interface.
- **Unassociated BYOIP:** Public IPv4 addresses you have brought to Amazon using BYOIP but you have not associated with a network interface.
- **Public IP addresses:** A table of public IPv4 addresses and their attributes.
 - **IP address:** The public IPv4 address.
 - **Associated:** Whether or not the address is associated with an EC2 instance, network interface, or Amazon resource.
 - **Associated:** The public IPv4 address is associated with an EC2 instance, network interface, or Amazon resource.
 - **Unassociated:** The public IPv4 address is not associated to any resource and is idle in your Amazon account.
 - **Address type:** The IP address type.
 - **Amazon-owned EIP:** The public IPv4 address is an Elastic IP address.
 - **BYOIP:** The public IPv4 address was brought to Amazon using BYOIP.
 - **EC2 public IP:** The public IPv4 address was assigned automatically to an EC2 instance.
 - **Service managed BYOIP:** The public IPv4 address was brought to Amazon using Bring your own IP (BYOIP).
 - **Service managed IP:** The public IPv4 address was provisioned and is managed by an Amazon service.
 - **Service:** The service that the IP address is associated with.
 - **AGA:** An Amazon Global Accelerator. If a [custom routing accelerator](#) is used, its public IPs are not listed. To view these public IPs, see [Viewing your custom routing accelerators](#).
 - **Database Migration Service:** An Amazon Database Migration Service (DMS) replication instance.
 - **Redshift:** An Amazon Redshift cluster.
 - **RDS:** An Amazon Relational Database Service (RDS) instance.

- **Load balancer (EC2):** An Application Load Balancer or a Network Load Balancer.
- **NAT gateway (VPC):** An Amazon VPC public NAT gateway.
- **Site-to-Site VPN:** An Amazon Site-to-Site VPN virtual private gateway.
- **Other:** Other service that is not currently identifiable.
- **Name (EIP ID):** If this public IPv4 address is an Elastic IP address allocation, this is the name and ID of the EIP allocation.
- **Network interface ID:** If this public IPv4 address is associated with a network interface, this is the ID of the network interface.
- **Instance ID:** If this public IPv4 address is associated with an EC2 instance, this is the instance ID.
- **Security groups:** If this public IPv4 address is associated with an EC2 instance, this is the name and ID of the security group assigned to the instance.
- **Public IPv4 pool:** If this is an Elastic IP address from an IP address pool owned and managed by Amazon, the value is "-". If this is an Elastic IP address from an IP address range which you own and have brought to Amazon (using BYOIP), the value is the public IPv4 pool ID.
- **Network border group:** If the IP address is advertised, this is the Amazon Region from which the IP address is advertised.
- **Owner ID:** The Amazon account number of resource owner.
- **Sample time:** The last successful resource discovery time.
- **Resource discovery ID:** ID of the resource discovery that has discovered this public IPv4 address.
- **Service resource:** Resource ARN or ID.

If an Elastic IP address is allocated to your account but is not associated with a network interface, a banner appears informing you that you have unassociated EIPs in your account and you should release them.

Important

Public IP insights was recently updated. If you see an error related to not having permissions to call `GetIpamDiscoveredPublicAddresses`, the managed permission attached to a resource discovery that was shared with you needs to be updated. Contact the person who created the resource discovery and ask them to update the managed permission

AWSRAMPermissionIpamResourceDiscovery to the default version. For more information, see [Update a resource share](#) in the *Amazon RAM User Guide* .

Amazon Management Console

To view public IP address insights

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Public IP insights**.
3. To view details for a public IP address, select an IP address by clicking on it.
4. View the following information about the IP address:
 - **Details:** The same information visible in the columns of the main Public IP insights pane, such as the **Address type** and **Service**.
 - **Inbound security group rules:** If this IP address is associated with an EC2 instance, these are the security group rules that control the inbound traffic to the instance.
 - **Outbound security group rules:** If this IP address is associated with an EC2 instance, these are the security group rules that control the outbound traffic from the instance.
 - **Tags:** Key and value pairs that act as metadata for organizing your Amazon resources.

Command line

Use the following command to get the public IP addresses that have been discovered by IPAM:
[get-ipam-discovered-public-addresses](#)

Tutorials for Amazon VPC IP Address Manager

The following tutorials show you how to perform common IPAM tasks using the Amazon CLI. To get the Amazon CLI, see [Access IPAM](#). For more information about the IPAM concepts that are mentioned in these tutorials, see [How IPAM works](#).

Contents

- [Tutorial: Create an IPAM and pools using the console](#)
- [Tutorial: Create an IPAM and pools using the Amazon CLI](#)
- [Tutorial: View IP address history using the Amazon CLI](#)
- [Tutorial: Bring your ASN to IPAM](#)
- [Tutorial: Bring your IP addresses to IPAM](#)
- [Tutorial: Transfer a BYOIP IPv4 CIDR to IPAM](#)
- [Tutorial: Plan VPC IP address space for subnet IP allocations](#)

Tutorial: Create an IPAM and pools using the console

In this tutorial, you create an IPAM, integrate with Amazon Organizations, create IP address pools, and create a VPC with a CIDR from an IPAM pool.

This tutorial shows you how you can use IPAM to organize IP address space based on different development needs. Once you've completed this tutorial, you'll have one IP address pool for pre-production resources. You can then create other pools based on your routing and security needs, such as a pool for production resources.

While you can use IPAM as a single user, integrating with Amazon Organizations enables you to manage IP addresses across accounts in your organization. This tutorial covers integrating IPAM with accounts in an organization. It does not cover how to [Integrate IPAM with accounts outside of your organization](#).

Note

For the purposes of this tutorial, the instructions will tell you to name IPAM resources in a particular way, create IPAM resources in specific Regions, and use specific IP address CIDR ranges for your pools. This is intended to streamline the choices available in IPAM and get

you started with IPAM quickly. Once you've completed this tutorial, you may decide to create a new IPAM and configure it differently.

Contents

- [Prerequisites](#)
- [How Amazon Organizations integrates with IPAM](#)
- [Step 1: Delegate an IPAM administrator](#)
- [Step 2: Create an IPAM](#)
- [Step 3: Create a top-level IPAM pool](#)
- [Step 4: Create Regional IPAM pools](#)
- [Step 5: Create a pre-production development pool](#)
- [Step 6: Share the IPAM pool](#)
- [Step 7: Create a VPC with a CIDR allocated from an IPAM pool](#)
- [Step 8: Cleanup](#)

Prerequisites

Before you begin, you must have set up an Amazon Organizations account with at least one member account. For how-to instructions, see [Creating and managing an organization](#) in the *Amazon Organizations User Guide*.

How Amazon Organizations integrates with IPAM

This section shows an example of the Amazon Organizations accounts you use in this tutorial. There are three accounts in your organization that you use when you integrate with IPAM in this tutorial:

- The management account (called **example-management-account** in the following image) to log into the IPAM console and delegate an IPAM admin. You cannot use the organization's management account as your IPAM admin.
- A member account (called *example-member-account-1* in the following image) as the IPAM admin account. The IPAM admin account is responsible for creating an IPAM and using it to manage and monitor IP address usage across the organization. Any member account in your organization can be delegated as the IPAM admin.

- A member account (called *example-member-account-2* in the following above) as the developer account. This account creates a VPC with a CIDR allocated from an IPAM pool.

The screenshot shows the AWS Organizations console. On the left, there is a navigation menu with 'AWS Organizations' and 'AWS accounts' selected. The main content area is titled 'AWS accounts' and includes an 'Add an AWS account' button. Below this, there is a search bar and buttons for 'Hierarchy' and 'List'. The 'Organizational structure' section shows a tree view with the following hierarchy:

- Root (r-fssg)
 - Organizational-unit-1 (ou-fssg-ycy89843)
 - Organizational-unit-1a (ou-fssg-q5brfv9c)
 - example-member-account-1 (848560618819 | example-member-account-1@amazon.com) - Joined 2022/12/28
 - example-member-account-2 (848560618819 | example-member-account-2@amazon.com) - Joined 2022/12/28
 - example-management-account (855210303341 | example-management-account@amazon.com) - management account - Joined 2022/12/28

In addition to the accounts, you'll need the ID of the organizational unit (**ou-fssg-q5brfv9c** in the preceding image) that contains the member account you'll use as the developer account. You need this ID so that, in a later step, when you share your IPAM pool, you can share it with this OU.

Note

For more information about Amazon Organizations account types like *management* and *member* accounts, see [Amazon Organizations terminology and concepts](#).

Step 1: Delegate an IPAM administrator

In this step, you'll delegate an Amazon Organizations member account as the IPAM admin. When you delegate an IPAM admin, [a service-linked role](#) is automatically created in each of your Amazon Organizations member accounts. IPAM monitors the IP address usage in these accounts by

assuming the service-linked role in each member account. It can then discover the resources and their CIDRs regardless of their Organizational Unit.

You cannot complete this step unless you have the required Amazon Identity and Access Management (IAM) permissions. For more information, see [Integrate IPAM with accounts in an Amazon Organization](#).

To delegate an IPAM admin account

1. Using the Amazon Organizations management account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.
2. In the Amazon Management Console, choose the Amazon Region in which you want to work with IPAM.
3. In the navigation pane, choose **Organization settings**.
4. Choose **Delegate**. The **Delegate** option is available only if you logged in to the console as the Amazon Organizations management account.
5. Enter the Amazon account ID for an organization member account. The IPAM administrator must be an Amazon Organizations member account, not the management account.

The screenshot shows the 'Settings' page in the Amazon VPC IP Address Manager console. The breadcrumb navigation at the top reads 'Amazon VPC IP Address Manager > Settings > Edit'. The main heading is 'Settings' with an 'Info' link. Below this is a section titled 'Delegated administrator'. Underneath, there is a sub-section 'Delegated administrator account' with a descriptive text: 'The account to be delegated as the IPAM administrator for your organization. To monitor resources across your organization, the IPAM must be created in the delegated administrator's account.' A text input field is provided with the placeholder text 'Enter an account ID for the IPAM administrator'. Below that is a 'Service access' section with the text: 'When you delegate an IPAM administrator, you grant Amazon VPC IP Address Manager permission to describe resources on your behalf.' A 'View details' button is located below the service access text. At the bottom right of the form, there are two buttons: 'Cancel' and 'Save changes'.

6. Choose **Save changes**. The **Delegated administrator** information is populated with details related to the member account.

Step 2: Create an IPAM

In this step you'll create an IPAM. When you create an IPAM, IPAM automatically creates two scopes for the IPAM: the private scope that's intended for all private space, and the public scope that's intended for all public space. The scopes, together with pools and allocations, are key components of your IPAM. For more information, see [How IPAM works](#).

To create an IPAM

1. Using the Amazon Organizations member account delegated as the IPAM admin in [the previous step](#), open the IPAM console at <https://console.aws.amazon.com/ipam/>.
2. In the Amazon Management Console, choose the Amazon Region in which you want to create the IPAM. Create the IPAM in your main Region of operations.
3. On the service home page, choose **Create IPAM**.
4. Select **Allow Amazon VPC IP Address Manager to replicate data from source account(s) into the IPAM delegate account**. If you do not select this option, you cannot create an IPAM.

The screenshot shows the 'Create IPAM' page in the AWS console. At the top, it says 'Create IPAM' with an 'Info' link. Below this is a light blue warning box with an information icon and the text: 'We have detected you are the IPAM delegated administrator of your organization. If you create an IPAM, it will monitor resources across all accounts of your organization.' Below the warning box is a section titled 'Allow data replication' with an 'Info' link. The text below this title reads: 'Amazon VPC IP Address Manager needs permission to replicate data from the member account(s) into the delegated account. The delegated account will have access to resource and IP usage details from each of the member accounts and the AWS Regions selected by those member accounts.' At the bottom of this section is a checkbox that is checked, with the text: 'Allow Amazon VPC IP Address Manager to replicate data from the member account(s) into the Amazon VPC IP Address Manager delegate account.' Below the checkbox is a note: 'You must select this checkbox to continue to create an IPAM.'

5. Under **Operating Regions**, choose the Amazon Regions in which this IPAM can manage and discover resources. The Amazon Region in which you are creating your IPAM is automatically selected as one of the operating Regions. In this tutorial, the home Region of our IPAM is us-east-1, so we'll choose us-west-1 and us-west-2 as additional operating Regions. If you forget an operating Region, you can edit your IPAM settings later and add or remove Regions.

IPAM settings [Info](#)

Name tag - *optional*

Creates a tag with a key of 'Name' and a value that you specify.

Description - *optional*

Write a brief description for the IPAM.

Operating Regions

Select Regions in which the IPAM will discover resources and manage IPs. The current region will always be set as an operating region.



Default resources will be created

On IPAM creation, the following IPAM resources will also be created:

- A default private scope. Resources using private IP space will be imported into the private scope.
- A default public scope. Resources using public IP space will be imported into the public scope.
- A default resource discovery, which controls the resources that IPAM will discover.

6. Choose **Create IPAM**.

✔ Successfully created IPAM ipam-005f921c17ebd5107
✕

Amazon VPC IP Address Manager > IPAMs > ipam-005f921c17ebd5107

DemoIPAM (ipam-005f921c17ebd5107) Info

Edit Delete

IPAM details

| | | | |
|--|---|--|---|
| <p>IPAM ID</p> <p> ipam-005f921c17ebd5107</p> <p>IPAM ARN</p> <p> arn:aws:ec2::320805250157:ipam/ipam-005f921c17ebd5107</p> <p>State</p> <p>✔ Create-complete</p> | <p>Description</p> <p>–</p> <p>Default public scope</p> <p> ipam-scope-0d3539a30b57dcdd1</p> <p>Default resource discovery</p> <p> ipam-res-disco-0f4ef577a9f37a162</p> | <p>Owner ID</p> <p> 320805250157</p> <p>Default private scope</p> <p> ipam-scope-0a158dde35c51107b</p> | <p>Region</p> <p> us-east-1</p> <p>Scope count</p> <p>2</p> |
|--|---|--|---|

Operating Regions | Associated discoveries | Tags

Operating Regions (3) Info

< 1 >

| Region |
|-------------------------------------|
| US East (N. Virginia) - us-east-1 |
| US West (N. California) - us-west-1 |
| US West (Oregon) - us-west-2 |

Step 3: Create a top-level IPAM pool


In this tutorial, you create a hierarchy of pools starting with the top-level IPAM pool. In the subsequent steps, you'll create a pair of Regional pools and a pre-production development pool in one of the regional pools.

For more information about pool hierarchies that you can build with IPAM, see [Example IPAM pool plans](#).

To create a top-level pool

- Using the IPAM admin account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.

2. In the navigation pane, choose **Pools**.
3. Choose the private scope.



4. Choose **Create pool**.
5. Under **IPAM scope**, leave the private scope selected.
6. (Optional) Add a **Name tag** for the pool and a description for the pool, such as “Global pool”.
7. Under **Source**, choose **IPAM scope**. Because this is our top level pool, it will not have a source pool.
8. Under **Address family**, choose **IPv4**.
9. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
10. For the **Locale**, choose **None**. Locales are the Amazon Regions where you want this IPAM pool to be available for allocations. You’ll set the locale for the Regional pools that you create in the next section of this tutorial.

Amazon VPC IP Address Manager > Pools > Create

Create pool in ipam-scope-0cbdc40f8f04fa968

Pool settings

| | |
|---|---|
| Name (IPAM ID) DemoIPAM (ipam-080d0c4b98089b437) | Name (Scope ID) ipam-scope-0cbdc40f8f04fa968 |
|---|---|

Name tag - optional
Creates a tag with a key of 'Name' and a value that you specify. Tags are not visible to other accounts even if a pool is shared.

Description - optional
Write a brief description for the pool.

Pool hierarchy [Info](#)

Source pool
To provision a CIDR into this pool, it must be available in the source pool. If no source pool is selected, then the space must be available in the scope.

Address family
Select the address family for this pool.

IPv4
 IPv6

Pools in the private scope must have address family IPv4.

Locale
Select a locale for this pool to reside.

A locale can only be selected if there is no source pool, or if the source pool's locale is None.

11. Choose a CIDR to provision for the pool. In this example, we provision 10.0.0.0/16.

CIDRs to provision [Info](#)

CIDRs to be provisioned must either be available in the source pool's space, or in the scope's space if no source pool.

CIDR

Enter a CIDR to be provisioned.

| | | |
|-------------|---------|--------|
| 10.0.0.0/16 | 65K IPs | Remove |
| < > ^ v | | |

Add new CIDR

12. Leave **Configure this pool's allocation rule settings** disabled. This is our top-level pool, and you will not be allocating CIDRs to VPCs directly from this pool. Instead, you will allocate them from a sub-pool that you create from this pool.

Allocation rule settings - *optional* [Info](#)



AWS best practice

We recommend you create a top-level pool and then Regional pools under the top-level pool. Under the Regional pools, create development pools. From the development pools you can configure allocation rules to control which resources can use CIDRs from these pools. For more examples of how to organize IPAM pools, see [Example IPAM pool plans](#).

Configure this pool's allocation rule settings

13. Choose **Create pool**. The pool is created and the CIDR is in a **Pending-provision** state:

🕒 Sent request to provision 10.0.0.0/16✕

Amazon VPC IP Address Manager > Pools > ipam-pool-06fb4cace4bc1e551

Global pool (ipam-pool-06fb4cace4bc1e551) 🔄 Actions ▾

Pool summary

| | | | |
|---|-----------------------------------|--|---|
| Pool ID 📄 ipam-pool-06fb4cace4bc1e551 | Description - | IPAM ID 📄 ipam-005f921c17ebd5107 | Scope ID 📄 ipam-scope-0a158dde35c51107b |
| Pool ARN 📄 arn:aws:ec2::320805250157:ipam-pool/ipam-pool-06fb4cace4bc1e551 | Owner ID 📄 320805250157 | Compliance status - | Overlap status - |

< Pool detailsMonitoringIP space visualizationCIDRsAllocationsResourcesComplianceReso >

CIDRs (1) Info

Deprovision CIDRsProvision CIDR

< 1 >⚙️

| | CIDR | CIDR ID | State |
|---|-------------|---|---------------------|
| ☐ | 10.0.0.0/16 | ipam-pool-cidr-0657f970d119e40899e0e... | ⌚ Pending-provision |

14. Wait for the state to be **Provisioned** before you go to the next step.

✔ Sent request to provision 10.0.0.0/16
✕

Amazon VPC IP Address Manager > Pools > ipam-pool-06fb4cace4bc1e551

Global pool (ipam-pool-06fb4cace4bc1e551) ↻ Actions ▾

Pool summary

| | | | |
|---|--|---|--|
| Pool ID ipam-pool-06fb4cace4bc1e551 | Description - | IPAM ID ipam-005f921c17ebd5107 | Scope ID ipam-scope-0a158dde35c51107b |
| Pool ARN arn:aws:ec2::320805250157:ipam-pool/ipam-pool-06fb4cace4bc1e551 | Owner ID 320805250157 | Compliance status - | Overlap status - |

< Pool details
Monitoring
IP space visualization
CIDRs
Allocations
Resources
Compliance
Resc >

CIDRs (1) Info

Deprovision CIDRs
Provision CIDR

< 1 >
⚙️

| <input type="checkbox"/> | CIDR | CIDR ID | State |
|--------------------------|-------------|--------------------------------------|---------------|
| <input type="checkbox"/> | 10.0.0.0/16 | ipam-pool-cidr-0657f970d119e40899... | ✔ Provisioned |

Now that you have created your top-level pool, you'll create Regional pools in us-west-1 and us-west-2.


Step 4: Create Regional IPAM pools

This section shows you how to organize your IP addresses using two Regional pools. In this tutorial, we're following one of [the example IPAM pool plans](#) and creating two Regional pools which can be used by the member accounts in your organization for allocating CIDRs to their VPCs.

To create a Regional pool

1. Using the IPAM admin account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.
2. In the navigation pane, choose **Pools**.


3. Choose the private scope.



4. Choose **Create pool**.

5. Under **IPAM scope**, leave the private scope selected.

6. (Optional) Add a **Name tag** for the pool and a description for the pool, such as **Regional pool us-west-1**.



7. Under **Source**, select **IPAM pool** and select the top-level pool (“Global pool”) that you created in [Step 3: Create a top-level IPAM pool](#). Then, under **Locale**, choose **us-west-1**.

Pool hierarchy [Info](#)

Source pool
To provision a CIDR into this pool, it must be available in the source pool. If no source pool is selected, then the space must be available in the scope.

Global pool (ipam-pool-023b91cf28c61a0fb) ▼

▼ **Source pool summary**

| | |
|---|-------------------|
| Name (Pool ID) | Provisioned CIDRs |
| Global pool (ipam-pool-023b91cf28c61a0fb) | 10.0.0.0/16 |
| Description | Locale |
| - | None |

Address family (inherited)
Select the address family for this pool.

IPv4
 IPv6

Pools in the private scope must have address family IPv4.

Locale
Select a locale for this pool to reside.

US West (N. California) - us-west-1 ▼

A locale can only be selected if there is no source pool, or if the source pool's locale is None.

- Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
- Under **CIDRs to provision**, enter 10.0.0.0/18, which will give this pool around 16,000 available IP addresses.

CIDRs to provision [Info](#)

CIDRs to be provisioned must either be available in the source pool's space, or in the scope's space if no source pool.

IP space visualization (source pool)

Zoom Overlapping New allocation Allocated Available

10.0.0.0/16 (100% available → 75% available after allocations)



CIDR

Enter a CIDR to be provisioned.

16K IPs

Remove

< > ^ v

Add specific CIDR

Add CIDR by size

10. Leave **Configure this pool's allocation rule settings** disabled. You will not be allocating CIDRs to VPCs directly from this pool. Instead, you will allocate them from a sub-pool that you create from this pool.

Allocation rule settings - optional [Info](#)




AWS best practice


We recommend you create a top-level pool and then Regional pools under the top-level pool. Under the Regional pools, create development pools. From the development pools you can configure allocation rules to control which resources can use CIDRs from these pools. For more examples of how to organize IPAM pools, see [Example IPAM pool plans](#).

Configure this pool's allocation rule settings

11. Choose **Create pool**.
12. Return to the **Pools** view to see the hierarchy of IPAM pools that you've created.



13. Repeat the steps in this section and create a second Regional pool in **us-west-2** locale with the CIDR **10.0.64.0/18** provisioned to it. When you complete that process, you'll have three pools in a hierarchy similar to this one:



Step 5: Create a pre-production development pool

Follow the steps in this section to create a development pool for pre-production resources within one of your Regional pools.

To create a pre-production development pool

1. In the same way that you did in the previous section, using the IPAM admin account, create a pool called **Pre-prod pool**, but this time use **Regional pool us-west-1** as the source pool.

Amazon VPC IP Address Manager > Pools > Create

Create pool in ipam-scope-0cbdc40f8f04fa968

Pool settings

Name (IPAM ID)

DemoIPAM (ipam-080d0c4b98089b437)

Name (Scope ID)

ipam-scope-0cbdc40f8f04fa968

Name tag - *optional*

Creates a tag with a key of 'Name' and a value that you specify. Tags are not visible to other accounts even if a pool is shared.

Description - *optional*

Write a brief description for the pool.

Pool hierarchy [Info](#)

Source pool

To provision a CIDR into this pool, it must be available in the source pool. If no source pool is selected, then the space must be available in the scope.

▼ Source pool summary

Name (Pool ID)

Regional pool us-west-1 (ipam-pool-03b74e706bb0df4ab)

Description

-

Provisioned CIDRs

10.0.0.0/18

Locale

us-west-1

2. Specify a CIDR of 10.0.0.0/20 to provision, which will give this pool around 4,000 IP addresses.

CIDRs to provision [Info](#)

CIDRs to be provisioned must either be available in the source pool's space, or in the scope's space if no source pool.

IP space visualization (source pool)

Zoom Overlapping New allocation Allocated Available

10.0.0.0/18 (100% available → 75% available after allocations)

CIDR

Enter a CIDR to be provisioned.

10.0.0.0/20 4K IPs Remove

< > ^ v

Add specific CIDR Add CIDR by size

3. Toggle the option for **Configure this pool's allocation rule settings**. Do the following:
 1. Under **CIDR management**, for **Automatically import discovered resources**, leave the default **Don't allow** option selected. This option would enable IPAM to automatically import resource CIDRs it discovers in the pool's locale. A detailed description of this option is outside the scope of this tutorial, but you can read more about the option in [Create a top-level IPv4 pool](#).
 2. Under **Netmask compliancy**, choose **/24** for the minimum, default, and maximum netmask length. A detailed description of this option is outside the scope of this tutorial, but you can read more about the option in [Create a top-level IPv4 pool](#). What's important to note is that the VPC that you create later with a CIDR from this pool will be limited to **/24** based on what we set here.
 3. Under **Tag compliance**, enter **environment/pre-prod**. This tag will be required for VPCs to allocate space from the pool. We will demonstrate later how this works.

Allocation rule settings - *optional* [Info](#)



AWS best practice

We recommend you create a top-level pool and then Regional pools under the top-level pool. Under the Regional pools, create development pools. From the development pools you can configure allocation rules to control which resources can use CIDRs from these pools. For more examples of how to organize IPAM pools, see [Example IPAM pool plans](#).

Configure this pool's allocation rule settings

CIDR management

Automatically import discovered resources

It is recommended to allow automatic import if this pool will be used to allocate CIDRs to resources such as VPCs.

- Allow automatic import
- Don't allow

Netmask compliancy

Minimum netmask length

The minimum netmask length for allocating resources within the pool.

/24 (256 IPs)

Default netmask length

The default netmask length used when IPAM allocates a CIDR from this pool to a resource.

/24 (256 IPs)

Maximum netmask length

The maximum netmask length for allocating resources within the pool.

/24 (256 IPs)

Tag compliancy

Tagging requirements

Add tagging requirements for resources in this pool.

Key

environment



Value - *optional*

pre-prod




Remove

Add new required tag

You can add up to 49 more tags.

4. Choose **Create pool**.

5. The pool hierarchy now includes an additional subpool under **Regional pool us-west-1**:



Now you're ready to share the IPAM pool with another member account in your organization and enable that account to allocate a CIDR from the pool to create a VPC.

Step 6: Share the IPAM pool

Follow the steps in this section to share the pre-production IPAM pool using Amazon Resource Access Manager (RAM).

This section consists of two subsections:


- [Step 6.1. Enable resource sharing in Amazon RAM](#): This step must be done by the Amazon Organizations management account.
- [Step 6.2. Share an IPAM pool using Amazon RAM](#): This step must be done by the IPAM admin.

Step 6.1. Enable resource sharing in Amazon RAM

After you create your IPAM, you'll want to share IP address pools with other accounts in your organization. Before you share an IPAM pool, complete the steps in this section to enable resource sharing with Amazon RAM.

To enable resource sharing

1. Using the Amazon Organizations management account, open the Amazon RAM console at <https://console.aws.amazon.com/ram/>.
2. In the left navigation pane, choose **Settings**, choose **Enable sharing with Amazon Organizations**, and then choose **Save settings**.



You can now share an IPAM pool with other members of the organization.

Step 6.2. Share an IPAM pool using Amazon RAM

In this section you'll share the pre-production development pool with another Amazon Organizations member account. For complete instructions on sharing IPAM pools, including information on the required IAM permissions, see [Share an IPAM pool using Amazon RAM](#).

To share an IPAM pool using Amazon RAM

1. Using the IPAM admin account, open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope, choose the pre-production IPAM pool, and choose **Actions > View details**.

- Under **Resource sharing**, choose **Create resource share**. The Amazon RAM console opens. You'll share the pool using Amazon RAM.
- Choose **Create a resource share**.

The screenshot shows the Amazon VPC IP Address Manager console. At the top, a green notification bar says "Sent request to provision 10.0.0/20". The breadcrumb navigation is "Amazon VPC IP Address Manager > Pools > ipam-pool-07bdd12d7c94e4693". The main heading is "Pre-prod pool (ipam-pool-07bdd12d7c94e4693)". Below this is a "Pool summary" section with a table of details:

| | | | |
|---|--------------------------|-----------------------------------|--|
| Pool ID ipam-pool-07bdd12d7c94e4693 | Description - | IPAM ID ipam-005f921c17ebd5107 | Scope ID ipam-scope-0a158dde35c51107b |
| Pool ARN arn:aws:ec2::320805250157:ipam-pool/ipam-pool-07bdd12d7c94e4693 | Owner ID 320805250157 | Compliance status - | Overlap status - |

Below the summary is a navigation bar with tabs: Pool details, Monitoring, IP space visualization, CIDRs, Allocations, Resources, Compliancy, Resource sharing (selected), and Tags. The "Resource sharing" tab is active, showing a "Create resource share" button highlighted with a red box. Below the button is a search bar "Filter resource shares" and a table with columns "Resource share ARN", "Status", and "Created at". The table is empty, and a message states "No shares. This resource is not part of any resource share." with a "Create resource share" button below it.

The Amazon RAM console opens.

- In the Amazon RAM console, choose **Create a resource share** again.
- Add a **Name** for the shared pool.
- Under **Select resource type**, choose **IPAM pools**, and then choose the ARN of the pre-production development pool.

Specify resource share details

Enter a name for the resource share and select the resources that you want to share.

Resource share name

Name

Provide a descriptive name for the resource share.

Resources - optional

Choose the resources to add to the resource share.

Select resource type

< 1 > ⚙

| <input type="checkbox"/> | ARN | Locale |
|-------------------------------------|---|-----------|
| <input type="checkbox"/> | arn:aws:ec2::320805250157:ipam-pool/ipam-pool-06fb4cace4bc1e551 | None |
| <input checked="" type="checkbox"/> | arn:aws:ec2::320805250157:ipam-pool/ipam-pool-07bdd12d7c94e4693 | us-west-1 |
| <input type="checkbox"/> | arn:aws:ec2::320805250157:ipam-pool/ipam-pool-0b8123821c7ef5319 | us-east-1 |
| <input type="checkbox"/> | arn:aws:ec2::320805250157:ipam-pool/ipam-pool-0d21e78124564dbb6 | us-west-2 |
| <input type="checkbox"/> | arn:aws:ec2::320805250157:ipam-pool/ipam-pool-0e0ed41b1a362ebc9 | us-west-1 |


Selected resources (1)

Deselect

| <input type="checkbox"/> | Resource ID ↗ | Resource Type |
|--------------------------|-------------------------------|---------------|
| <input type="checkbox"/> | ipam-pool-07bdd12d7c94e4693 | ec2:IpamPool |

9. Choose **Next**.

10. Leave the default **AWSRAMDefaultPermissionsIpamPool** permission selected. The details of the permission options are out of scope for this tutorial, but you can find out more about these options in [Share an IPAM pool using Amazon RAM](#).



11. Choose **Next**.

12. Under **Principals**, choose **Allow sharing only within your organization**. Enter your Amazon Organizations organization unit ID (as mentioned in [How Amazon Organizations integrates with IPAM](#)), and then choose **Add**.

Grant access to principals

Specify the principals that are allowed access to the shared resources. A principal can be any of the following: An entire organization or organizational unit (OU) in AWS Organizations, an AWS account, IAM role, or IAM user.

Principals - *optional*

Allow sharing with anyone

You can share resources with any AWS accounts, roles, and users. If you are in an organization, you can also share with the entire organization or organizational units in that organization.

Allow sharing only within your organization

You can share resources with the entire organization, organizational units, or AWS accounts, roles, and users in that organization.

Principals

You can add multiple principals of different types.

Organizational unit (OU) ▼

ou-fssg-q5brfv9c

Organizational unit ID format: ou-{4-32 characters}-{8-32 characters}.

Add

▼ Selected principals (0)

Deselect

The following principals will be allowed access to the shared resources.

| <input type="checkbox"/> | Principal ID | Type |
|--------------------------|--------------|------|
|--------------------------|--------------|------|

No selected principals.

Cancel

Previous

Next

13. Choose **Next**.

14. Review the resource share options and the principals that you'll be sharing with, and then choose **Create**.

Now that the pool has been shared, go to the next step to create a VPC with a CIDR allocated from an IPAM pool.

Step 7: Create a VPC with a CIDR allocated from an IPAM pool

Follow the steps in this section to create a VPC with a CIDR allocated from the pre-production pool. This step should be completed by the member account in the OU that the IPAM pool was shared

with in the previous section (called **example-member-account-2** in [How Amazon Organizations integrates with IPAM](#)). For more information about the IAM permissions that are required to create VPCs, see [Amazon VPC policy examples](#) in the *Amazon VPC User Guide*.

To create a VPC with a CIDR allocated from an IPAM pool

1. Using the member account, open the VPC console at <https://console.aws.amazon.com/vpc/> as the member account that you'll use as the developer account.
2. Choose **Create VPC**.
3. Do the following:
 1. Enter a name, such as **Example VPC**.
 2. Choose **IPAM-allocated IPv4 CIDR block**.
 3. Under **IPv4 IPAM pool**, choose the ID of the pre-production pool.
 4. Choose a **Netmask** length. Because you limited the available netmask length for this pool to /24 (in [Step 5: Create a pre-production development pool](#)), the only netmask option available is /24.

VPC > Your VPCs > Create VPC

Create VPC [Info](#)

A VPC is an isolated portion of the AWS Cloud populated by AWS objects, such as Amazon EC2 instances.

VPC settings

Resources to create [Info](#)
Create only the VPC resource or the VPC and other networking resources.

VPC only VPC and more

Name tag - optional
Creates a tag with a key of 'Name' and a value that you specify.

Example VPC

IPv4 CIDR block [Info](#)

IPv4 CIDR manual input
 IPAM-allocated IPv4 CIDR block

IPv4 IPAM pool

ipam-pool-0c4e32cfe1a0bb88f
us-west-1

The locale of the IPAM pool must be equal to the current region.

Netmask

/24 (allowed maximum) 256 IPs

- For demonstration purposes, under **Tags**, do not add any additional tags at this time. When you created the pre-prod pool (in [5. Create a pre-production development pool](#)), you added an allocation rule that required any VPCs that are created with CIDRs from this pool to have an environment/pre-prod tag. Leave the environment/pre-prod tag off for now so that you can see that an error appears telling you that a required tag was not added.
- Choose **Create VPC**.
- An error appears telling you that a required tag was not added. The error appears because you set an allocation rule when you created the pre-prod pool (in [Step 5: Create a pre-production development pool](#)). The allocation rule required any VPCs that are created with CIDRs from this pool to have an environment/pre-prod tag.

⊗ **There was an error creating your VPC**✕

The resource is missing one or more of the resource tags required by the IPAM pool.

VPC > Your VPCs > Create VPC

Create VPC [Info](#)

A VPC is an isolated portion of the AWS Cloud populated by AWS objects, such as Amazon EC2 instances.

VPC settings

Resources to create [Info](#)
Create only the VPC resource or the VPC and other networking resources.

VPC only VPC and more

Name tag - optional
Creates a tag with a key of 'Name' and a value that you specify.

Example VPC

IPv4 CIDR block [Info](#)

IPv4 CIDR manual input
 IPAM-allocated IPv4 CIDR block

7. Now, under **Tags**, add the tag **environment/pre-prod** and choose **Create VPC** again.

Tags

A tag is a label that you assign to an AWS resource. Each tag consists of a key and an optional value. You can use tags to search and filter your resources or track your AWS costs.

| Key | Value - optional | |
|--|--|--------|
| Q Name ✕ | Q Example VPC ✕ | Remove |
| Q environment ✕ | Q pre-prod ✕ | Remove |

Add new tag

You can add 48 more tags.

8. The VPC is created successfully, and the VPC complies with the tag rule on the pre-production pool:




✔ You successfully created vpc-07701f4fcc6549b8d / Example VPC

VPC > Your VPCs > vpc-07701f4fcc6549b8d

vpc-07701f4fcc6549b8d / Example VPC

Actions ▼

Details [Info](#)

| | | | |
|---|--|--|---|
| VPC ID  vpc-07701f4fcc6549b8d | State  Available | DNS hostnames Disabled | DNS resolution Enabled |
| Tenancy Default | DHCP option set dopt-0b14c6b1ccb2338bb | Main route table rtb-0a89b32824730ec5c | Main network ACL acl-0dee4236e2f7502c8 |
| Default VPC No | IPv4 CIDR 10.0.0.0/24 | IPv6 pool - | IPv6 CIDR - |
| Network Address Usage metrics Disabled | Route 53 Resolver DNS Firewall rule groups - | Owner ID  320805250157 | |

In the **Resources** pane of the IPAM console, the IPAM admin will be able to see and manage the VPC and its allocated CIDR. Note that it takes some time for the VPC to appear in the **Resources** pane.

Step 8: Cleanup

In this tutorial, you created an IPAM with a delegated admin, created multiple pools, and enabled a member account in your organization to allocate a VPC CIDR from a pool.

Follow the steps in this section to clean up the resources that you created in this tutorial.

To cleanup the resources created in this tutorial

1. Using the member account that created the example VPC, delete the VPC. For detailed instructions, see [Delete your VPC](#) in the *Amazon Virtual Private Cloud User Guide*.

- Using the IPAM admin account, delete the example resource share in the Amazon RAM console. For detailed instructions, see [Deleting a resource share in Amazon Amazon RAM](#) in the *Amazon Resource Access Manager User Guide*.
- Using the IPAM admin account, log into the RAM console and disable sharing with Amazon Organizations that you enable in [Step 6.1. Enable resource sharing in Amazon RAM](#).
- Using the IPAM admin account, delete the example IPAM by selecting the IPAM in the IPAM console and then choosing **Actions** > **Delete**. For detailed instructions, see [Delete an IPAM](#).
- When you're prompted to delete the IPAM, choose **Cascade delete**. This will delete all scopes and pools within the IPAM before deleting the IPAM.

Delete IPAM Demo IPAM (ipam-080d0c4b98089b437) ✕

Deleting this IPAM will permanently remove it. To confirm deletion, type *delete* in the field.

Cascade delete
Enables you to quickly delete an IPAM, private scopes, pools in private scopes, and any allocations in the pools in private scopes. You cannot delete the IPAM with this option if there is a pool in your public scope. No VPC resources will be deleted.

Cancel Delete

- Enter **delete** and then choose **Delete**.
- Using the Amazon Organizations management account, log into the IPAM console, choose **Settings**, and remove the delegated administrator account.
- (Optional) When you integrate IPAM with Amazon Organizations, [IPAM automatically creates a service-linked role in each member account](#). Using each Amazon Organizations member account, log into IAM and delete the **AWSServiceRoleForIPAM** service linked role in each member account.
- Cleanup is complete.

Tutorial: Create an IPAM and pools using the Amazon CLI

Follow the steps in this tutorial to use the Amazon CLI to create an IPAM, create IP address pools, and allocate a VPC with a CIDR from an IPAM pool.

The following is an example hierarchy of the pool structure that you will create by following the steps in this section:

- IPAM operating in Amazon Region 1, Amazon Region 2
 - Private scope
 - Top-level pool
 - Regional pool in Amazon Region 2
 - Development pool
 - Allocation for a VPC

Note

In this section, you'll create an IPAM. By default, you can only create one IPAM. For more information, see [Quotas for your IPAM](#). If you have already delegated an IPAM account and created an IPAM, you can skip steps 1 and 2.

Contents

- [Step 1: Enable IPAM in your organization](#)
- [Step 2: Create an IPAM](#)
- [Step 3: Create an IPv4 address pool](#)
- [Step 4: Provision a CIDR to the top-level pool](#)
- [Step 5. Create a Regional pool with CIDR sourced from the top-level pool](#)
- [Step 6: Provision a CIDR to the Regional pool](#)
- [Step 7. Create a RAM share for enabling IP assignments across accounts](#)
- [Step 8. Create a VPC](#)
- [Step 9. Cleanup](#)

Step 1: Enable IPAM in your organization

This step is optional. Complete this step to enable IPAM in your organization and configure your delegated IPAM using the Amazon CLI. For more information about the role of the IPAM account, see [Integrate IPAM with accounts in an Amazon Organization](#).

This request must be made from an Amazon Organizations management account. When you run the following command, ensure that you're using a role with an IAM policy that permits the following actions:

- `ec2:EnableIpamOrganizationAdminAccount`
- `organizations:EnableAwsServiceAccess`
- `organizations:RegisterDelegatedAdministrator`
- `iam:CreateServiceLinkedRole`

```
aws ec2 enable-ipam-organization-admin-account --region us-east-1 --delegated-admin-account-id 111111111111
```

You should see the following output, indicating that enabling was successful.

```
{
  "Success": true
}
```

Step 2: Create an IPAM

Follow the steps in this section to create an IPAM and view additional information about the scopes that are created. You will use this IPAM when you create pools and provision IP address ranges for those pools in later steps.

Note

The operating Regions option determines which Amazon Regions the IPAM pools can be used for. For more information about operating Regions, see [Create an IPAM](#).

To create an IPAM using the Amazon CLI

1. Run the following command to create the IPAM instance.

```
aws ec2 create-ipam --description my-ipam --region us-east-1 --operating-  
regions RegionName=us-west-2
```

When you create an IPAM, Amazon automatically does the following:

- Returns a globally unique resource ID (IpamId) for the IPAM.
- Creates a default public scope (PublicDefaultScopeId) and a default private scope (PrivateDefaultScopeId).

```
{  
  
  "Ipam": {  
    "OwnerId": "123456789012",  
    "IpamId": "ipam-0de83dba6694560a9",  
    "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",  
    "PublicDefaultScopeId": "ipam-scope-02a24107598e982c5",  
    "PrivateDefaultScopeId": "ipam-scope-065e7dfe880df679c",  
    "ScopeCount": 2,  
    "Description": "my-ipam",  
    "OperatingRegions": [  
      {  
        "RegionName": "us-west-2"  
      },  
      {  
        "RegionName": "us-east-1"  
      }  
    ],  
    "Tags": []  
  }  
}
```

2. Run the following command to view additional information related to the scopes. The public scope is intended for IP addresses that are going to be accessed via public internet. The private scope is intended for IP addresses that are not going to be accessed via public internet.

```
aws ec2 describe-ipam-scopes --region us-east-1
```

In the output, you see the available scopes. You'll use the private scope ID in the next step.

```
{
  "IpamScopes": [
    {
      "OwnerId": "123456789012",
      "IpamScopeId": "ipam-scope-02a24107598e982c5",
      "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-02a24107598e982c5",
      "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",
      "IpamScopeType": "public",
      "IsDefault": true,
      "PoolCount": 0
    },
    {
      "OwnerId": "123456789012",
      "IpamScopeId": "ipam-scope-065e7dfe880df679c",
      "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-065e7dfe880df679c",
      "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",
      "IpamScopeType": "private",
      "IsDefault": true,
      "PoolCount": 0
    }
  ]
}
```

Step 3: Create an IPv4 address pool

Follow the steps in this section to create an IPv4 address pool.

Important

You won't use the `--locale` option on this top-level pool. You will set the locale option later on the Regional pool. The locale is the AWS Region where you want a pool to be available for CIDR allocations. As a result of not setting the locale on the top-level pool, the locale will default to None. If a pool has a locale of None, the pool won't be available to VPC resources in any Amazon Region. You can only manually allocate IP address space in the pool to reserve space.

To create an IPv4 address pool for all of your Amazon resources using the Amazon CLI

1. Run the following command to create an IPv4 address pool. Use the ID of the private scope of the IPAM that you created in the previous step.

```
aws ec2 create-ipam-pool --ipam-scope-id ipam-scope-065e7dfe880df679c --  
description "top-level-pool" --address-family ipv4
```

In the output, you'll see a state of `create-in-progress` for the pool.

```
{  
  "IpamPool": {  
    "OwnerId": "123456789012",  
    "IpamPoolId": "ipam-pool-0008f25d7187a08d9",  
    "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-  
pool-0008f25d7187a08d9",  
    "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-  
scope-065e7dfe880df679c",  
    "IpamScopeType": "private",  
    "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",  
    "Locale": "None",  
    "PoolDepth": 1,  
    "State": "create-in-progress",  
    "Description": "top-level-pool",  
    "AutoImport": false,  
    "AddressFamily": "ipv4",  
    "Tags": []  
  }  
}
```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools
```

The following example output shows the correct state.

```
{  
  "IpamPools": [  
    {  
      "OwnerId": "123456789012",  
      "IpamPoolId": "ipam-pool-0008f25d7187a08d9",
```

```

        "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0008f25d7187a08d9",
        "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-065e7dfe880df679c",
        "IpamScopeType": "private",
        "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",
        "Locale": "None",
        "PoolDepth": 1,
        "State": "create-complete",
        "Description": "top-level-pool",
        "AutoImport": false,
        "AddressFamily": "ipv4"
    }
]
}

```

Step 4: Provision a CIDR to the top-level pool

Follow the steps in this section to provision a CIDR to the top-level pool, and then verify that the CIDR is provisioned. For more information, see [Provision CIDRs to a pool](#).

To provision a CIDR block to the pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 provision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-
pool-0008f25d7187a08d9 --cidr 10.0.0.0/8
```

In the output, you can verify the state of the provisioning.

```

{
  "IpamPoolCidr": {
    "Cidr": "10.0.0.0/8",
    "State": "pending-provision"
  }
}

```

2. Run the following command until you see a state of provisioned in the output.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-pool-0008f25d7187a08d9
```

The following example output shows the correct state.

```
{
  "IpamPoolCidrs": [
    {
      "Cidr": "10.0.0.0/8",
      "State": "provisioned"
    }
  ]
}
```

Step 5. Create a Regional pool with CIDR sourced from the top-level pool

When you create an IPAM pool, the pool belongs to the Amazon Region of the IPAM by default. When you create a VPC, the pool that the VPC draws from must be in the same Region as the VPC. You can use the `--locale` option when you create a pool to make the pool available to services in a Region other than the Region of the IPAM. Follow the steps in this section to create a Regional pool in another locale.

To create a pool with a CIDR sourced from the previous pool using the Amazon CLI

1. Run the following command to create the pool and insert space with a known available CIDR from the previous pool.

```
aws ec2 create-ipam-pool --description "regional--pool" --region us-east-1 --ipam-scope-id ipam-scope-065e7dfe880df679c --source-ipam-pool-id ipam-pool-0008f25d7187a08d9 --locale us-west-2 --address-family ipv4
```

In the output, you'll see the ID of the pool that you created. You'll need this ID in the next step.

```
{
  "IpamPool": {
    "OwnerId": "123456789012",
    "IpamPoolId": "ipam-pool-0da89c821626f1e4b",
  }
}
```

```

    "SourceIpamPoolId": "ipam-pool-0008f25d7187a08d9",
    "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0da89c821626f1e4b",
    "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-065e7dfe880df679c",
    "IpamScopeType": "private",
    "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",
    "Locale": "us-west-2",
    "PoolDepth": 2,
    "State": "create-in-progress",
    "Description": "regional--pool",
    "AutoImport": false,
    "AddressFamily": "ipv4",
    "Tags": []
  }
}

```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools
```

In the output, you see the pools that you have in your IPAM. In this tutorial, we created a top-level and a Regional pool, so you'll see them both.

```

{
  "IpamPools": [
    {
      "OwnerId": "123456789012",
      "IpamPoolId": "ipam-pool-0008f25d7187a08d9",
      "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0008f25d7187a08d9",
      "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-065e7dfe880df679c",
      "IpamScopeType": "private",
      "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",
      "Locale": "None",
      "PoolDepth": 1,
      "State": "create-complete",
      "Description": "top-level-pool",
      "AutoImport": false,
      "AddressFamily": "ipv4"
    },
    {

```

```

        "OwnerId": "123456789012",
        "IpamPoolId": "ipam-pool-0da89c821626f1e4b",
        "SourceIpamPoolId": "ipam-pool-0008f25d7187a08d9",
        "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0da89c821626f1e4b",
        "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-065e7dfe880df679c",
        "IpamScopeType": "private",
        "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-0de83dba6694560a9",
        "Locale": "us-west-2",
        "PoolDepth": 2,
        "State": "create-complete",
        "Description": "regional--pool",
        "AutoImport": false,
        "AddressFamily": "ipv4"
    }
]
}

```

Step 6: Provision a CIDR to the Regional pool

Follow the steps in this section to assign a CIDR block to the pool, and validate that it's been successfully provisioned.

To assign a CIDR block to the Regional pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 provision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-
pool-0da89c821626f1e4b --cidr 10.0.0.0/16
```

In the output, you see the state of the pool.

```
{
  "IpamPoolCidr": {
    "Cidr": "10.0.0.0/16",
    "State": "pending-provision"
  }
}
```

2. Run the following command until you see the state of provisioned in the output.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-pool-0da89c821626f1e4b
```

The following example output shows the correct state.

```
{
  "IpamPoolCidrs": [
    {
      "Cidr": "10.0.0.0/16",
      "State": "provisioned"
    }
  ]
}
```

3. Run the following command to query the top-level pool to view the allocations. The Regional pool is considered an allocation within the top-level pool.

```
aws ec2 get-ipam-pool-allocations --region us-east-1 --ipam-pool-id ipam-pool-0008f25d7187a08d9
```

In the output, you see the Regional pool as an allocation in the top-level pool.

```
{
  "IpamPoolAllocations": [
    {
      "Cidr": "10.0.0.0/16",
      "IpamPoolAllocationId": "ipam-pool-alloc-fbd525f6c2bf4e77a75690fc2d93479a",
      "ResourceId": "ipam-pool-0da89c821626f1e4b",
      "ResourceType": "ipam-pool",
      "ResourceOwner": "123456789012"
    }
  ]
}
```

Step 7. Create a RAM share for enabling IP assignments across accounts

This step is optional. You can complete this step only if you completed [Integrate IPAM with accounts in an Amazon Organization](#).

When you create an IPAM pool Amazon RAM share, it enables IP assignments across accounts. RAM sharing is only available in your home Amazon Region. Note that you create this share in the same Region as the IPAM, not in the local Region for the pool. All administrative operations on IPAM resources are made through the home Region of your IPAM. The example in this tutorial creates a single share for a single pool, but you can add multiple pools to a single share. For more information, including an explanation of the options that you must enter, see [Share an IPAM pool using Amazon RAM](#).

Run the following command to create a resource share.

```
aws ram create-resource-share --region us-east-1 --name pool_share --resource-arns arn:aws:ec2::123456789012:ipam-pool/ipam-pool-0dec9695bca83e606 --principals 123456
```

The output shows that the pool was created.

```
{
  "resourceShare": {
    "resourceShareArn": "arn:aws:ram:us-west-2:123456789012:resource-share/3ab63985-99d9-1cd2-7d24-75e93EXAMPLE",
    "name": "pool_share",
    "owningAccountId": "123456789012",
    "allowExternalPrincipals": false,
    "status": "ACTIVE",
    "creationTime": 1565295733.282,
    "lastUpdatedTime": 1565295733.282
  }
}
```

Step 8. Create a VPC

Run the following command to create a VPC and assign a CIDR block to the VPC from the pool in your newly created IPAM.

```
aws ec2 create-vpc --region us-east-1 --ipv4-ipam-pool-id ipam-pool-04111dca0d960186e --cidr-block 10.0.0.0/24
```

The output shows that the VPC was created.

```
{
  "Vpc": {
```

```
"CidrBlock": "10.0.0.0/24",
"DhcpOptionsId": "dopt-19edf471",
"State": "pending",
"VpcId": "vpc-0983f3c454f3d8be5",
"OwnerId": "123456789012",
"InstanceTenancy": "default",
"Ipv6CidrBlockAssociationSet": [],
"CidrBlockAssociationSet": [
  {
    "AssociationId": "vpc-cidr-assoc-00b24cc1c2EXAMPLE",
    "CidrBlock": "10.0.0.0/24",
    "CidrBlockState": {
      "State": "associated"
    }
  }
],
"IsDefault": false
}
```

Step 9. Cleanup

Follow the steps in this section to delete the IPAM resources you've created in this tutorial.

1. Delete the VPC.

```
aws ec2 delete-vpc --vpc-id vpc-0983f3c454f3d8be5
```

2. Delete the IPAM pool RAM share.

```
aws ram delete-resource-share --resource-share-arn arn:aws:ram:us-
west-2:123456789012:resource-share/3ab63985-99d9-1cd2-7d24-75e93EXAMPLE
```

3. Deprovision pool CIDR from the Regional pool.

```
aws ec2 deprovision-ipam-pool-cidr --ipam-pool-id ipam-pool-0da89c821626f1e4b --
region us-east-1
```

4. Deprovision pool CIDR from the top-level pool.

```
aws ec2 deprovision-ipam-pool-cidr --ipam-pool-id ipam-pool-0008f25d7187a08d9 --
region us-east-1
```


5. Delete the IPAM

```
aws ec2 delete-ipam --region us-east-1
```

Tutorial: View IP address history using the Amazon CLI

The scenarios in this section show you how to analyze and audit IP address usage using the Amazon CLI. For general information about using the Amazon CLI, see [Using the Amazon CLI](#) in the *Amazon Command Line Interface User Guide*.

Contents

- [Overview](#)
- [Scenarios](#)

Overview

IPAM automatically retains your IP address monitoring data for up to three years. You can use the historical data to analyze and audit your network security and routing policies. You can search for historical insights for the following types of resources:

- VPCs
- VPC subnets
- Elastic IP addresses
- EC2 instances that are running
- EC2 network interfaces attached to instances

Important

Although IPAM doesn't monitor Amazon EC2 instances or EC2 network interfaces attached to instances, you can use the Search IP history feature to search for historical data on EC2 instance and network interface CIDRs.

Note

- The commands in this tutorial must be run using the account that owns the IPAM and the Amazon Region that hosts the IPAM.
- Records of changes to CIDRs are picked up in periodic snapshots, which means that it can take some time for records to appear or be updated, and the values for `SampledStartTime` and `SampledEndTime` can differ from the actual times they occurred.

Scenarios

The scenarios in this section show you how to analyze and audit IP address usage using the Amazon CLI. For more information about the values mentioned in this tutorial like sampled end time and start time, see [View IP address history](#).

Scenario 1: Which resources were associated with 10.2.1.155/32 between 1:00 AM and 9:00 PM on December 27, 2021 (UTC)?

1. Run the following command:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 10.2.1.155/32 --ipam-scope-id ipam-scope-05b579a1909c5fc7a --start-time 2021-12-20T01:00:00.000Z --end-time 2021-12-27T21:00:00.000Z
```

2. View the results of the analysis. In the example below, the CIDR was allocated to a network interface and EC2 instance over the course of the time period. Note that no **SampledEndTime** value means the record is still active. For more information about the values shown in the following output, see [View IP address history](#).

```
{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "network-interface",
      "ResourceId": "eni-0b4e53eb1733aba16",
      "ResourceCidr": "10.2.1.155/32",
      "VpcId": "vpc-0f5ee7e1ba908a378",
      "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
```

```

    },
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "instance",
      "ResourceId": "i-064da1f79baed14f3",
      "ResourceCidr": "10.2.1.155/32",
      "VpcId": "vpc-0f5ee7e1ba908a378",
      "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    }
  ]
}

```

If the owner ID of the instance to which a network interface is attached differs from the owner ID of the network interface (as is the case for NAT gateways, Lambda network interfaces in VPCs, and other Amazon services), the `ResourceOwnerId` is `amazon-aws` rather than the account ID of the owner of the network interface. The following example shows the record for a CIDR associated with a NAT gateway:

```

{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "network-interface",
      "ResourceId": "eni-0b4e53eb1733aba16",
      "ResourceCidr": "10.0.0.176/32",
      "VpcId": "vpc-0f5ee7e1ba908a378",
      "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    },
    {
      "ResourceOwnerId": "amazon-aws",
      "ResourceRegion": "us-east-1",
      "ResourceType": "instance",
      "ResourceCidr": "10.0.0.176/32",
      "VpcId": "vpc-0f5ee7e1ba908a378",
      "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    }
  ]
}

```

Scenario 2: Which resources were associated with 10.2.1.0/24 from December 1, 2021 to December 27, 2021 (UTC)?

1. Run the following command:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 10.2.1.0/24 --ipam-scope-id ipam-scope-05b579a1909c5fc7a --start-time 2021-12-01T00:00:00.000Z --end-time 2021-12-27T23:59:59.000Z
```

2. View the results of the analysis. In the example below, the CIDR was allocated to a subnet and VPC over the course of the time period. Note that no **SampledEndTime** value means the record is still active. For more information about the values shown in the following output, see [View IP address history](#).

```
{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "subnet",
      "ResourceId": "subnet-0864c82a42f5bffd",
      "ResourceCidr": "10.2.1.0/24",
      "VpcId": "vpc-0f5ee7e1ba908a378",
      "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    },
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "vpc",
      "ResourceId": "vpc-0f5ee7e1ba908a378",
      "ResourceCidr": "10.2.1.0/24",
      "ResourceComplianceStatus": "compliant",
      "ResourceOverlapStatus": "nonoverlapping",
      "VpcId": "vpc-0f5ee7e1ba908a378",
      "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    }
  ]
}
```

Scenario 3: Which resources were associated with 2605:9cc0:409::/56 from December 1, 2021 to December 27, 2021 (UTC)?

1. Run the following command, where --region is the IPAM home Region:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 2605:9cc0:409::/56 --
ipam-scope-id ipam-scope-07cb485c8b4a4d7cc --start-time 2021-12-01T01:00:00.000Z --
end-time 2021-12-27T23:59:59.000Z
```

2. View the results of the analysis. In the example below, the CIDR was allocated to two different VPCs over the course of the time period in a Region outside the IPAM home Region. Note that no **SampledEndTime** value means the record is still active. For more information about the values shown in the following output, see [View IP address history](#).

```
{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-2",
      "ResourceType": "vpc",
      "ResourceId": "vpc-01d967bf3b923f72c",
      "ResourceCidr": "2605:9cc0:409::/56",
      "ResourceName": "First example VPC",
      "ResourceComplianceStatus": "compliant",
      "ResourceOverlapStatus": "nonoverlapping",
      "VpcId": "vpc-01d967bf3b923f72c",
      "SampledStartTime": "2021-12-23T20:02:00.701000+00:00",
      "SampledEndTime": "2021-12-23T20:12:59.848000+00:00"
    },
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-2",
      "ResourceType": "vpc",
      "ResourceId": "vpc-03e62c7eca81cb652",
      "ResourceCidr": "2605:9cc0:409::/56",
      "ResourceName": "Second example VPC",
      "ResourceComplianceStatus": "compliant",
      "ResourceOverlapStatus": "nonoverlapping",
      "VpcId": "vpc-03e62c7eca81cb652",
      "SampledStartTime": "2021-12-27T15:11:00.046000+00:00"
    }
  ]
}
```

```
}

```

Scenario 4: Which resources were associated with 10.0.0.0/24 in the last 24 hours (assuming the current time is midnight on December 27, 2021 (UTC))?

1. Run the following command:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 10.0.0.0/24 --ipam-
scope-id ipam-scope-05b579a1909c5fc7a --start-time 2021-12-27T00:00:00.000Z

```

2. View the results of the analysis. In the example below, the CIDR has been allocated to numerous subnets and VPCs over the time period. Note that no **SampledEndTime** value means the record is still active. For more information about the values shown in the following output, see [View IP address history](#).

```
{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-2",
      "ResourceType": "subnet",
      "ResourceId": "subnet-0d1b8f899725aa72d",
      "ResourceCidr": "10.0.0.0/24",
      "ResourceName": "Example name",
      "VpcId": "vpc-042b8a44f64267d67",
      "SampledStartTime": "2021-12-11T16:35:59.074000+00:00",
      "SampledEndTime": "2021-12-28T15:34:00.017000+00:00"
    },
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-2",
      "ResourceType": "vpc",
      "ResourceId": "vpc-09754dfd85911abec",
      "ResourceCidr": "10.0.0.0/24",
      "ResourceName": "Example name",
      "ResourceComplianceStatus": "unmanaged",
      "ResourceOverlapStatus": "overlapping",
      "VpcId": "vpc-09754dfd85911abec",
      "SampledStartTime": "2021-12-27T20:07:59.947000+00:00",
      "SampledEndTime": "2021-12-28T15:34:00.017000+00:00"
    }
  ],
}
```

```

    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-west-2",
      "ResourceType": "vpc",
      "ResourceId": "vpc-0a8347f594bea5901",
      "ResourceCidr": "10.0.0.0/24",
      "ResourceName": "Example name",
      "ResourceComplianceStatus": "unmanaged",
      "ResourceOverlapStatus": "overlapping",
      "VpcId": "vpc-0a8347f594bea5901",
      "SampledStartTime": "2021-12-11T16:35:59.318000+00:00"
    },
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "subnet",
      "ResourceId": "subnet-0af7eadb0798e9148",
      "ResourceCidr": "10.0.0.0/24",
      "ResourceName": "Example name",
      "VpcId": "vpc-03298ba16756a8736",
      "SampledStartTime": "2021-12-14T21:07:22.357000+00:00"
    }
  ]
}

```

Scenario 5: Which resources are currently associated with 10.2.1.155/32?

1. Run the following command:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 10.2.1.155/32 --ipam-scope-id ipam-scope-05b579a1909c5fc7a
```

2. View the results of the analysis. In the example below, the CIDR was allocated to a network interface and EC2 instance over the time period. Note that no **SampledEndTime** value means the record is still active. For more information about the values shown in the following output, see [View IP address history](#).

```

{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",

```

```

    "ResourceRegion": "us-east-1",
    "ResourceType": "network-interface",
    "ResourceId": "eni-0b4e53eb1733aba16",
    "ResourceCidr": "10.2.1.155/32",
    "VpcId": "vpc-0f5ee7e1ba908a378",
    "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
  },
  {
    "ResourceOwnerId": "123456789012",
    "ResourceRegion": "us-east-1",
    "ResourceType": "instance",
    "ResourceId": "i-064da1f79baed14f3",
    "ResourceCidr": "10.2.1.155/32",
    "VpcId": "vpc-0f5ee7e1ba908a378",
    "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
  }
]
}

```

Scenario 6: Which resources are currently associated with 10.2.1.0/24?

1. Run the following command:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 10.2.1.0/24 --ipam-scope-id ipam-scope-05b579a1909c5fc7a
```

2. View the results of the analysis. In the example below, the CIDR was allocated to a VPC and subnet over the time period. Only the results that match this exact /24 CIDR are returned, not all /32 within the /24 CIDR. Note that no **SampledEndTime** value means the record is still active. For more information about the values shown in the following output, see [View IP address history](#).

```

{
  "HistoryRecords": [
    {
      "ResourceOwnerId": "123456789012",
      "ResourceRegion": "us-east-1",
      "ResourceType": "subnet",
      "ResourceId": "subnet-0864c82a42f5bffd",
      "ResourceCidr": "10.2.1.0/24",
      "VpcId": "vpc-0f5ee7e1ba908a378",

```



```

        "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    },
    {
        "ResourceOwnerId": "123456789012",
        "ResourceRegion": "us-east-1",
        "ResourceType": "vpc",
        "ResourceId": "vpc-0f5ee7e1ba908a378",
        "ResourceCidr": "10.2.1.0/24",
        "ResourceComplianceStatus": "compliant",
        "ResourceOverlapStatus": "nonoverlapping",
        "VpcId": "vpc-0f5ee7e1ba908a378",
        "SampledStartTime": "2021-12-27T20:08:46.672000+00:00"
    }
]
}

```

Scenario 7: Which resources are currently associated with 54.0.0.9/32?

In this example, 54.0.0.9/32 is assigned to an Elastic IP address that is not part of the Amazon Organization integrated with your IPAM.

1. Run the following command:

```
aws ec2 get-ipam-address-history --region us-east-1 --cidr 54.0.0.9/32 --ipam-scope-id ipam-scope-05b579a1909c5fc7a
```

2. Since 54.0.0.9/32 is assigned to an Elastic IP address that is not part of the Amazon Organization integrated with the IPAM in this example, no records are returned.

```

{
  "HistoryRecords": []
}

```

Tutorial: Bring your ASN to IPAM

If your applications are using trusted IP addresses and Autonomous System Numbers (ASNs) that your partners or customers have allow listed in their network, you can run these applications in Amazon without requiring your partners or customers to change their allow lists.

An Autonomous System Number (ASN) is a globally unique number which enables a group of networks to be identified over the internet and exchange routing data with other networks dynamically using [Border Gateway Protocol](#). Internet service providers (ISPs), for example, use ASNs to identify the network traffic source. Not all organizations purchase their own ASNs, but for organizations which do, they can bring their ASN to Amazon.

Bring your own autonomous system number (BYOASN) enables you to advertise the IP addresses that you bring to Amazon with your own public ASN instead of the Amazon ASN. When you use BYOASN, the traffic originating from your IP address carries your ASN instead of the Amazon ASN, and your workloads are reachable by customers or partners that have allow listed traffic based on your IP address and ASN.

Important

- Complete this tutorial using the IPAM admin account in your IPAM's home Region.
- This tutorial assumes you own the public ASN you'd like to bring to IPAM and that you've already brought a BYOIP CIDR to Amazon and provisioned it to a pool in your public scope. You can bring an ASN to IPAM at any time, but to use it, you have to associate with a CIDR that you've brought to your Amazon account. This tutorial assumes that you have already done that. For more information, see [Tutorial: Bring your IP addresses to IPAM](#).
- You can change between your advertising your own ASN or an Amazon ASN without delay, but you are limited to changing from an Amazon ASN to your own ASN once per hour.
- If your BYOIP CIDR is currently advertised, you do not have to withdraw it from advertising to associate with your ASN.

Onboarding prerequisites for your ASN

You will need the following to complete this tutorial:

- Your public 2-byte or 4-byte ASN.
- If you've already brought an IP address range to Amazon with [Tutorial: Bring your IP addresses to IPAM](#), you need the IP address CIDR range. You'll also need a private key. You can use the private key that you created when you brought the IP address CIDR range to Amazon or you can create a new private key as described in [Create a private key and generate an X.509 certificate](#) in the *EC2 User Guide*.

- When you bring an IP address range to Amazon with [Tutorial: Bring your IP addresses to IPAM](#), you [create an X.509 certificate](#) and [upload the X.509 certificate to the RDAP record in your RIR](#). You must upload the same certificate you created to the RDAP record in your RIR for the ASN. Be sure to include the -----BEGIN CERTIFICATE----- and -----END CERTIFICATE----- strings before and after the encoded portion. All of this content must be on a single, long line. The procedure for updating RDAP depends on your RIR:
 - For ARIN, use the [Account Manager portal](#) to add the certificate in the "Public Comments" section for the "Network Information" object representing your ASN by using the "Modify ASN" option. Do not add it to the comments section for your organization.
 - For RIPE, add the certificate as a new "descr" field to the "aut-num" object representing your ASN. These can usually be found in the "My Resources" section of the [RIPE Database portal](#). Do not add it to the comments section for your organization or the "remarks" field of the "aut-num" object.
 - For APNIC, email the certificate to helpdesk@apnic.net to manually add it to the "remarks" field for your ASN. Send the email using the APNIC authorized contact for the ASN.

Tutorial steps

Complete the steps below using the Amazon console or the Amazon CLI.

Amazon Management Console

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
 2. In the left navigation pane, choose **IPAMs**.
 3. Choose your IPAM.
 4. Choose the **BYOASNs** tab and choose **Provision BYOASNs**.
 5. Enter the **ASN**. As a result, the **Message** field is automatically populated with the message you will need to sign in the next step.
 - The format of the message is as follows, where ACCOUNT is your Amazon account number, ASN is the ASN you are bringing to IPAM, and YYYYMMDD is the expiry date of the message (which defaults to the last day of the next month). Example:
- ```
text_message="1|aws|ACCOUNT|ASN|YYYYMMDD|SHA256|RSAPSS"
```
6. Copy the message and replace the expiry date with your own value if you want to.

7. Sign the message using the private key. Example:

```
signed_message=$(echo -n $text_message | openssl dgst -sha256 -sigopt
rsa_padding_mode:pss -sigopt rsa_pss_saltlen:-1 -sign private-key.pem -keyform
PEM | openssl base64 | tr -- '+=/' '-_~' | tr -d "\n")
```

8. Under **Signature**, enter the signature.
9. (Optional) To provision another ASN, choose **Provision another ASN**. You can provision up to 5 ASNs. To increase this quota, see [Quotas for your IPAM](#).
10. Choose **Provision**.
11. View the provisioning process in the **BYOASNs** tab. Wait for the **State** to change from *Pending-provision* to *Provisioned*. BYOASNs in a *Failed-provision* state are automatically removed after 7 days. Once the ASN is successfully provisioned, you can associate it with a BYOIP CIDR.
12. In the left navigation pane, choose **Pools**.
13. Choose your public scope. For more information about scopes, see [How IPAM works](#).
14. Choose a regional pool that has a BYOIP CIDR provisioned to it. The pool must have **Service** set to **EC2** and must have a locale chosen.
15. Choose the **CIDRs** tab and select a BYOIP CIDR.
16. Choose **Actions > Manage BYOASN associations**.
17. Under **Associated BYOASNs**, choose the ASN you brought to Amazon. If you have multiple ASNs, you can associate multiple ASNs to the BYOIP CIDR. You can associate as many ASNs as you can bring to IPAM. Note that you can bring up to 5 ASNs to IPAM by default. For more information, see [Quotas for your IPAM](#).
18. Choose **Associate**.
19. Wait for the ASN association to complete. Once the ASN is successfully associated with the BYOIP CIDR, you can advertise the BYOIP CIDR again.
20. Choose the pool **CIDRs** tab.
21. Select the BYOIP CIDR and choose **Actions > Advertise**. As a result, your ASN options are displayed: the Amazon ASN and any ASNs you've brought to IPAM.
22. Select the ASN you brought to IPAM and choose **Advertise CIDR**. As a result, the BYOIP CIDR is advertised and the value in the **Advertising** column changes from *Withdrawn* to *Advertised*. The **Autonomous System Number** column displays the ASN associated with the CIDR.

23. (optional) If you decide that you want to change the ASN association back to the Amazon ASN, select the BYOIP CIDR and choose **Actions** > **Advertise** again. This time, choose the Amazon ASN. You can swap back to the Amazon ASN at any time, but you can only change to a custom ASN once every hour.

The tutorial is complete.

## Cleanup

1. Disassociate the ASN from the BYOIP CIDR
  - To withdraw the BYOIP CIDR from advertising, in your pool in the public scope, choose the BYOIP CIDR and choose **Actions** > **Withdraw from advertising**.
  - To disassociate the ASN from the CIDR, choose **Actions** > **Manage BYOASN associations**.
2. Deprovision the ASN
  - To deprovision the ASN, in the BYOASNs tab, choose the ASN and choose **Deprovision ASN**. As a result, the ASN is deprovisioned. BYOASNs in a *Deprovisioned* state are automatically removed after 7 days.

Cleanup is complete.

## Command line

1. Provision your ASN by including your ASN and authorization message. The signature is the message signed with your private key.

```
aws ec2 provision-ipam-byoasn --ipam-id $ipam_id --asn 12345 --asn-authorization-context Message="$text_message",Signature="$signed_message"
```

2. Describe your ASN to track the provisioning process. If the request succeeds, you should see the *ProvisionStatus* set to *provisioned* after a few minutes.

```
aws ec2 describe-ipam-byoasn
```

3. Associate your ASN with your BYOIP CIDR. Any custom ASN you wish to advertise from must first be associated with your CIDR.

```
aws ec2 associate-ipam-byoasn --asn 12345 --cidr xxx.xxx.xxx.xxx/n
```

#### 4. Describe your CIDR to track the association process.

```
aws ec2 describe-byoip-cidrs --max-results 10
```

#### 5. Advertise your CIDR with your ASN. If the CIDR is already advertised, this will swap the origin ASN from Amazon's to yours.

```
aws ec2 advertise-byoip-cidr --asn 12345 --cidr xxx.xxx.xxx.xxx/n
```

#### 6. Describe your CIDR to see the ASN state change from *associated* to *advertised*.

```
aws ec2 describe-byoip-cidrs --max-results 10
```

The tutorial is complete.

### Cleanup

#### 1. Do one of the following:

- To withdraw just your ASN advertisement and go back to using the Amazon ASNs while keeping the CIDR advertised you must call `advertise-byoip-cidr` with the special Amazon value for the `asn` parameter. You can swap back to the Amazon ASN at any time, but you can only change to a custom ASN once every hour.

```
aws ec2 advertise-byoip-cidr --asn AWS --cidr xxx.xxx.xxx.xxx/n
```

- To withdraw your CIDR and ASN advertisement simultaneously, you can call `withdraw-byoip-cidr`.

```
aws ec2 withdraw-byoip-cidr --cidr xxx.xxx.xxx.xxx/n
```

#### 2. To clean up your ASN, you must first disassociate it from your BYOIP CIDR.

```
aws ec2 disassociate-ipam-byoasn --asn 12345 --cidr xxx.xxx.xxx.xxx/n
```

#### 3. Once your ASN is disassociated from all the BYOIP CIDRs with which you associated it, you can deprovision it.

```
aws ec2 deprovision-ipam-byoasn --ipam-id $ipam_id --asn 12345
```

4. The BYOIP CIDR can also be deprovisioned once all ASN associations are removed.

```
aws ec2 deprovision-ipam-pool-cidr --ipam-pool-id ipam-pool-1234567890abcdef0 --
cidr xxx.xxx.xxx.xxx/n
```

5. Confirm the deprovisioning.

```
aws ec2 get-ipam-pool-cidrs --ipam-pool-id ipam-pool-1234567890abcdef0
```

Cleanup is complete.

## Tutorial: Bring your IP addresses to IPAM

The tutorials in this section walk you through the process of bringing public IP address space to Amazon and managing the space with IPAM.

Managing public IP address space with IPAM has the following benefits:

- **Improves public IP addresses utilization across your organization:** You can use IPAM to share IP address space across Amazon accounts. Without using IPAM, you cannot share your public IP space across Amazon Organizations accounts.
- **Simplifies the process of bringing public IP space to Amazon:** You can use IPAM to onboard public IP address space once, and then use IPAM to distribute your public IPs across Regions. Without IPAM, you have to onboard your public IPs for each Amazon Region.

### Important

- Before you begin this tutorial, complete the steps in [Onboarding prerequisites for your BYOIP address range](#) in the *Amazon EC2 User Guide for Linux Instances*.

When you create the ROAs, for IPv4 CIDRs you must set the maximum length of an IP address prefix to /24. For IPv6 CIDRs, if you are adding them to an advertisable pool, the maximum length of an IP address prefix must be /48. This ensures that you have full flexibility to divide your public IP address across Amazon Regions. IPAM enforces the maximum length you set. The maximum length is the smallest prefix length announcement you will allow for this route. For example, if you bring a /20 CIDR block to

Amazon, by setting the maximum length to /24, you can divide the larger block any way you like (such as with /21, /22, or /24) and distribute those smaller CIDR blocks to any Region. If you were to set the maximum length to /23, you would not be able to divide and advertise a /24 from the larger block. Also, note that /24 is the smallest IPv4 block and /48 is the smallest IPv6 block you can advertise from a Region to the internet.

- Once you bring an IPv4 address range to Amazon, you can use all of the IP addresses in the range, including the first address (the network address) and the last address (the broadcast address).

## Contents

- [Bring your own public IPv4 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI](#)
- [Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI](#)

## Bring your own public IPv4 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI

Follow these steps to bring an IPv4 or IPv6 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI.

### Important

- Before you begin this tutorial, complete the steps in [Onboarding prerequisites for your BYOIP address range](#) in the *Amazon EC2 User Guide for Linux Instances*.

When you create the ROAs, for IPv4 CIDRs you must set the maximum length of an IP address prefix to /24. For IPv6 CIDRs, if you are adding them to an advertisable pool, the maximum length of an IP address prefix must be /48. This ensures that you have full flexibility to divide your public IP address across Amazon Regions. IPAM enforces the maximum length you set. The maximum length is the smallest prefix length announcement you will allow for this route. For example, if you bring a /20 CIDR block to Amazon, by setting the maximum length to /24, you can divide the larger block any way you like (such as with /21, /22, or /24) and distribute those smaller CIDR blocks to any Region. If you were to set the maximum length to /23, you would not be able to divide



and advertise a /24 from the larger block. Also, note that /24 is the smallest IPv4 block and /48 is the smallest IPv6 block you can advertise from a Region to the internet.

- Once you bring an IPv4 address range to Amazon, you can use all of the IP addresses in the range, including the first address (the network address) and the last address (the broadcast address).

## Contents

- [Bring your own IPv4 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI](#)
- [Bring your own IPv6 CIDR to IPAM using the Amazon Management Console](#)

## Bring your own IPv4 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI

Follow these steps to bring an IPv4 CIDR to IPAM and allocate an Elastic IP address (EIP) using both the Amazon Management Console and the Amazon CLI.

### Important

- You cannot provision or advertise BYOIP address ranges in Local Zones at this time.
- This tutorial assumes you have already completed the steps in the following sections:
  - [Integrate IPAM with accounts in an Amazon Organization](#).
  - [Create an IPAM](#).
- Each step of this tutorial must be done by one of three Amazon Organizations accounts:
  - The management account.
  - The member account configured to be your IPAM administrator in [Integrate IPAM with accounts in an Amazon Organization](#). In this tutorial, this account will be called the IPAM account.
  - The member account in your organization which will allocate CIDRs from an IPAM pool. In this tutorial, this account will be called the member account.

## Contents

- [Step 1: Create Amazon CLI named profiles and IAM roles](#)
- [Step 2: Create a top-level IPAM pool](#)
- [Step 3. Create a Regional pool within the top-level pool](#)
- [Step 4. Share the Regional pool](#)
- [Step 5: Create a public IPv4 pool](#)
- [Step 6: Provision the public IPv4 CIDR to your public IPv4 pool](#)
- [Step 7: Create an Elastic IP address from the public IPv4 pool](#)
- [Step 8: Associate the Elastic IP address with an EC2 instance](#)
- [Step 9: Advertise the CIDR](#)
- [Step 10: Cleanup](#)

## Step 1: Create Amazon CLI named profiles and IAM roles

To complete this tutorial as a single Amazon user, you can use Amazon CLI named profiles to switch from one IAM role to another. [Named profiles](#) are collections of settings and credentials that you refer to when using the `--profile` option with the Amazon CLI. For more information about how to create IAM roles and named profiles for Amazon accounts, see [Using an IAM role in the Amazon CLI](#) in the *Amazon Identity and Access Management User Guide*.

Create one role and one named profile for each of the three Amazon accounts you will use in this tutorial:

- A profile called `management-account` for the Amazon Organizations management account.
- A profile called `ipam-account` for the Amazon Organizations member account that is configured to be your IPAM administrator.
- A profile called `member-account` for the Amazon Organizations member account in your organization which will allocate CIDRs from an IPAM pool.

After you have created the IAM roles and named profiles, return to this page and go to the next step. You will notice throughout the rest of this tutorial that the sample Amazon CLI commands use the `--profile` option with one of the named profiles to indicate which account must run the command.

## Step 2: Create a top-level IPAM pool

Complete the steps in this section to create a top-level IPAM pool.

This step must be done by the IPAM account.

## To create a pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. Choose the public scope. For more information about scopes, see [How IPAM works](#).
4. Choose **Create pool**.
5. (Optional) Add a **Name tag** for the pool and a **Description** for the pool.
6. Under **Source**, choose **IPAM scope**.
7. Under **Address family**, choose **IPv4**.
8. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
9. Under **Locale**, choose **None**.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

The IPAM integration with BYOIP requires that the locale is set on whichever pool will be used for the BYOIP CIDR. Since we are going to create a top-level IPAM pool with a Regional pool within it, and we're going to allocate space to an Elastic IP address from the Regional pool, you will set the locale on the Regional pool and not the top-level pool. You'll add the locale to the Regional pool when you create the Regional pool in a later step.

### Note

If you are creating a single pool only and not a top-level pool with Regional pools within it, you would want to choose a Locale for this pool so that the pool is available for allocations.

10. Under **Public IP source**, choose one of the following options:

- **BYOIP:** You are bringing your own IPv4 or IPv6 address range (BYOIP) to this pool.
- **Amazon owned:** You want Amazon to provision an IPv6 address range to this pool.

11. Do one of the following:

- If you chose **BYOIP** in the previous step, under **CIDRs to provision**, choose a CIDR to provision for the pool. Note that when provisioning an IPv4 CIDR to a pool within the top-level pool, the minimum IPv4 CIDR you can provision is /24; more specific CIDRs (such as /25) are not permitted. You must include the CIDR and the BYOIP message and certificate signature in the request so we can verify that you own the public space. For a list of BYOIP prerequisites including how to get this BYOIP message and certificate signature, see [Bring your own public IPv4 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI](#).

 **Important**

It can take up to one week for the BYOIP CIDR to be provisioned.

- If you chose **Amazon owned**, under **Netmask length** choose a netmask length from /40 to /52. Default is /52.

12. Leave **Configure this pool's allocation rule settings** unselected.

13. (Optional) Choose **Tags** for the pool.

14. Choose **Create pool**.

Ensure that this CIDR has been provisioned before you continue. You can see the state of provisioning in the **CIDRs** tab in the pool details page. Note that it can take up to one week for the BYOIP CIDR to be provisioned.

### Step 3. Create a Regional pool within the top-level pool

Create a Regional pool within the top-level pool. The IPAM integration with BYOIP requires that the locale is set on whichever pool will be used for the BYOIP CIDR. You'll add the locale to the Regional pool when you create the Regional pool in this section. The `Locale` must be one of the operating Regions you configured when you created the IPAM.

This step must be done by the IPAM account.

## To create a Regional pool within a top-level pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. Choose **Create pool**.
5. (Optional) Add a **Name tag** for the pool and a **Description** for the pool.
6. Under **Source**, choose the top-level pool that you created in the previous section.
7. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
8. Under **Locale**, choose the locale for the pool. In this tutorial, we'll use us-east-2 as the locale for the Regional pool. The available options come from the operating Regions that you chose when you created your IPAM.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses. Choosing a locale ensures there are no cross-region dependencies between your pool and the resources allocating from it.

9. Under **Service**, choose **EC2 (EIP/VPC)**. The service you select determines the Amazon service where the CIDR will be advertisable. Currently, the only option is **EC2 (EIP/VPC)**, which means that the CIDRs allocated from this pool will be advertisable for the Amazon EC2 service (for Elastic IP addresses) and the Amazon VPC service (for CIDRs associated with VPCs).
10. Under **CIDRs to provision**, choose a CIDR to provision for the pool. Note that when provisioning a CIDR to a pool within the top-level pool, the minimum IPv4 CIDR you can provision is /24; more specific CIDRs (such as /25) are not permitted.
11. Enable **Configure this pool's allocation rule settings**. You have the same allocation rule options here as you did when you created the top-level pool. See [Create a top-level IPv4 pool](#) for an explanation of the options that are available when you create pools. The allocation rules

for the Regional pool are not inherited from the top-level pool. If you do not apply any rules here, there will be no allocation rules set for the pool.

12. (Optional) Choose **Tags** for the pool.
13. When you've finished configuring your pool, choose **Create pool**.

Ensure that this CIDR has been provisioned before you continue. You can see the state of provisioning in the **CIDRs** tab in the pool details page.

#### Step 4. Share the Regional pool

Follow the steps in this section to share the IPAM pool using Amazon Resource Access Manager (RAM).

##### 4.1. Enable resource sharing in Amazon RAM

After you create your IPAM, you'll want to share the regional pool with other accounts in your organization. Before you share an IPAM pool, complete the steps in this section to enable resource sharing with Amazon RAM. If you are using the Amazon CLI to enable resource sharing, use the `--profile management-account` option.

##### To enable resource sharing

1. Using the Amazon Organizations management account, open the Amazon RAM console at <https://console.aws.amazon.com/ram/>.
2. In the left navigation pane, choose **Settings**, choose **Enable sharing with Amazon Organizations**, and then choose **Save settings**.

You can now share an IPAM pool with other members of the organization.

##### 4.2. Share an IPAM pool using Amazon RAM

In this section you'll share the regional pool with another Amazon Organizations member account. For complete instructions on sharing IPAM pools, including information on the required IAM permissions, see [Share an IPAM pool using Amazon RAM](#). If you are using the Amazon CLI to enable resource sharing, use the `--profile ipam-account` option.

## To share an IPAM pool using Amazon RAM

1. Using the IPAM admin account, open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope, choose the IPAM pool, and choose **Actions > View details**.
4. Under **Resource sharing**, choose **Create resource share**. The Amazon RAM console opens. You share the pool using Amazon RAM.
5. Choose **Create a resource share**.
6. In the Amazon RAM console, choose **Create a resource share** again.
7. Add a **Name** for the shared pool.
8. Under **Select resource type**, choose **IPAM pools**, and then choose the ARN of the pool you want to share.
9. Choose **Next**.
10. Choose the **AWSRAMPermissionIpamPoolByoipCidrImport** permission. The details of the permission options are out of scope for this tutorial, but you can find out more about these options in [Share an IPAM pool using Amazon RAM](#).
11. Choose **Next**.
12. Under **Principals > Select principal type**, choose **Amazon account** and enter the account ID of the account that will be bringing an IP address range to IPAM and choose **Add**.
13. Choose **Next**.
14. Review the resource share options and the principals that you'll be sharing with, and then choose **Create**.
15. To allow the **member-account** account to allocate IP address CIDRS from the IPAM pool, create a second resource share with `AWSRAMDefaultPermissionsIpamPool` and create a second resource share. The value for `--resource-arns` is the ARN of the IPAM pool that you created in the previous section. The value for `--principals` is the account ID of the BYOIP CIDR owner account. The value for `--permission-arns` is the ARN of the `AWSRAMDefaultPermissionsIpamPool` permission.

## Step 5: Create a public IPv4 pool

Creating a public IPv4 pool is a required step for bringing a public IPv4 address to Amazon to be managed with IPAM. This step should be done by the member account that will provision an Elastic IP address.

### Important

- This step must be done by the member account using the Amazon CLI.
- Public IPv4 pools and IPAM pools are managed by distinct resources in Amazon. Public IPv4 pools are single account resources that enable you to convert your publicly-owned CIDRs to Elastic IP addresses. IPAM pools can be used to allocate your public space to public IPv4 pools.

### To create a public IPv4 pool using the Amazon CLI

- Run the following command to provision the CIDR. When you run the command in this section, the value for `--region` must match the `Locale` option you chose when you created the pool that will be used for the BYOIP CIDR.

```
aws ec2 create-public-ipv4-pool --region us-east-2 --profile member-account
```

In the output, you'll see the public IPv4 pool ID. You will need this ID in the next step.

```
{
 "PoolId": "ipv4pool-ec2-09037ce61cf068f9a"
}
```

## Step 6: Provision the public IPv4 CIDR to your public IPv4 pool

Provision the public IPv4 CIDR to your public IPv4 pool. The value for `--region` must match the `Locale` value you chose when you created the pool that will be used for the BYOIP CIDR. The `--netmask-length` is the amount of space out of the IPAM pool that you want to bring to your public pool. The value cannot be larger than the netmask length of the IPAM pool. The least specific IPv4 prefix you can bring is `/24`.



**Note**

If you are bringing a /24 CIDR range to IPAM to share across an Amazon Organization, you can provision smaller prefixes to multiple IPAM pools, say /27 (using `-- netmask-length 27`), rather than provisioning the entire /24 CIDR (using `-- netmask-length 24`) as is shown in this tutorial.

**Important**

This step must be done by the member account using the Amazon CLI.

**To create a public IPv4 pool using the Amazon CLI**

1. Run the following command to provision the CIDR.

```
aws ec2 provision-public-ipv4-pool-cidr --region us-east-2 --ipam-pool-id ipam-pool-04d8e2d9670eeab21 --pool-id ipv4pool-ec2-09037ce61cf068f9a --netmask-length 24 --profile member-account
```

In the output, you'll see the provisioned CIDR.

```
{
 "PoolId": "ipv4pool-ec2-09037ce61cf068f9a",
 "PoolAddressRange": {
 "FirstAddress": "130.137.245.0",
 "LastAddress": "130.137.245.255",
 "AddressCount": 256,
 "AvailableAddressCount": 256
 }
}
```

2. Run the following command to view the CIDR provisioned in the public IPv4 pool.

```
aws ec2 describe-public-ipv4-pools --region us-east-2 --max-results 10 --profile member-account
```

In the output, you'll see the provisioned CIDR. By default the CIDR is not advertised, which means it's not publicly accessible over the internet. You will have the chance to set this CIDR to advertised in the last step of this tutorial.

```
{
 "PublicIpv4Pools": [
 {
 "PoolId": "ipv4pool-ec2-09037ce61cf068f9a",
 "Description": "",
 "PoolAddressRanges": [
 {
 "FirstAddress": "130.137.245.0",
 "LastAddress": "130.137.245.255",
 "AddressCount": 256,
 "AvailableAddressCount": 255
 }
],
 "TotalAddressCount": 256,
 "TotalAvailableAddressCount": 255,
 "NetworkBorderGroup": "us-east-2",
 "Tags": []
 }
]
}
```

Once you create the public IPv4 pool, to view the public IPv4 pool allocated in the IPAM Regional pool, open the IPAM console and view the allocation in the Regional pool under **Allocations** or **Resources**.

### Step 7: Create an Elastic IP address from the public IPv4 pool

Complete the steps in [Allocate an Elastic IP address](#) in the *Amazon EC2 User Guide for Linux Instances* to create an Elastic IP address (EIP) from the public IPv4 pool. When you open EC2 in the Amazon Management console, the Amazon Region you allocate the EIP in must match the `Local` option you chose when you created the pool that will be used for the BYOIP CIDR.

This step must be done by the member account. If you are using the Amazon CLI, use the `--profile member-account` option.

## Step 8: Associate the Elastic IP address with an EC2 instance

Complete the steps in [Associate an Elastic IP address with an instance or network interface](#) in the *Amazon EC2 User Guide for Linux Instances* to associate the EIP with an EC2 instance. When you open EC2 in the Amazon Management console, the Amazon Region you associate the EIP in must match the `Locale` option you chose when you created the pool that will be used for the BYOIP CIDR. In this tutorial, that pool is the Regional pool.

This step must be done by the member account. If you are using the Amazon CLI, use the `--profile member-account` option.

## Step 9: Advertise the CIDR

The steps in this section must be done by the IPAM account. Once you associate the Elastic IP address (EIP) with an instance or Elastic Load Balancer, you can then start advertising the CIDR you brought to Amazon that is in pool that has the **Service EC2 (EIP/VPC)** configured. In this tutorial, that's your Regional pool. By default the CIDR is not advertised, which means it's not publicly accessible over the internet.

This step must be done by the IPAM account.

### To advertise the CIDR

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. Choose the public scope. For more information about scopes, see [How IPAM works](#).
4. Choose the Regional pool you created in this tutorial.
5. Choose the **CIDRs** tab.
6. Select the BYOIP CIDR and choose **Actions > Advertise**.
7. Choose **Advertise CIDR**.

As a result, the BYOIP CIDR is advertised and the value in the **Advertising** column changes from **Withdrawn** to **Advertised**.

## Step 10: Cleanup

Follow the steps in this section to clean up the resources you've provisioned and created in this tutorial.

## Step 1: Withdraw the CIDR from advertising

This step must be done by the IPAM account.

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. Choose the public scope.
4. Choose the Regional pool you created in this tutorial.
5. Choose the **CIDRs** tab.
6. Select the BYOIP CIDR and choose **Actions** > **Withdraw from advertising**.
7. Choose **Withdraw CIDR**.

As a result, the BYOIP CIDR is no longer advertised and the value in the **Advertising** column changes from **Advertised** to **Withdrawn**.

## Step 2: Disassociate the Elastic IP address

This step must be done by the member account. If you are using the Amazon CLI, use the `--profile member-account` option.

- Complete the steps in [Disassociate an Elastic IP address](#) in the *Amazon EC2 User Guide for Linux Instances* to disassociate the EIP. When you open EC2 in the Amazon Management console, the Amazon Region you disassociate the EIP in must match the `Local` option you chose when you created the pool that will be used for the BYOIP CIDR. In this tutorial, that pool is the Regional pool.

## Step 3: Release the Elastic IP address

This step must be done by the member account. If you are using the Amazon CLI, use the `--profile member-account` option.

- Complete the steps in [Release an Elastic IP address](#) in the *Amazon EC2 User Guide for Linux Instances* to release an Elastic IP address (EIP) from the public IPv4 pool. When you open EC2 in the Amazon Management console, the Amazon Region you allocate the EIP in must match the `Local` option you chose when you created the pool that will be used for the BYOIP CIDR.

## Step 4: Deprovision the public IPv4 CIDR from your public IPv4 pool

### Important

This step must be done by the member account using the Amazon CLI.

#### 1. View your BYOIP CIDRs.

```
aws ec2 describe-public-ipv4-pools --region us-east-2 --profile member-account
```

In the output, you'll see the IP addresses in your BYOIP CIDR.

```
{
 "PublicIpv4Pools": [
 {
 "PoolId": "ipv4pool-ec2-09037ce61cf068f9a",
 "Description": "",
 "PoolAddressRanges": [
 {
 "FirstAddress": "130.137.245.0",
 "LastAddress": "130.137.245.255",
 "AddressCount": 256,
 "AvailableAddressCount": 256
 }
],
 "TotalAddressCount": 256,
 "TotalAvailableAddressCount": 256,
 "NetworkBorderGroup": "us-east-2",
 "Tags": []
 }
]
}
```

#### 2. Run the following command to release the last IP address in the CIDR from the public IPv4 pool. Enter the IP address with a netmask of /32.

```
aws ec2 deprovision-public-ipv4-pool-cidr --region us-east-2 --pool-id ipv4pool-ec2-09037ce61cf068f9a --cidr 130.137.245.255/32 --profile member-account
```

In the output, you'll see the deprovisioned CIDR.

```
{
 "PoolId": "ipv4pool-ec2-09037ce61cf068f9a",
 "DevisionedAddresses": [
 "130.137.245.255"
]
}
```

### Important

You must rerun this command for each IP address in the CIDR range. If your CIDR is a /24, you will have to run this command to deprovision each of the 256 IP addresses in the /24 CIDR.

3. View your BYOIP CIDRs again and ensure there are no more provisioned addresses. When you run the command in this section, the value for `--region` must match the Region of your IPAM.

```
aws ec2 describe-public-ipv4-pools --region us-east-2 --profile member-account
```

In the output, you'll see the IP addresses count in your public IPv4 pool.

```
{
 "PublicIpv4Pools": [
 {
 "PoolId": "ipv4pool-ec2-09037ce61cf068f9a",
 "Description": "",
 "PoolAddressRanges": [],
 "TotalAddressCount": 0,
 "TotalAvailableAddressCount": 0,
 "NetworkBorderGroup": "us-east-2",
 "Tags": []
 }
]
}
```

**Note**

It can take some time for IPAM to discover that public IPv4 pool allocations have been removed. You cannot continue to clean up and deprovision the IPAM pool CIDR until you see that the allocation has been removed from IPAM.

**Step 5: Delete the public IPv4 pool**

This step must be done by the member account.

- Run the following command to delete the public IPv4 pool the CIDR. When you run the command in this section, the value for `--region` must match the `Locale` option you chose when you created the pool that will be used for the BYOIP CIDR. In this tutorial, that pool is the Regional pool. This step must be done using the Amazon CLI.

```
aws ec2 delete-public-ipv4-pool --region us-east-2 --pool-id ipv4pool-ec2-09037ce61cf068f9a --profile member-account
```

In the output, you'll see the return value **true**.

```
{
 "ReturnValue": true
}
```

Once you delete the pool, to view the allocation unmanaged by IPAM, open the IPAM console and view the details of the Regional pool under **Allocations**.

**Step 6: Delete any RAM shares and disable RAM integration with Amazon Organizations**

This step must be done by the IPAM account and management account respectively. If you are using the Amazon CLI to delete the RAM shares and disable RAM integration, use the `--profile ipam-account` and `--profile management-account` options.

- Complete the steps in [Deleting a resource share in Amazon RAM](#) and [Disabling resource sharing with Amazon Organizations](#) in the *Amazon RAM User Guide*, in that order, to delete the RAM shares and disable RAM integration with Amazon Organizations.

## Step 7: Deprovision the CIDRs from the Regional pool and top-level pool

This step must be done by the IPAM account. If you are using the Amazon CLI to share the pool, use the `--profile ipam-account` option.

- Complete the steps in [Deprovision CIDRs from a pool](#) to deprovision the CIDRs from the Regional pool and then the top-level pool, in that order.

## Step 8: Delete the Regional pool and top-level pool

This step must be done by the IPAM account. If you are using the Amazon CLI to share the pool, use the `--profile ipam-account` option.

- Complete the steps in [Delete a pool](#) to delete the Regional pool and then the top-level pool, in that order.

## Bring your own IPv6 CIDR to IPAM using the Amazon Management Console

Follow the steps in this tutorial to bring an IPv6 CIDR to IPAM and allocate a VPC with the CIDR using both the Amazon Management Console and the Amazon CLI.

### Important

- You cannot provision or advertise BYOIP address ranges in Local Zones at this time.
- This tutorial assumes you have already completed the steps in the following sections:
  - [Integrate IPAM with accounts in an Amazon Organization](#).
  - [Create an IPAM](#).
- Each step of this tutorial must be done by one of three Amazon Organizations accounts:
  - The management account.
  - The member account configured to be your IPAM administrator in [Integrate IPAM with accounts in an Amazon Organization](#). In this tutorial, this account will be called the IPAM account.
  - The member account in your organization which will allocate CIDRs from an IPAM pool. In this tutorial, this account will be called the member account.



## Contents

- [Step 1: Create a top-level IPAM pool](#)
- [Step 2. Create a Regional pool within the top-level pool](#)
- [Step 3. Share the Regional pool](#)
- [Step 4: Create a VPC](#)
- [Step 5: Advertise the CIDR](#)
- [Step 6: Cleanup](#)

### Step 1: Create a top-level IPAM pool

Since you are going to create a top-level IPAM pool with a Regional pool within it, and we're going to allocate space to a resource (an Elastic IP address) from the Regional pool, you will set the locale on the Regional pool and not the top-level pool. You'll add the locale to the Regional pool when you create the Regional pool in a later step. The IPAM integration with BYOIP requires that the locale is set on whichever pool will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

#### To create a pool


1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. Choose the public scope. For more information about scopes, see [How IPAM works](#).
4. Choose **Create pool**.
5. (Optional) Add a **Name tag** for the pool and a **Description** for the pool.
6. Under **Source**, choose **IPAM scope**.
7. Under **Address family**, choose **IPv6**.

When you choose **IPv6**, a toggle option appears that enables you to control if Amazon can to publicly advertise the CIDRs in this pool. Leave this option enabled.

8. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
9. Ensure **Allow CIDRs in this pool to be publicly advertisable** is selected.

10. Under **Locale**, choose **None**. You will set the locale on the Regional pool.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

 **Note**

If you are creating a single pool only and not a top-level pool with Regional pools within it, you would want to choose a Locale for this pool so that the pool is available for allocations.

11. Under **Public IP source**, **BYOIP** is selected by default.
12. Under **CIDRs to provision**, choose a CIDR to provision for the pool. Note that when provisioning an IPv6 CIDR to a pool within the top-level pool, the most specific IPv6 address range that you can bring is /48 for CIDRs that are publicly advertisable and /60 for CIDRs that are not publicly advertisable. You must include the CIDR and the BYOIP message and certificate signature in the request so we can verify that you own the public space. For a list of BYOIP prerequisites including how to get this BYOIP message and certificate signature, see [Bring your own public IPv4 CIDR to IPAM using both the Amazon Management Console and the Amazon CLI](#).

 **Important**

It can take up to one week for the BYOIP CIDR to be provisioned.

13. Leave **Configure this pool's allocation rule settings** unselected.
14. (Optional) Choose **Tags** for the pool.
15. Choose **Create pool**.

Ensure that this CIDR has been provisioned before you continue. You can see the state of provisioning in the **CIDRs** tab in the pool details page. Note that it can take up to one week for the BYOIP CIDR to be provisioned.

## Step 2. Create a Regional pool within the top-level pool

Create a Regional pool within the top-level pool. A Locale is required on the pool and it must be one of the operating Regions you configured when you created the IPAM.

This step must be done by the IPAM account.

### To create a Regional pool within a top-level pool

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. If you don't want to use the default private scope, from the dropdown menu at the top of the content pane, choose the scope you want to use. For more information about scopes, see [How IPAM works](#).
4. Choose **Create pool**.
5. (Optional) Add a **Name tag** for the pool and a description for the pool.
6. Under **Source**, choose the top-level pool that you created in the previous section.
7. Under **Resource planning**, leave **Plan IP space within the scope** selected. For more information about using this option to plan for subnet IP space within a VPC, see [Tutorial: Plan VPC IP address space for subnet IP allocations](#).
8. Choose the locale for the pool. Choosing a locale ensures there are no cross-region dependencies between your pool and the resources allocating from it. The available options come from the operating Regions that you chose when you created your IPAM. In this tutorial, we'll use us-east-2 as the locale for the Regional pool.

The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

9. Under **Service**, choose **EC2 (EIP/VPC)**. The service you select determines the Amazon service where the CIDR will be advertisable. Currently, the only option is **EC2 (EIP/VPC)**, which means that the CIDRs allocated from this pool will be advertisable for the Amazon EC2 service (for Elastic IP addresses) and the Amazon VPC service (for CIDRs associated with VPCs).
10. Under **CIDRs to provision**, choose a CIDR to provision for the pool. Note that when provisioning an IPv6 CIDR to a pool within the top-level pool, the most specific IPv6 address

range that you can bring is /48 for CIDRs that are publicly advertisable and /60 for CIDRs that are not publicly advertisable.

11. Enable **Configure this pool's allocation rule settings** and choose optional allocation rules for this pool:
  - **Automatically import discovered resources:** This option is not available if the **Locale** is set to **None**. If selected, IPAM will continuously look for resources within the CIDR range of this pool and automatically import them as allocations into your IPAM. Note the following:
    - The CIDRs that will be allocated for these resources must not already be allocated to other resources in order for the import to succeed.
    - IPAM will import a CIDR regardless of its compliance with the pool's allocation rules, so a resource might be imported and subsequently marked as noncompliant.
    - If IPAM discovers multiple CIDRs that overlap, IPAM will import the largest CIDR only.
    - If IPAM discovers multiple CIDRs with matching CIDRs, IPAM will randomly import one of them only.
  - **Minimum netmask length:** The minimum netmask length required for CIDR allocations in this IPAM pool to be compliant and the largest size CIDR block that can be allocated from the pool. The minimum netmask length must be less than the maximum netmask length. Possible netmask lengths for IPv4 addresses are 0 - 32. Possible netmask lengths for IPv6 addresses are 0 - 128.
  - **Default netmask length:** A default netmask length for allocations added to this pool.
  - **Maximum netmask length:** The maximum netmask length that will be required for CIDR allocations in this pool. This value dictates the smallest size CIDR block that can be allocated from the pool. Ensure that this value is minimum **/48**.
  - **Tagging requirements:** The tags that are required for resources to allocate space from the pool. If the resources have their tags changed after they have allocated space or if the allocation tagging rules are changed on the pool, the resource may be marked as noncompliant.
  - **Locale:** The locale that will be required for resources that use CIDRs from this pool. Automatically imported resources that do not have this locale will be marked noncompliant. Resources that are not automatically imported into the pool will not be allowed to allocate space from the pool unless they are in this locale.
12. (Optional) Choose **Tags** for the pool.
13. When you've finished configuring your pool, choose **Create pool**.

Ensure that this CIDR has been provisioned before you continue. You can see the state of provisioning in the **CIDRs** tab in the pool details page.

### Step 3. Share the Regional pool

Follow the steps in this section to share the IPAM pool using Amazon Resource Access Manager (RAM).

#### 4.1. Enable resource sharing in Amazon RAM

After you create your IPAM, you'll want to share the regional pool with other accounts in your organization. Before you share an IPAM pool, complete the steps in this section to enable resource sharing with Amazon RAM. If you are using the Amazon CLI to enable resource sharing, use the `--profile management-account` option.

##### To enable resource sharing

1. Using the Amazon Organizations management account, open the Amazon RAM console at <https://console.aws.amazon.com/ram/>.
2. In the left navigation pane, choose **Settings**, choose **Enable sharing with Amazon Organizations**, and then choose **Save settings**.

You can now share an IPAM pool with other members of the organization.

#### 4.2. Share an IPAM pool using Amazon RAM

In this section you'll share the regional pool with another Amazon Organizations member account. For complete instructions on sharing IPAM pools, including information on the required IAM permissions, see [Share an IPAM pool using Amazon RAM](#). If you are using the Amazon CLI to enable resource sharing, use the `--profile ipam-account` option.

##### To share an IPAM pool using Amazon RAM

1. Using the IPAM admin account, open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope, choose the IPAM pool, and choose **Actions > View details**.
4. Under **Resource sharing**, choose **Create resource share**. The Amazon RAM console opens. You share the pool using Amazon RAM.

5. Choose **Create a resource share**.
6. In the Amazon RAM console, choose **Create a resource share** again.
7. Add a **Name** for the shared pool.
8. Under **Select resource type**, choose **IPAM pools**, and then choose the ARN of the pool you want to share.
9. Choose **Next**.
10. Choose the **AWSRAMPermissionIpamPoolByoipCidrImport** permission. The details of the permission options are out of scope for this tutorial, but you can find out more about these options in [Share an IPAM pool using Amazon RAM](#).
11. Choose **Next**.
12. Under **Principals > Select principal type**, choose **Amazon account** and enter the account ID of the account that will be bringing an IP address range to IPAM and choose **Add**.
13. Choose **Next**.
14. Review the resource share options and the principals that you'll be sharing with, and then choose **Create**.
15. To allow the **member-account** account to allocate IP address CIDRS from the IPAM pool, create a second resource share with `AWSRAMDefaultPermissionsIpamPool` and create a second resource share. The value for `--resource-arns` is the ARN of the IPAM pool that you created in the previous section. The value for `--principals` is the account ID of the BYOIP CIDR owner account. The value for `--permission-arns` is the ARN of the `AWSRAMDefaultPermissionsIpamPool` permission.

#### Step 4: Create a VPC

Complete the steps in [Creating a VPC](#) in the *Amazon VPC User Guide*.

This step must be done by the member account.

#### Note

- When you open VPC in the Amazon Management console, the Amazon Region you create the VPC in must match the `Local` option you chose when you created the pool that will be used for the BYOIP CIDR.

- When you reach the step to choose a CIDR for the VPC, you will have an option to use a CIDR from an IPAM pool. Choose the Regional pool you created in this tutorial.

When you create the VPC, Amazon allocates a CIDR in the IPAM pool to the VPC. You can view the allocation in IPAM by choosing a pool in the content pane of the IPAM console and viewing the **Allocations** tab for the pool.

## Step 5: Advertise the CIDR

The steps in this section must be done by the IPAM account. Once you create the VPC, you can then start advertising the CIDR you brought to Amazon that is in the pool that has the **Service EC2 (EIP/VPC)** configured. In this tutorial, that's your Regional pool. By default the CIDR is not advertised, which means it's not publicly accessible over the internet.

This step must be done by the IPAM account.

### To advertise the CIDR

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. Choose the public scope. For more information about scopes, see [How IPAM works](#).
4. Choose the Regional pool you created in this tutorial.
5. Choose the **CIDRs** tab.
6. Select the BYOIP CIDR and choose **Actions > Advertise**.
7. Choose **Advertise CIDR**.

As a result, the BYOIP CIDR is advertised and the value in the **Advertising** column changes from **Withdrawn** to **Advertised**.

## Step 6: Cleanup

Follow the steps in this section to clean up the resources you've provisioned and created in this tutorial.

### Step 1: Withdraw the CIDR from advertising

This step must be done by the IPAM account.

1. Open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. By default, when you create a pool, the default private scope is selected. Choose the public scope.
4. Choose the Regional pool you created in this tutorial.
5. Choose the **CIDRs** tab.
6. Select the BYOIP CIDR and choose **Actions > Withdraw from advertising**.
7. Choose **Withdraw CIDR**.

As a result, the BYOIP CIDR is no longer advertised and the value in the **Advertising** column changes from **Advertised** to **Withdrawn**.

## Step 2: Delete the VPC

This step must be done by the member account.

- Complete the steps in [Deleting a VPC](#) in the *Amazon VPC User Guide* to delete the VPC. When you open VPC in the Amazon Management console, the Amazon Region delete the VPC from must match the Local option you chose when you created the pool that will be used for the BYOIP CIDR. In this tutorial, that pool is the Regional pool.

When you delete the VPC, it takes time for IPAM to discover that the resource has been deleted and to deallocate the CIDR allocated to the VPC. You cannot continue to the next step in the cleanup until you see that IPAM has removed the allocation from the pool in the pool details **Allocations** tab.

## Step 3: Delete the RAM shares and disable RAM integration with Amazon Organizations

This step must be done by the IPAM account and management account respectively.

- Complete the steps in [Deleting a resource share in Amazon RAM](#) and [Disabling resource sharing with Amazon Organizations](#) in the *Amazon RAM User Guide*, in that order, to delete the RAM shares and disable RAM integration with Amazon Organizations.

## Step 4: Deprovision the CIDRs from the Regional pool and top-level pool

This step must be done by the IPAM account.



- Complete the steps in [Deprovision CIDRs from a pool](#) to deprovision the CIDRs from the Regional pool and then the top-level pool, in that order.

### Step 5: Delete the Regional pool and top-level pool

This step must be done by the IPAM account.

- Complete the steps in [Delete a pool](#) to delete the Regional pool and then the top-level pool, in that order.

## Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI

Follow these steps to bring an IPv4 or IPv6 CIDR to IPAM using only the Amazon CLI.

### Important

- Before you begin this tutorial, complete the steps in [Onboarding prerequisites for your BYOIP address range](#) in the *Amazon EC2 User Guide for Linux Instances*.

When you create the ROAs, for IPv4 CIDRs you must set the maximum length of an IP address prefix to /24. For IPv6 CIDRs, if you are adding them to an advertisable pool, the maximum length of an IP address prefix must be /48. This ensures that you have full flexibility to divide your public IP address across Amazon Regions. IPAM enforces the maximum length you set. The maximum length is the smallest prefix length announcement you will allow for this route. For example, if you bring a /20 CIDR block to Amazon, by setting the maximum length to /24, you can divide the larger block any way you like (such as with /21, /22, or /24) and distribute those smaller CIDR blocks to any Region. If you were to set the maximum length to /23, you would not be able to divide and advertise a /24 from the larger block. Also, note that /24 is the smallest IPv4 block and /48 is the smallest IPv6 block you can advertise from a Region to the internet.

- Once you bring an IPv4 address range to Amazon, you can use all of the IP addresses in the range, including the first address (the network address) and the last address (the broadcast address).

### Contents

- [Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI](#)

- [Bring your own IPv6 CIDR to IPAM using only the Amazon CLI](#)

## Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI

Follow these steps to bring an IPv4 CIDR to IPAM and allocate an Elastic IP address (EIP) with the CIDR using only the Amazon CLI.

### Important

- You cannot provision or advertise BYOIP address ranges in Local Zones at this time.
- This tutorial assumes you have already completed the steps in the following sections:
  - [Integrate IPAM with accounts in an Amazon Organization](#).
  - [Create an IPAM](#).
- Each step of this tutorial must be done by one of three Amazon Organizations accounts:
  - The management account.
  - The member account configured to be your IPAM administrator in [Integrate IPAM with accounts in an Amazon Organization](#). In this tutorial, this account will be called the IPAM account.
  - The member account in your organization which will allocate CIDRs from an IPAM pool. In this tutorial, this account will be called the member account.

### Contents

- [Step 1: Create Amazon CLI named profiles and IAM roles](#)
- [Step 2: Create an IPAM](#)
- [Step 3: Create a top-level IPAM pool](#)
- [Step 4: Provision a CIDR to the top-level pool](#)
- [Step 5: Create a Regional pool within the top-level pool](#)
- [Step 6: Provision a CIDR to the Regional pool](#)
- [Step 7: Share the Regional pool](#)
- [Step 8: Create a public IPv4 pool](#)
- [Step 9: Provision the public IPv4 CIDR to your public IPv4 pool](#)

- [Step 10: Create an Elastic IP address from the public IPv4 pool](#)
- [Step 11: Advertise the CIDR](#)
- [Step 12: Cleanup](#)

## Step 1: Create Amazon CLI named profiles and IAM roles

To complete this tutorial as a single Amazon user, you can use Amazon CLI named profiles to switch from one IAM role to another. [Named profiles](#) are collections of settings and credentials that you refer to when using the `--profile` option with the Amazon CLI. For more information about how to create IAM roles and named profiles for Amazon accounts, see [Using an IAM role in the Amazon CLI](#) in the *Amazon Identity and Access Management User Guide*.

Create one role and one named profile for each of the three Amazon accounts you will use in this tutorial:

- A profile called `management-account` for the Amazon Organizations management account.
- A profile called `ipam-account` for the Amazon Organizations member account that is configured to be your IPAM administrator.
- A profile called `member-account` for the Amazon Organizations member account in your organization which will allocate CIDRs from an IPAM pool.

After you have created the IAM roles and named profiles, return to this page and go to the next step. You will notice throughout the rest of this tutorial that the sample Amazon CLI commands use the `--profile` option with one of the named profiles to indicate which account must run the command.

## Step 2: Create an IPAM

This step is optional. If you already have an IPAM created with operating Regions of `us-east-1` and `us-west-2` created, you can skip this step. Create an IPAM and specify an operating region of `us-east-1` and `us-west-2`. You must select an operating region so that you can use the `locale` option when you create your IPAM pool. The IPAM integration with BYOIP requires that the `locale` is set on whichever pool will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

Run the following command:

```
aws ec2 create-ipam --description my-ipam --region us-east-1 --operating-
regions RegionName=us-west-2 --profile ipam-account
```

In the output, you'll see the IPAM you've created. Note the value for `PublicDefaultScopeId`. You will need your public scope ID in the next step. You are using the public scope because BYOIP CIDRs are public IP addresses, which is what the public scope is meant for.

```
{
 "Ipam": {
 "OwnerId": "123456789012",
 "IpamId": "ipam-090e48e75758de279",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "PublicDefaultScopeId": "ipam-scope-0087d83896280b594",
 "PrivateDefaultScopeId": "ipam-scope-08b70b04fbd524f8d",
 "ScopeCount": 2,
 "Description": "my-ipam",
 "OperatingRegions": [
 {
 "RegionName": "us-east-1"
 },
 {
 "RegionName": "us-west-2"
 }
],
 "Tags": []
 }
}
```

### Step 3: Create a top-level IPAM pool

Complete the steps in this section to create a top-level IPAM pool.

This step must be done by the IPAM account.

#### To create an IPv4 address pool for all of your Amazon resources using the Amazon CLI

1. Run the following command to create an IPAM pool. Use the ID of the public scope of the IPAM that you created in the previous step.

This step must be done by the IPAM account.

```
aws ec2 create-ipam-pool --region us-east-1 --ipam-scope-id ipam-
scope-0087d83896280b594 --description "top-level-IPv4-pool" --address-family ipv4
--profile ipam-account
```

In the output, you'll see `create-in-progress`, which indicates that pool creation is in progress.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0a03d430ca3f5c035",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "None",
 "PoolDepth": 1,
 "State": "create-in-progress",
 "Description": "top-level-pool",
 "AutoImport": false,
 "AddressFamily": "ipv4",
 "Tags": []
 }
}
```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools --region us-east-1 --profile ipam-account
```

The following example output shows the state of the pool.

```
{
 "IpamPools": [
 {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0a03d430ca3f5c035",
```

```
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "None",
 "PoolDepth": 1,
 "State": "create-complete",
 "Description": "top-level-IPV4-pool",
 "AutoImport": false,
 "AddressFamily": "ipv4",
 "Tags": []
 }
]
}
```

#### Step 4: Provision a CIDR to the top-level pool

Provision a CIDR block to the top-level pool. Note that when provisioning an IPv4 CIDR to a pool within the top-level pool, the minimum IPv4 CIDR you can provision is /24; more specific CIDRs (such as /25) are not permitted. You must include the CIDR and the BYOIP message and certificate signature in the request so we can verify that you own the public space. For a list of BYOIP prerequisites including how to get this BYOIP message and certificate signature, see [Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI](#).

This step must be done by the IPAM account.

#### Important

You only need to add `--cidr-authorization-context` when you provision the BYOIP CIDR to the top-level pool. For the Regional pool within the top-level pool, you can omit the `--cidr-authorization-context` option. Once you onboard your BYOIP to IPAM, you are not required to perform ownership validation when you divide the BYOIP across Regions and accounts.

#### To provision a CIDR block to the pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 provision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-
pool-0a03d430ca3f5c035 --cidr 130.137.245.0/24 --cidr-authorization-
context Message="1|aws|470889052444|130.137.245.0/24|20250101|SHA256|
RSAPSS",Signature="W3gdQ9PZHLjPmrnGM~cvGx~KCIsmAU0P7EN07VRnfSuf9NuJU5RUveQzus~QmF~Nx42j3z7d
hApR89Kt6GxRY0dRaNx8yt-uoZWzxt2yIhWngy-
du9pnEHBOX6WhoGYjWszPw0iV4cmaAX9DuMs8ASR83K127VvcBcRXE1T5URr3gWEB1CQe3rmuyQk~gAdbXiDN-94-
oS9AZ1afBbrFxrjFWRCTJhc7Cg3ASbR0-VWNci-
C~bWAPczbX3wPQSjtWGV3k1bGuD26ohUc02o8oJZQyYXRpgqcWGVJdQ__" --profile ipam-account
```

In the output, you'll see the CIDR pending provision.

```
{
 "IpamPoolCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "pending-provision"
 }
}
```

2. Ensure that this CIDR has been provisioned before you continue.

### Important

It can take up to one week for the BYOIP CIDR to be provisioned.

Run the following command until you see a state of provisioned in the output.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-
pool-0a03d430ca3f5c035 --profile ipam-account
```

The following example output shows the state.

```
{
 "IpamPoolCidrs": [
 {
 "Cidr": "130.137.245.0/24",
```

```
 "State": "provisioned"
 }
]
 }
```

## Step 5: Create a Regional pool within the top-level pool

Create a Regional pool within the top-level pool. `--locale` is required on the pool and it must be one of the operating Regions you configured when you created the IPAM. The locale is the Amazon Region where you want this IPAM pool to be available for allocations. For example, you can only allocate a CIDR for a VPC from an IPAM pool that shares a locale with the VPC's Region. Note that when you have chosen a locale for a pool, you cannot modify it. If the home Region of the IPAM is unavailable due to an outage and the pool has a locale different than the home Region of the IPAM, the pool can still be used to allocate IP addresses.

This step must be done by the IPAM account.

Choosing a locale ensures there are no cross-region dependencies between your pool and the resources allocating from it. The available options come from the operating Regions that you chose when you created your IPAM. In this tutorial, we'll use `us-west-2` as the locale for the Regional pool.

### Important

When you create the pool, you must include `--aws-service ec2`. The service you select determines the Amazon service where the CIDR will be advertisable. Currently, the only option is `ec2`, which means that the CIDRs allocated from this pool will be advertisable for the Amazon EC2 service (for Elastic IP addresses) and the Amazon VPC service (for CIDRs associated with VPCs).

## To create a Regional pool using the Amazon CLI

1. Run the following command to create the pool.

```
aws ec2 create-ipam-pool --description "Regional-IPv4-pool" --region us-east-1
--ipam-scope-id ipam-scope-0087d83896280b594 --source-ipam-pool-id ipam-
pool-0a03d430ca3f5c035 --locale us-west-2 --address-family ipv4 --aws-service ec2
--profile ipam-account
```



In the output, you'll see IPAM creating the pool.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0d8f3646b61ca5987",
 "SourceIpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0d8f3646b61ca5987",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-west-2",
 "PoolDepth": 2,
 "State": "create-in-progress",
 "Description": "Regional--pool",
 "AutoImport": false,
 "AddressFamily": "ipv4",
 "Tags": [],
 "ServiceType": "ec2"
 }
}
```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools --region us-east-1 --profile ipam-account
```

In the output, you see the pools that you have in your IPAM. In this tutorial, we created a top-level and a Regional pool, so you'll see them both.

## Step 6: Provision a CIDR to the Regional pool

Provision a CIDR block to the Regional pool. Note that when provisioning a CIDR to a pool within the top-level pool, the minimum IPv4 CIDR you can provision is /24; more specific CIDRs (such as /25) are not permitted.

This step must be done by the IPAM account.

## To assign a CIDR block to the Regional pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 provision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --cidr 130.137.245.0/24 --profile ipam-account
```

In the output, you'll see the CIDR pending provision.

```
{
 "IpamPoolCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "pending-provision"
 }
}
```

2. Run the following command until you see the state of provisioned in the output.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --profile ipam-account
```

The following example output shows the correct state.

```
{
 "IpamPoolCidrs": [
 {
 "Cidr": "130.137.245.0/24",
 "State": "provisioned"
 }
]
}
```

## Step 7. Share the Regional pool

Follow the steps in this section to share the IPAM pool using Amazon Resource Access Manager (RAM).

## 4.1. Enable resource sharing in Amazon RAM

After you create your IPAM, you'll want to share the regional pool with other accounts in your organization. Before you share an IPAM pool, complete the steps in this section to enable resource sharing with Amazon RAM. If you are using the Amazon CLI to enable resource sharing, use the `--profile management-account` option.

### To enable resource sharing

1. Using the Amazon Organizations management account, open the Amazon RAM console at <https://console.aws.amazon.com/ram/>.
2. In the left navigation pane, choose **Settings**, choose **Enable sharing with Amazon Organizations**, and then choose **Save settings**.

You can now share an IPAM pool with other members of the organization.

## 4.2. Share an IPAM pool using Amazon RAM

In this section you'll share the regional pool with another Amazon Organizations member account. For complete instructions on sharing IPAM pools, including information on the required IAM permissions, see [Share an IPAM pool using Amazon RAM](#). If you are using the Amazon CLI to enable resource sharing, use the `--profile ipam-account` option.

### To share an IPAM pool using Amazon RAM

1. Using the IPAM admin account, open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope, choose the IPAM pool, and choose **Actions > View details**.
4. Under **Resource sharing**, choose **Create resource share**. The Amazon RAM console opens. You share the pool using Amazon RAM.
5. Choose **Create a resource share**.
6. In the Amazon RAM console, choose **Create a resource share** again.
7. Add a **Name** for the shared pool.
8. Under **Select resource type**, choose **IPAM pools**, and then choose the ARN of the pool you want to share.
9. Choose **Next**.

10. Choose the **AWSRAMPermissionIpamPoolByoipCidrImport** permission. The details of the permission options are out of scope for this tutorial, but you can find out more about these options in [Share an IPAM pool using Amazon RAM](#).
11. Choose **Next**.
12. Under **Principals** > **Select principal type**, choose **Amazon account** and enter the account ID of the account that will be bringing an IP address range to IPAM and choose **Add**.
13. Choose **Next**.
14. Review the resource share options and the principals that you'll be sharing with, and then choose **Create**.
15. To allow the **member-account** account to allocate IP address CIDRS from the IPAM pool, create a second resource share with `AWSRAMDefaultPermissionsIpamPool` and create a second resource share. The value for `--resource-arns` is the ARN of the IPAM pool that you created in the previous section. The value for `--principals` is the account ID of the BYOIP CIDR owner account. The value for `--permission-arns` is the ARN of the `AWSRAMDefaultPermissionsIpamPool` permission.

## Step 8: Create a public IPv4 pool

Creating a public IPv4 pool is a required step for bringing a public IPv4 address to Amazon to be managed with IPAM. This step would typically be done by a different Amazon account which wants to provision an Elastic IP address.

This step must be done by the member account.

### Important

Public IPv4 pools and IPAM pools are managed by distinct resources in Amazon. Public IPv4 pools are single account resources that enable you to convert your publicly-owned CIDRs to Elastic IP addresses. IPAM pools can be used to allocate your public space to public IPv4 pools.

## To create a public IPv4 pool using the Amazon CLI

- Run the following command to provision the CIDR. When you run the command in this section, the value for `--region` must match the `--locale` option you entered when you created the pool that will be used for the BYOIP CIDR.

```
aws ec2 create-public-ipv4-pool --region us-west-2 --profile member-account
```

In the output, you'll see the public IPv4 pool ID. You will need this ID in the next step.

```
{
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b2"
}
```

## Step 9: Provision the public IPv4 CIDR to your public IPv4 pool

Provision the public IPv4 CIDR to your public IPv4 pool. The value for `--region` must match the `--locale` value you entered when you created the pool that will be used for the BYOIP CIDR.

This step must be done by the member account.

### To create a public IPv4 pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 provision-public-ipv4-pool-cidr --region us-west-2 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --pool-id ipv4pool-ec2-0019eed22a684e0b2 --netmask-length 24 --profile member-account
```

In the output, you'll see the provisioned CIDR.

```
{
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b2",
 "PoolAddressRange": {
 "FirstAddress": "130.137.245.0",
 "LastAddress": "130.137.245.255",
 "AddressCount": 256,
 "AvailableAddressCount": 256
 }
}
```

2. Run the following command to view the CIDR provisioned in the public IPv4 pool.

```
aws ec2 describe-byoip-cidrs --region us-west-2 --max-results 10 --profile member-account
```

In the output, you'll see the provisioned CIDR. By default the CIDR is not advertised, which means it's not publicly accessible over the internet. You will have the chance to set this CIDR to advertised in the last step of this tutorial.

```
{
 "ByoipCidrs": [
 {
 "Cidr": "130.137.245.0/24",
 "StatusMessage": "Cidr successfully provisioned",
 "State": "provisioned"
 }
]
}
```

## Step 10: Create an Elastic IP address from the public IPv4 pool

Create an Elastic IP address (EIP) from the public IPv4 pool. When you run the commands in this section, the value for `--region` must match the `--locale` option you entered when you created the pool that will be used for the BYOIP CIDR.

This step must be done by the member account.

### To create an EIP from the public IPv4 pool using the Amazon CLI

1. Run the following command to create the EIP.

```
aws ec2 allocate-address --region us-west-2 --public-ipv4-pool ipv4pool-ec2-0019eed22a684e0b2 --profile member-account
```

In the output, you'll see the allocation.

```
{
 "PublicIp": "130.137.245.100",
 "AllocationId": "eipalloc-0db3405026756dbf6",
 "PublicIpv4Pool": "ipv4pool-ec2-0019eed22a684e0b2",
 "NetworkBorderGroup": "us-east-1",
 "Domain": "vpc"
}
```

2. Run the following command to view the EIP allocation managed in IPAM.

This step must be done by the IPAM account.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --profile ipam-account
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": [
 {
 "Cidr": "130.137.245.0/24",
 "IpamPoolAllocationId": "ipam-pool-alloc-5dedc8e7937c4261b56dc3e3eb53dc45",
 "ResourceId": "ipv4pool-ec2-0019eed22a684e0b2",
 "ResourceType": "ec2-public-ipv4-pool",
 "ResourceOwner": "123456789012"
 }
]
}
```

## Step 11: Advertise the CIDR

The steps in this section must be done by the IPAM account. Once you associate the Elastic IP address (EIP) with an instance or Elastic Load Balancer, you can then start advertising the CIDR you brought to Amazon that is in pool that has `--aws-service ec2` defined. In this tutorial, that's your Regional pool. By default the CIDR is not advertised, which means it's not publicly accessible over the internet. When you run the command in this section, the value for `--region` must match the `--locale` option you entered when you created the pool that will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

### Start advertising the CIDR using the Amazon CLI

- Run the following command to advertise the CIDR.

```
aws ec2 advertise-byoip-cidr --region us-west-2 --cidr 130.137.245.0/24 --profile ipam-account
```

In the output, you'll see the CIDR is advertised.

```
{
 "ByoipCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "advertised"
 }
}
```

## Step 12: Cleanup

Follow the steps in this section to clean up the resources you've provisioned and created in this tutorial. When you run the commands in this section, the value for `--region` must match the `--locale` option you entered when you created the pool that will be used for the BYOIP CIDR.

### Clean up using the Amazon CLI

1. View the EIP allocation managed in IPAM.

This step must be done by the IPAM account.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --profile ipam-account
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": [
 {
 "Cidr": "130.137.245.0/24",
 "IpamPoolAllocationId": "ipam-pool-alloc-5dedc8e7937c4261b56dc3e3eb53dc45",
 "ResourceId": "ipv4pool-ec2-0019eed22a684e0b2",
 "ResourceType": "ec2-public-ipv4-pool",
 "ResourceOwner": "123456789012"
 }
]
}
```

2. Stop advertising the IPv4 CIDR.

This step must be done by the IPAM account.



```
aws ec2 withdraw-byoip-cidr --region us-west-2 --cidr 130.137.245.0/24 --
profile ipam-account
```

In the output, you'll see the CIDR State has changed from **advertised** to **provisioned**.

```
{
 "ByoipCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "provisioned"
 }
}
```

### 3. Release the Elastic IP address.

This step must be done by the member account.

```
aws ec2 release-address --region us-west-2 --allocation-
id eipalloc-0db3405026756dbf6 --profile member-account
```

You will not see any output when you run this command.

### 4. View your BYOIP CIDRs.

This step must be done by the member account.

```
aws ec2 describe-public-ipv4-pools --region us-west-2 --profile member-account
```

In the output, you'll see the IP addresses in your BYOIP CIDR.

```
{
 "PublicIpv4Pools": [
 {
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b2",
 "Description": "",
 "PoolAddressRanges": [
 {
 "FirstAddress": "130.137.245.0",
 "LastAddress": "130.137.245.255",
 "AddressCount": 256,
 "AvailableAddressCount": 256
 }
]
 }
]
}
```

```

],
 "TotalAddressCount": 256,
 "TotalAvailableAddressCount": 256,
 "NetworkBorderGroup": "us-east-1",
 "Tags": []
 }
]
}

```

5. Release the last IP address in the CIDR from the public IPv4 pool. Enter the IP address with a netmask of /32. You must rerun this command for each IP address in the CIDR range. If your CIDR is a /24, you will have to run this command to deprovision each of the 256 IP addresses in the /24 CIDR. When you run the command in this section, the value for `--region` must match the Region of your IPAM.

This step must be done by the member account.

```
aws ec2 deprovision-public-ipv4-pool-cidr --region us-east-1 --pool-id ipv4pool-ec2-0019eed22a684e0b2 --cidr 130.137.245.255/32 --profile member-account
```

In the output, you'll see the deprovisioned CIDR.

```

{
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b2",
 "DeprovisionedAddresses": [
 "130.137.245.255"
]
}

```

6. View your BYOIP CIDRs again and ensure there are no more provisioned addresses. When you run the command in this section, the value for `--region` must match the Region of your IPAM.

This step must be done by the member account.

```
aws ec2 describe-public-ipv4-pools --region us-east-1 --profile member-account
```

In the output, you'll see the IP addresses count in your public IPv4 pool.

```
{
 "PublicIpv4Pools": [
 {
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b2",
 "Description": "",
 "PoolAddressRanges": [],
 "TotalAddressCount": 0,
 "TotalAvailableAddressCount": 0,
 "NetworkBorderGroup": "us-east-1",
 "Tags": []
 }
]
}
```

7. View the EIP allocation is no longer managed in IPAM. It can take some time for IPAM to discover that the Elastic IP address has been removed. You cannot continue to clean up and deprovision the IPAM pool CIDR until you see that the allocation has been removed from IPAM. When you run the command in this section, the value for `--region` must match the `--locale` option you entered when you created the pool that will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --profile ipam-account
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": []
}
```

8. Deprovision the Regional pool CIDR. When you run the commands in this step, the value for `--region` must match the Region of your IPAM.

This step must be done by the IPAM account.

```
aws ec2 deprovision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --cidr 130.137.245.0/24 --profile ipam-account
```

In the output, you'll see the CIDR pending deprovision.

```
{
 "IpamPoolCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "pending-deprovision"
 }
}
```

Deprovisioning takes time to complete. Check the status of deprovisioning.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-
pool-0d8f3646b61ca5987 --profile ipam-account
```

Wait until you see **deprovisioned** before you continue to the next step.

```
{
 "IpamPoolCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "deprovisioned"
 }
}
```

9. Delete the RAM shares and disable RAM integration with Amazon Organizations. Complete the steps in [Deleting a resource share in Amazon RAM](#) and [Disabling resource sharing with Amazon Organizations](#) in the *Amazon RAM User Guide*, in that order, to delete the RAM shares and disable RAM integration with Amazon Organizations.

This step must be done by the IPAM account and management account respectively. If you are using the Amazon CLI to delete the RAM shares and disable RAM integration, use the `--profile ipam-account` and `--profile management-account` options.

10. Delete the Regional pool. When you run the command in this step, the value for `--region` must match the Region of your IPAM.

This step must be done by the IPAM account.

```
aws ec2 delete-ipam-pool --region us-east-1 --ipam-pool-id ipam-pool-0d8f3646b61ca5987 --profile ipam-account
```

In the output, you can see the delete state.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0d8f3646b61ca5987",
 "SourceIpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-pool-0d8f3646b61ca5987",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-east-1",
 "PoolDepth": 2,
 "State": "delete-in-progress",
 "Description": "reg-ipv4-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv4"
 }
}
```

11. Deprovision the top-level pool CIDR. When you run the commands in this step, the value for `--region` must match the Region of your IPAM.

This step must be done by the IPAM account.

```
aws ec2 deprovision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-pool-0a03d430ca3f5c035 --cidr 130.137.245.0/24 --profile ipam-account
```

In the output, you'll see the CIDR pending deprovision.

```
{
 "IpamPoolCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "pending-deprovision"
 }
}
```

Deprovisioning takes time to complete. Run the following command to check the status of deprovisioning.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-pool-0a03d430ca3f5c035 --profile ipam-account
```

Wait until you see **deprovisioned** before you continue to the next step.

```
{
 "IpamPoolCidr": {
 "Cidr": "130.137.245.0/24",
 "State": "deprovisioned"
 }
}
```

12. Delete the top-level pool. When you run the command in this step, the value for `--region` must match the Region of your IPAM.

This step must be done by the IPAM account.

```
aws ec2 delete-ipam-pool --region us-east-1 --ipam-pool-id ipam-pool-0a03d430ca3f5c035 --profile ipam-account
```

In the output, you can see the delete state.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0a03d430ca3f5c035",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-east-1",
 "PoolDepth": 2,
 "State": "delete-in-progress",
 "Description": "top-level-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv4"
 }
}
```

13. Delete the IPAM. When you run the command in this step, the value for `--region` must match the Region of your IPAM.

This step must be done by the IPAM account.

```
aws ec2 delete-ipam --region us-east-1 --ipam-id ipam-090e48e75758de279 --
profile ipam-account
```

In the output, you'll see the IPAM response. This means that the IPAM was deleted.

```
{
 "Ipam": {
 "OwnerId": "123456789012",
 "IpamId": "ipam-090e48e75758de279",

 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "PublicDefaultScopeId": "ipam-scope-0087d83896280b594",

 "PrivateDefaultScopeId": "ipam-scope-08b70b04fbd524f8d",
```

```
"ScopeCount": 2,

"OperatingRegions": [

 {

 "RegionName": "us-east-1"

 },

 {

 "RegionName": "us-west-2"

 }

],

}
```

## Bring your own IPv6 CIDR to IPAM using only the Amazon CLI

Follow these steps to bring an IPv6 CIDR to IPAM and allocate a VPC using only the Amazon CLI.

### Important

- You cannot provision or advertise BYOIP address ranges in Local Zones at this time.
- This tutorial assumes you have already completed the steps in the following sections:
  - [Integrate IPAM with accounts in an Amazon Organization](#).
  - [Create an IPAM](#).
- Each step of this tutorial must be done by one of three Amazon Organizations accounts:
  - The management account.
  - The member account configured to be your IPAM administrator in [Integrate IPAM with accounts in an Amazon Organization](#). In this tutorial, this account will be called the IPAM account.
  - The member account in your organization which will allocate CIDRs from an IPAM pool. In this tutorial, this account will be called the member account.

## Contents

- [Step 1: Create Amazon CLI named profiles and IAM roles](#)



- [Step 2: Create an IPAM](#)
- [Step 3: Create an IPAM pool](#)
- [Step 4: Provision a CIDR to the top-level pool](#)
- [Step 5: Create a Regional pool within the top-level pool](#)
- [Step 6: Provision a CIDR to the Regional pool](#)
- [Step 7. Share the Regional pool](#)
- [Step 8: Create a VPC using the IPv6 CIDR](#)
- [Step 9: Advertise the CIDR](#)
- [Step 10: Cleanup](#)

### Step 1: Create Amazon CLI named profiles and IAM roles

To complete this tutorial as a single Amazon user, you can use Amazon CLI named profiles to switch from one IAM role to another. [Named profiles](#) are collections of settings and credentials that you refer to when using the `--profile` option with the Amazon CLI. For more information about how to create IAM roles and named profiles for Amazon accounts, see [Using an IAM role in the Amazon CLI](#) in the *Amazon Identity and Access Management User Guide*.

Create one role and one named profile for each of the three Amazon accounts you will use in this tutorial:

- A profile called `management-account` for the Amazon Organizations management account.
- A profile called `ipam-account` for the Amazon Organizations member account that is configured to be your IPAM administrator.
- A profile called `member-account` for the Amazon Organizations member account in your organization which will allocate CIDRs from an IPAM pool.

After you have created the IAM roles and named profiles, return to this page and go to the next step. You will notice throughout the rest of this tutorial that the sample Amazon CLI commands use the `--profile` option with one of the named profiles to indicate which account must run the command.

### Step 2: Create an IPAM

This step is optional. If you already have an IPAM created with operating Regions of `us-east-1` and `us-west-2` created, you can skip this step. Create an IPAM and specify an operating region of

us-east-1 and us-west-2 . You must select an operating region so that you can use the locale option when you create your IPAM pool. The IPAM integration with BYOIP requires that the locale is set on whichever pool will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

Run the following command:

```
aws ec2 create-ipam --description my-ipam --region us-east-1 --operating-
regions RegionName=us-west-2 --profile ipam-account
```

In the output, you'll see the IPAM you've created. Note the value for `PublicDefaultScopeId`. You will need your public scope ID in the next step.

```
{
 "Ipam": {
 "OwnerId": "123456789012",
 "IpamId": "ipam-090e48e75758de279",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "PublicDefaultScopeId": "ipam-scope-0087d83896280b594",
 "PrivateDefaultScopeId": "ipam-scope-08b70b04fbd524f8d",
 "ScopeCount": 2,
 "Description": "my-ipam",
 "OperatingRegions": [
 {
 "RegionName": "us-east-1"
 },
 {
 "RegionName": "us-west-2"
 }
],
 "Tags": []
 }
}
```

### Step 3: Create an IPAM pool

Since you are going to create a top-level IPAM pool with a Regional pool within it, and we're going to allocate space to a resource (a VPC) from the Regional pool, you will set the locale on the Regional pool and not the top-level pool. You'll add the locale to the Regional pool when you create the Regional pool in a later step. The IPAM integration with BYOIP requires that the locale is set on whichever pool will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

Choose if you want this IPAM pool CIDR to be advertisable by Amazon over the public internet (`--publicly-advertisable` or `--no-publicly-advertisable`).

**Note**

Note that the scope ID must be the ID for the public scope and the address family must be `ipv6`.

### To create an IPv6 address pool for all of your Amazon resources using the Amazon CLI

1. Run the following command to create an IPAM pool. Use the ID of the public scope of the IPAM that you created in the previous step.

```
aws ec2 create-ipam-pool --region us-east-1 --ipam-scope-id ipam-scope-0087d83896280b594 --description "top-level-IPv6-pool" --address-family ipv6 --publicly-advertisable --profile ipam-account
```

In the output, you'll see `create-in-progress`, which indicates that pool creation is in progress.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-07f2466c7158b50c4",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-pool-07f2466c7158b50c4",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "None",
 "PoolDepth": 1,
 }
}
```

```
 "State": "create-in-progress",
 "Description": "top-level-Ipv6-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv6",
 "Tags": []
 }
}
```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools --region us-east-1 --profile ipam-account
```

The following example output shows the state of the pool.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-07f2466c7158b50c4",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-07f2466c7158b50c4",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "None",
 "PoolDepth": 1,
 "State": "create-complete",
```

```

 "Description": "top-level-Ipv6-pool",

 "AutoImport": false,

 "Advertisable": true,

 "AddressFamily": "ipv6",

 "Tags": []

 }
}

```

#### Step 4: Provision a CIDR to the top-level pool

Provision a CIDR block to the top-level pool. Note that when provisioning an IPv6 CIDR to a pool within the top-level pool, the most specific IPv6 address range that you can bring is /48 for CIDRs that are publicly advertisable and /60 for CIDRs that are not publicly advertisable. You must include the CIDR and the BYOIP message and certificate signature in the request so we can verify that you own the public space. For a list of BYOIP prerequisites including how to get this BYOIP message and certificate signature, see [Bring your own public IPv4 CIDR to IPAM using only the Amazon CLI](#).

You only need to add `--cidr-authorization-context` when you provision the BYOIP CIDR to the top-level pool. For the Regional pool within the top-level pool, you can omit the `--cidr-authorization-context` option.

This step must be done by the IPAM account.

#### To provision a CIDR block to the pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```

aws ec2 provision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-
pool1-07f2466c7158b50c4 --cidr 2605:9cc0:409::/48 --cidr-authorization-
context Message="1|aws|470889052444|2605:9cc0:409::/48|20250101|
SHA256|RSAPSS",Signature="FU26~vRG~NUGXa~akxd6dvdcCfvL88g8d~YAuai-
CR7HqMwzcgds9R1pBGtFidsRGyr77LmWyWqU9Xp1g2R1kSkfD00NiLKLcv9F63k6wdEkyFxnP7RAJDvF1mBwxmSgH~C
Vp6L0N3y00Xmp4JENB9uM7sM1u6oeoutGyyhXFeYPz1GSRdcdfKNKaimvPCqVsxGN5AwSi1KQ8byNqoa~G3dvs8ueSa
wispI~r69fq515UR19TA~fmmxBdh1huQ8DkM1rqcwveWow__" --profile ipam-account

```

In the output, you'll see the CIDR pending provision.

```
{
 "IpamPoolCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "pending-provision"
 }
}
```

2. Ensure that this CIDR has been provisioned before you continue.

 **Important**

It can take up to one week for the BYOIP CIDR to be provisioned.

Run the following command until you see a state of provisioned in the output.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-
pool-07f2466c7158b50c4 --profile ipam-account
```

The following example output shows the state.

```
{
 "IpamPoolCidrs": [
 {
 "Cidr": "2605:9cc0:409::/48",
 "State": "provisioned"
 }
]
}
```

## Step 5: Create a Regional pool within the top-level pool

Create a Regional pool within the top-level pool. `--locale` is required on the pool and it must be one of the operating Regions you configured when you created the IPAM.

This step must be done by the IPAM account.

### Important

When you create the pool, you must include `--aws-service ec2`. The service you select determines the Amazon service where the CIDR will be advertisable. Currently, the only option is `ec2`, which means that the CIDRs allocated from this pool will be advertisable for the Amazon EC2 service (for Elastic IP addresses) and the Amazon VPC service (for CIDRs associated with VPCs).

## To create a Regional pool using the Amazon CLI

1. Run the following command to create the pool.

```
aws ec2 create-ipam-pool --description "Regional-IPv6-pool" --region us-east-1
--ipam-scope-id ipam-scope-0087d83896280b594 --source-ipam-pool-id ipam-
pool-07f2466c7158b50c4 --locale us-west-2 --address-family ipv6 --aws-service ec2
--profile ipam-account
```

In the output, you'll see IPAM creating the pool.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0053b7d2b4fc3f730",
 "SourceIpamPoolId": "ipam-pool-07f2466c7158b50c4",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0053b7d2b4fc3f730",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-west-2",
 "PoolDepth": 2,
 "State": "create-in-progress",
```

```
 "Description": "reg-ipv6-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv6",
 "Tags": [],
 "ServiceType": "ec2"
 }
}
```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools --region us-east-1 --profile ipam-account
```

In the output, you see the pools that you have in your IPAM. In this tutorial, we created a top-level and a Regional pool, so you'll see them both.

## Step 6: Provision a CIDR to the Regional pool

Provision a CIDR block to the Regional pool. Note that when provisioning the CIDR to a pool within the top-level pool, the most specific IPv6 address range that you can bring is /48 for CIDRs that are publicly advertisable and /60 for CIDRs that are not publicly advertisable.

This step must be done by the IPAM account.

### To assign a CIDR block to the Regional pool using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 provision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-pool1-0053b7d2b4fc3f730 --cidr 2605:9cc0:409::/48 --profile ipam-account
```

In the output, you'll see the CIDR pending provision.

```
{
 "IpamPoolCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "pending-provision"
 }
}
```

2. Run the following command until you see the state of `provisioned` in the output.



```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-
pool-0053b7d2b4fc3f730 --profile ipam-account
```

The following example output shows the correct state.

```
{
 "IpamPoolCidrs": [
 {
 "Cidr": "2605:9cc0:409::/48",
 "State": "provisioned"
 }
]
}
```

## Step 7. Share the Regional pool

Follow the steps in this section to share the IPAM pool using Amazon Resource Access Manager (RAM).

### 4.1. Enable resource sharing in Amazon RAM

After you create your IPAM, you'll want to share the regional pool with other accounts in your organization. Before you share an IPAM pool, complete the steps in this section to enable resource sharing with Amazon RAM. If you are using the Amazon CLI to enable resource sharing, use the `--profile management-account` option.

#### To enable resource sharing

1. Using the Amazon Organizations management account, open the Amazon RAM console at <https://console.aws.amazon.com/ram/>.
2. In the left navigation pane, choose **Settings**, choose **Enable sharing with Amazon Organizations**, and then choose **Save settings**.

You can now share an IPAM pool with other members of the organization.

### 4.2. Share an IPAM pool using Amazon RAM

In this section you'll share the regional pool with another Amazon Organizations member account. For complete instructions on sharing IPAM pools, including information on the required IAM

permissions, see [Share an IPAM pool using Amazon RAM](#). If you are using the Amazon CLI to enable resource sharing, use the `--profile ipam-account` option.

### To share an IPAM pool using Amazon RAM

1. Using the IPAM admin account, open the IPAM console at <https://console.amazonaws.cn/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope, choose the IPAM pool, and choose **Actions > View details**.
4. Under **Resource sharing**, choose **Create resource share**. The Amazon RAM console opens. You share the pool using Amazon RAM.
5. Choose **Create a resource share**.
6. In the Amazon RAM console, choose **Create a resource share** again.
7. Add a **Name** for the shared pool.
8. Under **Select resource type**, choose **IPAM pools**, and then choose the ARN of the pool you want to share.
9. Choose **Next**.
10. Choose the **AWSRAMPermissionIpamPoolByoipCidrImport** permission. The details of the permission options are out of scope for this tutorial, but you can find out more about these options in [Share an IPAM pool using Amazon RAM](#).
11. Choose **Next**.
12. Under **Principals > Select principal type**, choose **Amazon account** and enter the account ID of the account that will be bringing an IP address range to IPAM and choose **Add**.
13. Choose **Next**.
14. Review the resource share options and the principals that you'll be sharing with, and then choose **Create**.
15. To allow the **member-account** account to allocate IP address CIDRS from the IPAM pool, create a second resource share with `AWSRAMDefaultPermissionsIpamPool` and create a second resource share. The value for `--resource-arns` is the ARN of the IPAM pool that you created in the previous section. The value for `--principals` is the account ID of the BYOIP CIDR owner account. The value for `--permission-arns` is the ARN of the `AWSRAMDefaultPermissionsIpamPool` permission.

## Step 8: Create a VPC using the IPv6 CIDR

Create a VPC using the IPAM pool ID. You must associate an IPv4 CIDR block to the VPC as well using the `--cidr-block` option or the request will fail. When you run the command in this section, the value for `--region` must match the `--locale` option you entered when you created the pool that will be used for the BYOIP CIDR.

This step must be done by the member account.

### To create a VPC with the IPv6 CIDR using the Amazon CLI

1. Run the following command to provision the CIDR.

```
aws ec2 create-vpc --region us-west-2 --ipv6-ipam-pool-id ipam-
pool-0053b7d2b4fc3f730 --cidr-block 10.0.0.0/16 --ipv6-netmask-length 56 --
profile member-account
```

In the output, you'll see the VPC being created.

```
{
 "Vpc": {
 "CidrBlock": "10.0.0.0/16",
 "DhcpOptionsId": "dopt-2afccf50",
 "State": "pending",
 "VpcId": "vpc-00b5573ffc3b31a29",
 "OwnerId": "123456789012",
 "InstanceTenancy": "default",
 "Ipv6CidrBlockAssociationSet": [
 {
 "AssociationId": "vpc-cidr-assoc-01b5703d6cc695b5b",
 "Ipv6CidrBlock": "2605:9cc0:409::/56",
 "Ipv6CidrBlockState": {
 "State": "associating"
 },
 "NetworkBorderGroup": "us-east-1",
 "Ipv6Pool": "ipam-pool-0053b7d2b4fc3f730"
 }
],
 "CidrBlockAssociationSet": [
 {
 "AssociationId": "vpc-cidr-assoc-09cccb07d4e9a0e0e",
 "CidrBlock": "10.0.0.0/16",
 "State": "pending"
 }
]
 }
}
```

```

 "CidrBlockState": {
 "State": "associated"
 }
],
 "IsDefault": false
}

```

## 2. View the VPC allocation in IPAM.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-pool-0053b7d2b4fc3f730 --profile ipam-account
```

In the output, you'll see allocation in IPAM.

```

{
 "IpamPoolAllocations": [
 {
 "Cidr": "2605:9cc0:409::/56",
 "IpamPoolAllocationId": "ipam-pool-alloc-5f8db726fb9e4ff0a33836e649283a52",
 "ResourceId": "vpc-00b5573ffc3b31a29",
 "ResourceType": "vpc",
 "ResourceOwner": "123456789012"
 }
]
}

```

## Step 9: Advertise the CIDR

Once you create the VPC with CIDR allocated in IPAM, you can then start advertising the CIDR you brought to Amazon that is in pool that has `--aws-service ec2` defined. In this tutorial, that's your Regional pool. By default the CIDR is not advertised, which means it's not publicly accessible over the internet. When you run the command in this section, the value for `--region` must match the `--locale` option you entered when you created the Regional pool that will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

## Start advertising the CIDR using the Amazon CLI

- Run the following command to advertise the CIDR.

```
aws ec2 advertise-byoip-cidr --region us-west-2 --cidr 2605:9cc0:409::/48 --
profile ipam-account
```

In the output, you'll see the CIDR is advertised.

```
{
 "ByoipCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "advertised"
 }
}
```

## Step 10: Cleanup

Follow the steps in this section to clean up the resources you've provisioned and created in this tutorial. When you run the commands in this section, the value for `--region` must match the `--locale` option you entered when you created the Regional pool that will be used for the BYOIP CIDR.

### Clean up using the Amazon CLI

1. Run the following command to view the VPC allocation managed in IPAM.

This step must be done by the IPAM account.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-
pool-0053b7d2b4fc3f730 --profile ipam-account
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": [
 {
 "Cidr": "2605:9cc0:409::/56",
 "IpamPoolAllocationId": "ipam-pool-
alloc-5f8db726fb9e4ff0a33836e649283a52",
```

```

 "ResourceId": "vpc-00b5573ffc3b31a29",
 "ResourceType": "vpc",
 "ResourceOwner": "123456789012"
 }
]
}

```

2. Run the following command to stop advertising the CIDR. When you run the command in this step, the value for `--region` must match the `--locale` option you entered when you created the Regional pool that will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

```
aws ec2 withdraw-byoip-cidr --region us-west-2 --cidr 2605:9cc0:409::/48 --
profile ipam-account
```

In the output, you'll see the CIDR State has changed from **advertised** to **provisioned**.

```

{
 "ByoipCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "provisioned"
 }
}

```

3. Run the following command to delete the VPC. When you run the command in this section, the value for `--region` must match the `--locale` option you entered when you created the Regional pool that will be used for the BYOIP CIDR.

This step must be done by the member account.

```
aws ec2 delete-vpc --region us-west-2 --vpc-id vpc-00b5573ffc3b31a29 --
profile member-account
```

You will not see any output when you run this command.

4. Run the following command to view the VPC allocation in IPAM. It can take some time for IPAM to discover that the VPC has been deleted and remove this allocation. When you run the commands in this section, the value for `--region` must match the `--locale` option you entered when you created the Regional pool that will be used for the BYOIP CIDR.

This step must be done by the IPAM account.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-pool-0053b7d2b4fc3f730 --profile ipam-account
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": [
 {
 "Cidr": "2605:9cc0:409::/56",
 "IpamPoolAllocationId": "ipam-pool-alloc-5f8db726fb9e4ff0a33836e649283a52",
 "ResourceId": "vpc-00b5573ffc3b31a29",
 "ResourceType": "vpc",
 "ResourceOwner": "123456789012"
 }
]
}
```

Rerun the command and look for the allocation to be removed. You cannot continue to clean up and deprovision the IPAM pool CIDR until you see that the allocation has been removed from IPAM.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --ipam-pool-id ipam-pool-0053b7d2b4fc3f730 --profile ipam-account
```

The output shows the allocation removed from IPAM.

```
{
 "IpamPoolAllocations": []
}
```

```
}
```

5. Delete the RAM shares and disable RAM integration with Amazon Organizations. Complete the steps in [Deleting a resource share in Amazon RAM](#) and [Disabling resource sharing with Amazon Organizations](#) in the *Amazon RAM User Guide*, in that order, to delete the RAM shares and disable RAM integration with Amazon Organizations.

This step must be done by the IPAM account and management account respectively. If you are using the Amazon CLI to delete the RAM shares and disable RAM integration, use the `--profile ipam-account` and `--profile management-account` options.

6. Run the following command to deprovision the Regional pool CIDR.

This step must be done by the IPAM account.

```
aws ec2 deprovision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-pool-0053b7d2b4fc3f730 --cidr 2605:9cc0:409::/48 --profile ipam-account
```

In the output, you'll see the CIDR pending deprovision.

```
{
 "IpamPoolCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "pending-deprovision"
 }
}
```

Deprovisioning takes time to complete. Continue to run the command until you see the CIDR state **deprovisioned**.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-pool-0053b7d2b4fc3f730 --cidr 2605:9cc0:409::/48 --profile ipam-account
```

In the output, you'll see the CIDR pending deprovision.

```
{
 "IpamPoolCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "deprovisioned"
 }
}
```



```
}
```

7. Run the following command to delete the Regional pool.

This step must be done by the IPAM account.

```
aws ec2 delete-ipam-pool --region us-east-1 --ipam-pool-id ipam-pool-0053b7d2b4fc3f730 --profile ipam-account
```

In the output, you can see the delete state.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0053b7d2b4fc3f730",
 "SourceIpamPoolId": "ipam-pool-07f2466c7158b50c4",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-pool-0053b7d2b4fc3f730",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-east-1",
 "PoolDepth": 2,
 "State": "delete-in-progress",
 "Description": "reg-ipv6-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv6"
 }
}
```

8. Run the following command to deprovision the top-level pool CIDR.

This step must be done by the IPAM account.

```
aws ec2 deprovision-ipam-pool-cidr --region us-east-1 --ipam-pool-id ipam-pool-07f2466c7158b50c4 --cidr 2605:9cc0:409::/48 --profile ipam-account
```

In the output, you'll see the CIDR pending deprovision.

```
{
```

```
"IpamPoolCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "pending-deprovision"
}
}
```

Deprovisioning takes time to complete. Run the following command to check the status of deprovisioning.

```
aws ec2 get-ipam-pool-cidrs --region us-east-1 --ipam-pool-id ipam-
pool-07f2466c7158b50c4 --profile ipam-account
```

Wait until you see **deprovisioned** before you continue to the next step.

```
{
 "IpamPoolCidr": {
 "Cidr": "2605:9cc0:409::/48",
 "State": "deprovisioned"
 }
}
```

9. Run the following command to delete the top-level pool.

This step must be done by the IPAM account.

```
aws ec2 delete-ipam-pool --region us-east-1 --ipam-pool-id ipam-
pool-07f2466c7158b50c4 --profile ipam-account
```

In the output, you can see the delete state.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0053b7d2b4fc3f730",
 "SourceIpamPoolId": "ipam-pool-07f2466c7158b50c4",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0053b7d2b4fc3f730",
 }
}
```

```

 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-east-1",
 "PoolDepth": 2,
 "State": "delete-in-progress",
 "Description": "reg-ipv6-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv6"
 }
}

```

10. Run the following command to delete the IPAM.

This step must be done by the IPAM account.

```
aws ec2 delete-ipam --region us-east-1 --ipam-id ipam-090e48e75758de279 --
profile ipam-account
```

In the output, you'll see the IPAM response. This means that the IPAM was deleted.

```

{
 "Ipam": {
 "OwnerId": "123456789012",
 "IpamId": "ipam-090e48e75758de279",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "PublicDefaultScopeId": "ipam-scope-0087d83896280b594",
 "PrivateDefaultScopeId": "ipam-scope-08b70b04fbd524f8d",
 "ScopeCount": 2,
 "OperatingRegions": [
 {
 "RegionName": "us-east-1"
 },
 {
 "RegionName": "us-west-2"
 }
]
 }
}

```

}

## Tutorial: Transfer a BYOIP IPv4 CIDR to IPAM

Follow these steps to transfer an existing IPv4 CIDR to IPAM. If you already have an IPv4 BYOIP CIDR with Amazon, you can move the CIDR to IPAM from a public IPv4 pool. You cannot move an IPv6 CIDR to IPAM.

This tutorial assumes you have already successfully brought an IP address range to Amazon using the process described in [Bring your own IP addresses \(BYOIP\) in Amazon EC2](#) and now you want to transfer that IP address range to IPAM. If you are bringing a new IP address to Amazon for the first time, complete the steps in [Tutorial: Bring your IP addresses to IPAM](#).

If you transfer a public IPv4 pool to IPAM, there is no impact on existing allocations. Once you transfer a public IPv4 pool to IPAM, depending on the resource type, you may be able to monitor the existing allocations. For more information, see [Monitor CIDR usage by resource](#).

### Important

- This tutorial assumes you have already completed the steps in [Create an IPAM](#).
- Each step of this tutorial must be done by one of two Amazon accounts:
  - The account for the IPAM administrator. In this tutorial, this account will be called the IPAM account.
  - The account in your organization which owns the BYOIP CIDR. In this tutorial, this account will be called the BYOIP CIDR owner account.

### Contents

- [Step 1: Create Amazon CLI named profiles and IAM roles](#)
- [Step 2: Get your IPAM's public scope ID](#)
- [Step 3: Create an IPAM pool](#)
- [Step 4: Share the IPAM pool using Amazon RAM](#)
- [Step 5: Transfer an existing BYOIP IPV4 CIDR to IPAM](#)
- [Step 6: View the CIDR in IPAM](#)
- [Step 7: Cleanup](#)

## Step 1: Create Amazon CLI named profiles and IAM roles

To complete this tutorial as a single Amazon user, you can use Amazon CLI named profiles to switch from one IAM role to another. [Named profiles](#) are collections of settings and credentials that you refer to when using the `--profile` option with the Amazon CLI. For more information about how to create IAM roles and named profiles for Amazon accounts, see [Using an IAM role in the Amazon CLI](#) in the *Amazon Identity and Access Management User Guide*.

Create one role and one named profile for each of the three Amazon accounts you will use in this tutorial:

- A profile called `ipam-account` for the Amazon account that is the IPAM administrator.
- A profile called `byoip-owner-account` for the Amazon account in your organization which owns the BYOIP CIDR.

After you have created the IAM roles and named profiles, return to this page and go to the next step. You will notice throughout the rest of this tutorial that the sample Amazon CLI commands use the `--profile` option with one of the named profiles to indicate which account must run the command.

## Step 2: Get your IPAM's public scope ID

Follow the steps in this section to get your IPAM's public scope ID. This step should be performed by the `ipam-account` account.

Run the following command to get your public scope ID.

```
aws ec2 describe-ipams --region us-east-1 --profile ipam-account
```

In the output, you'll see your public scope ID. Note the values for `PublicDefaultScopeId`. You will need it in the next step.

```
{
 "Ipams": [
 {
 "OwnerId": "123456789012",
 "IpamId": "ipam-090e48e75758de279",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "PublicDefaultScopeId": "ipam-scope-0087d83896280b594",
```

```

 "PrivateDefaultScopeId": "ipam-scope-08b70b04fbd524f8d",
 "ScopeCount": 2,
 "Description": "my-ipam",
 "OperatingRegions": [
 {
 "RegionName": "us-east-1"
 },
 {
 "RegionName": "us-west-2"
 }
],
 "Tags": []
 }
]
}

```

### Step 3: Create an IPAM pool

Follow the steps in this section to create an IPAM pool. This step should be performed by the **ipam-account** account. The IPAM pool you create must be a top-level pool with the `--locale` option matching the BYOIP CIDR Amazon Region. You can only transfer a BYOIP to a top-level IPAM pool.

#### Important

When you create the pool, you must include `--aws-service ec2`. The service you select determines the Amazon service where the CIDR will be advertisable. Currently, the only option is `ec2`, which means that the CIDRs allocated from this pool will be advertisable for the Amazon EC2 service (for Elastic IP addresses) and the Amazon VPC service (for CIDRs associated with VPCs).

#### To create an IPv4 address pool for the transferred BYOIP CIDR using the Amazon CLI

1. Run the following command to create an IPAM pool. Use the ID of the public scope of the IPAM that you retrieved in the previous step.

```

aws ec2 create-ipam-pool --region us-east-1 --profile ipam-account --ipam-scope-
id ipam-scope-0087d83896280b594 --description "top-level-pool" --locale us-west-2
--aws-service ec2 --address-family ipv4

```

In the output, you'll see `create-in-progress`, which indicates that pool creation is in progress.

```
{
 "IpamPool": {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0a03d430ca3f5c035",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-west-2",
 "PoolDepth": 1,
 "State": "create-in-progress",
 "Description": "top-level-pool",
 "AutoImport": false,
 "AddressFamily": "ipv4",
 "Tags": [],
 "AwsService": "ec2"
 }
}
```

2. Run the following command until you see a state of `create-complete` in the output.

```
aws ec2 describe-ipam-pools --region us-east-1 --profile ipam-account
```

The following example output shows the state of the pool. You will need the **OwnerId** in the next step.

```
{
 "IpamPools": [
 {
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0a03d430ca3f5c035",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
```

```

 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-west-2",
 "PoolDepth": 1,
 "State": "create-complete",
 "Description": "top-level-pool",
 "AutoImport": false,
 "AddressFamily": "ipv4",
 "Tags": [],
 "AwsService": "ec2"
 }
]
}

```

## Step 4: Share the IPAM pool using Amazon RAM

Follow the steps in this section to share an IPAM pool using Amazon RAM so that another Amazon account can transfer an existing BYOIP IPV4 CIDR to the IPAM pool and use the IPAM pool. This step should be performed by the **ipam-account** account.

### To share an IPv4 address pool using the Amazon CLI

1. View the Amazon RAM permissions available for IPAM pools. You need both ARNs to complete the steps in this section.

```
aws ram list-permissions --region us-east-1 --profile ipam-account --resource-type ec2:IpamPool
```

```

{
 "permissions": [
 {
 "arn": "arn:aws:ram::aws:permission/AWSRAMDefaultPermissionsIpamPool",
 "version": "1",
 "defaultVersion": true,
 "name": "AWSRAMDefaultPermissionsIpamPool",
 "resourceType": "ec2:IpamPool",
 "status": "ATTACHABLE",
 "creationTime": "2022-06-30T13:04:29.335000-07:00",
 "lastUpdatedTime": "2022-06-30T13:04:29.335000-07:00",
 "isResourceTypeDefault": true
 },
 {

```



```

 "arn": "arn:aws:ram::aws:permission/
AWSRAMPermissionIpamPoolByoipCidrImport",
 "version": "1",
 "defaultVersion": true,
 "name": "AWSRAMPermissionIpamPoolByoipCidrImport",
 "resourceType": "ec2:IpamPool",
 "status": "ATTACHABLE",
 "creationTime": "2022-06-30T13:03:55.032000-07:00",
 "lastUpdatedTime": "2022-06-30T13:03:55.032000-07:00",
 "isResourceTypeDefault": false
 }
]
}

```

2. Create a resource share to enable the **byoip-owner-account** account to import BYOIP CIDRs to IPAM. The value for `--resource-arns` is the ARN of the IPAM pool that you created in the previous section. The value for `--principals` is the account ID of the BYOIP CIDR owner account. The value for `--permission-arns` is the ARN of the `AWSRAMPermissionIpamPoolByoipCidrImport` permission.

```

aws ram create-resource-share --region us-east-1 --profile ipam-account
--name PoolShare2 --resource-arns arn:aws:ec2::123456789012:ipam-pool/
ipam-pool-0a03d430ca3f5c035 --principals 111122223333 --permission-arns
arn:aws:ram::aws:permission/AWSRAMPermissionIpamPoolByoipCidrImport

```

```

{
 "resourceShare": {
 "resourceShareArn": "arn:aws:ram:us-east-1:123456789012:resource-
share/7993758c-a4ea-43ad-be12-b3abaffe361a",
 "name": "PoolShare2",
 "owningAccountId": "123456789012",
 "allowExternalPrincipals": true,
 "status": "ACTIVE",
 "creationTime": "2023-04-28T07:32:25.536000-07:00",
 }
}

```

```

 "lastUpdatedTime": "2023-04-28T07:32:25.536000-07:00"
 }
}

```

3. (Optional) If you want to allow the **byoip-owner-account** account to allocate IP address CIDRS from the IPAM pool to public IPv4 pools after the transfer is complete, copy the ARN for `AWSRAMDefaultPermissionsIpamPool` and create a second resource share. The value for `--resource-arns` is the ARN of the IPAM pool that you created in the previous section. The value for `--principals` is the account ID of the BYOIP CIDR owner account. The value for `--permission-arns` is the ARN of the `AWSRAMDefaultPermissionsIpamPool` permission.

```

aws ram create-resource-share --region us-east-1 --profile ipam-account
--name PoolShare1 --resource-arns arn:aws:ec2::123456789012:ipam-pool/
ipam-pool-0a03d430ca3f5c035 --principals 111122223333 --permission-arns
arn:aws:ram::aws:permission/AWSRAMDefaultPermissionsIpamPool

```

```

{
 "resourceShare": {
 "resourceShareArn": "arn:aws:ram:us-east-1:123456789012:resource-
share/8d1e229b-2830-4cf4-8b10-19c889235a2f",
 "name": "PoolShare1",
 "owningAccountId": "123456789012",
 "allowExternalPrincipals": true,
 "status": "ACTIVE",
 "creationTime": "2023-04-28T07:31:25.536000-07:00",
 "lastUpdatedTime": "2023-04-28T07:31:25.536000-07:00"
 }
}

```

As a result of creating the resource share in RAM, the `byoip-owner-account` account can now move CIDRs to IPAM.

## Step 5: Transfer an existing BYOIP IPV4 CIDR to IPAM

Follow the steps in this section to transfer an existing BYOIP IPV4 CIDR to IPAM. This step should be performed by the `byoip-owner-account` account.

### Important

Once you bring an IPv4 address range to Amazon, you can use all of the IP addresses in the range, including the first address (the network address) and the last address (the broadcast address).

To transfer the BYOIP CIDR to IPAM, the BYOIP CIDR owner must have these permissions in their IAM policy:

- `ec2:MoveByoipCidrToIpam`
- `ec2:ImportByoipCidrToIpam`

### Note

You can use either the Amazon Web Services Management Console or the Amazon CLI for this step.

Amazon Management Console

#### To transfer a BYOIP CIDR to the IPAM pool:

1. Open the IPAM console at <https://console.aws.amazon.com/ipam/> as the `byoip-owner-account` account.
2. In the navigation pane, choose **Pools**.
3. Choose the top-level pool created and shared in this tutorial.
4. Choose **Actions > Transfer BYOIP CIDR**.
5. Choose **Transfer BYOIP CIDR**.

6. Choose your BYOIP CIDR.
7. Choose **Provision**.

## Command line

Use the following Amazon CLI commands transfer a BYOIP CIDR to the IPAM pool using the Amazon CLI:

1. Run the following command to transfer the CIDR. Ensure that the `--region` value is the Amazon Region of the BYOIP CIDR.

```
aws ec2 move-byoip-cidr-to-ipam --region us-west-2 --profile byoip-owner-account
--ipam-pool-id ipam-pool-0a03d430ca3f5c035 --ipam-pool-owner 123456789012 --
cidr 130.137.249.0/24
```

In the output, you'll see the CIDR pending provision.

```
{
 "ByoipCidr": {
 "Cidr": "130.137.249.0/24",
 "State": "pending-transfer"
 }
}
```

2. Ensure that the CIDR has been transferred. Run the following command until you see a state of `complete-transfer` in the output.

```
aws ec2 move-byoip-cidr-to-ipam --region us-west-2 --profile byoip-
owner-account --ipam-pool-id ipam-pool-0a03d430ca3f5c035 --ipam-pool-
owner 123456789012 --cidr 130.137.249.0/24
```

The following example output shows the state.

```
{
 "ByoipCidr": {
```

```
 "Cidr": "130.137.249.0/24",
 "State": "complete-transfer"
 }
}
```

## Step 6: View the CIDR in IPAM

Follow the steps in this section to view the CIDR in IPAM. This step should be performed by the **ipam-account** account.

### To view the transferred BYOIP CIDR in IPAM pool using the Amazon CLI

- Run the following command to view the allocation managed in IPAM. Ensure that the `--region` value is the Amazon Region of the BYOIP CIDR.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --profile ipam-account --
ipam-pool-id ipam-pool-0d8f3646b61ca5987
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": [
 {
 "Cidr": "130.137.249.0/24",
 "IpamPoolAllocationId": "ipam-pool-
alloc-5dedc8e7937c4261b56dc3e3eb53dc46",
 "ResourceId": "ipv4pool-ec2-0019eed22a684e0b3",
 "ResourceType": "ec2-public-ipv4-pool",
 "ResourceOwner": "111122223333"
 }
]
}
```

## Step 7: Cleanup

Follow the steps in this section to remove the resources you created in this tutorial. This step should be performed by the **ipam-account** account.

### To cleanup the resources created in this tutorial using the Amazon CLI

1. To delete the IPAM pool shared resource, run the following command to get the first resource share ARN:

```
aws ram get-resource-shares --region us-east-1 --profile ipam-account --
name PoolShare1 --resource-owner SELF
```

```
{
 "resourceShares": [
 {
 "resourceShareArn": "arn:aws:ram:us-east-1:123456789012:resource-
share/8d1e229b-2830-4cf4-8b10-19c889235a2f",
 "name": "PoolShare1",
 "owningAccountId": "123456789012",
 "allowExternalPrincipals": true,
 "status": "ACTIVE",
 "creationTime": "2023-04-28T07:31:25.536000-07:00",
 "lastUpdatedTime": "2023-04-28T07:31:25.536000-07:00",
 "featureSet": "STANDARD"
 }
]
}
```

2. Copy the resource share ARN and use it to delete the IPAM pool resource share.

```
aws ram delete-resource-share --region us-east-1 --profile ipam-account
--resource-share-arn arn:aws:ram:us-east-1:123456789012:resource-
share/8d1e229b-2830-4cf4-8b10-19c889235a2f
```

```
{
 "returnValue": true
}
```

3. If you created an additional resource share in [Step 4: Share the IPAM pool using Amazon RAM](#), repeat the previous two steps to get the second resource share ARN for PoolShare2 and delete the second resource share.
4. Run the following command to get the allocation ID for the BYOIP CIDR. Ensure that the `--region` value matches the Amazon Region of the BYOIP CIDR.

```
aws ec2 get-ipam-pool-allocations --region us-west-2 --profile ipam-account --ipam-pool-id ipam-pool-0d8f3646b61ca5987
```

The output shows the allocation in IPAM.

```
{
 "IpamPoolAllocations": [
 {
 "Cidr": "130.137.249.0/24",
 "IpamPoolAllocationId": "ipam-pool-alloc-5dedc8e7937c4261b56dc3e3eb53dc46",
 "ResourceId": "ipv4pool-ec2-0019eed22a684e0b3",
 "ResourceType": "ec2-public-ipv4-pool",
 "ResourceOwner": "111122223333"
 }
]
}
```

5. Release the last IP address in the CIDR from the public IPv4 pool. Enter the IP address with a netmask of /32. You must rerun this command for each IP address in the CIDR range. If your CIDR is a /24, you will have to run this command to deprovision each of the 256 IP addresses in the /24 CIDR. When you run the command in this section, the value for `--region` must match the Region of your IPAM.

This step must be done by the **byoip-owner-account** account.

```
aws ec2 deprovision-public-ipv4-pool-cidr --region us-east-1 --profile byoip-owner-account --pool-id ipv4pool-ec2-0019eed22a684e0b3 --cidr 130.137.249.255/32
```

In the output, you'll see the deprovisioned CIDR.

```
{
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b3",
```

```

 "DeprovisionedAddresses": [
 "130.137.249.255"
]
 }

```

6. View your BYOIP CIDRs again and ensure there are no more provisioned addresses. When you run the command in this section, the value for `--region` must match the Region of your IPAM.

This step must be done by the **byoip-owner-account** account.

```
aws ec2 describe-public-ipv4-pools --region us-east-1 --profile byoip-owner-account
```

In the output, you'll see the IP addresses count in your public IPv4 pool.

```

{
 "PublicIpv4Pools": [
 {
 "PoolId": "ipv4pool-ec2-0019eed22a684e0b3",
 "Description": "",
 "PoolAddressRanges": [],
 "TotalAddressCount": 0,
 "TotalAvailableAddressCount": 0,
 "NetworkBorderGroup": "us-east-1",
 "Tags": []
 }
]
}

```

7. Run the following command to delete the top-level pool.

```
aws ec2 delete-ipam-pool --region us-east-1 --profile ipam-account --ipam-pool-id ipam-pool-0a03d430ca3f5c035
```

In the output, you can see the delete state.

```

{
 "IpamPool": {

```



```
 "OwnerId": "123456789012",
 "IpamPoolId": "ipam-pool-0a03d430ca3f5c035",
 "IpamPoolArn": "arn:aws:ec2::123456789012:ipam-pool/ipam-
pool-0a03d430ca3f5c035",
 "IpamScopeArn": "arn:aws:ec2::123456789012:ipam-scope/ipam-
scope-0087d83896280b594",
 "IpamScopeType": "public",
 "IpamArn": "arn:aws:ec2::123456789012:ipam/ipam-090e48e75758de279",
 "Locale": "us-east-1",
 "PoolDepth": 2,
 "State": "delete-in-progress",
 "Description": "top-level-pool",
 "AutoImport": false,
 "Advertisable": true,
 "AddressFamily": "ipv4",
 "AwsService": "ec2"
 }
}
```

## Tutorial: Plan VPC IP address space for subnet IP allocations

Complete this tutorial to plan the VPC IP address space for allocating IP addresses to VPC subnets and monitor IP address-related metrics at the subnet and VPC level.

### Note

This tutorial covers allocating private IPv4 address space in a private IPAM scope to VPCs and subnets. You can also complete this tutorial using the public scope and an IPv6 CIDR range by creating the VPC with the Amazon-provided IPv6 CIDR block option on the VPC console.

Planning VPC IP address space for subnets enables you to do the following:

- **Plan and organize your VPC's IP addresses for allocation to subnets:** You can divide VPC IP address space into smaller CIDR blocks and provision those CIDR blocks to subnets with different business needs, such as if you're running workloads in development or production subnets.
- **Simplify IP address allocations for VPC subnets:** Once your VPC's address space is planned and organized, you can choose a netmask length rather than manually inputting a CIDR. For example,

if a developer is creating a subnet for hosting development workloads, they need to choose a pool and a netmask length for the subnet and IPAM will automatically allocate the CIDR block to your subnet.

The following example shows the hierarchy of the pool and resource structure that you will create with this tutorial:

- Private scope
  - Resource planning pool (10.0.0.0/20)
    - Dev subnet pool (10.0.0.0/24)
      - Dev subnet (10.0.0.0/28)
    - Prod subnet pool (10.0.0.1/24)
      - Prod subnet (10.0.0.16/28)

### Important

- The resource planning pool can be used to allocate CIDRs to subnets or it can be used as a source pool in which you can create other pools. In this tutorial, we use the resource planning pool as a source pool for subnet pools.
- You can create multiple resource planning pools using the same VPC if the VPC has more than one CIDR provisioned to it; if a VPC has two CIDRs assigned to it, for example, you can create two resource planning pools, one from each CIDR. Each CIDR can be assigned to one pool at a time.

## Step 1: Create a VPC

Complete the steps in this section to create a VPC to be used for subnet IP address planning. For more information about the IAM permissions that are required to create VPCs, see [Amazon VPC policy examples](#) in the *Amazon VPC User Guide*.

**Note**

You can use an existing VPC rather than creating a new one, but this tutorial focuses on the scenario where the VPC is configured with a manually-allocated CIDR block, not an IPAM-allocated automatically CIDR block.

**To create a VPC**

1. Using the IPAM admin account, open the VPC console at <https://console.aws.amazon.com/vpc/>.
2. Choose **Create VPC**.
3. Enter a name for the VPC, such as tutorial-vpc.
4. Choose **IPv4 CIDR manual input** and enter an IPv4 CIDR block. In this tutorial, we use 10.0.0.0/20.
5. Skip the option to add an IPv6 CIDR block.
6. Choose **Create VPC**.
7. Using the IPAM admin account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.
8. Choose **Resources** in the left navigation pane.
9. Wait for the VPC that you created to appear. This takes some time to happen and you may need to refresh the window to see it appear. The VPC must be discovered by IPAM before you continue to the next step.

**Step 2: Create a resource planning pool**

Complete the steps in this section to create a resource planning pool.

**To create a resource planning pool**

1. Using the IPAM admin account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope.
4. Choose **Create pool**.

5. Under **IPAM scope**, leave the private scope selected.
6. (Optional) Add a **Name tag** for the pool, such as “Resource-planning-pool”.
7. Under **Source**, choose **IPAM scope**.
8. Under **Resource planning**, choose **Plan IP space within a VPC** and choose the VPC you created in the previous step. The VPC is the resource used to provision CIDRs to the resource planning pool.
9. Under **CIDRs to provision**, choose the VPC CIDR to provision for the resource pool. The CIDR you provision to the resource planning pool must match the CIDR provisioned to the VPC. In this tutorial, we use 10.0.0.0/20.
10. Choose **Create pool**.
11. Once the pool is created, choose the **CIDR** tab to see the state of the provisioned CIDR. Refresh the page and wait for the CIDR state to change from *Pending-provision* to *Provisioned* before you go to the next step.

### Step 3: Create subnet pools

Complete the steps in this section to create two subnet pools that will be used for allocating IP space to subnets.

#### To create subnet pools

1. Using the IPAM admin account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope.
4. Choose **Create pool**.
5. Under **IPAM scope**, leave the private scope selected.
6. (Optional) Add a **Name tag** for the pool, such as “dev-subnet-pool”.
7. Under **Source**, choose **IPAM pool** and select the resource planning pool you created in Step 3. The address family, Resource planning configuration, and Locale are automatically inherited from the source pool.
8. Under **CIDRs to provision**, choose the CIDR to provision for the subnet pool. In this tutorial, we use 10.0.0.0/24.
9. Choose **Create pool**.

10. Once the pool is created, choose the **CIDR tab** to see the state of the provisioned CIDR. Refresh the page and wait for the CIDR state to change from *Pending-provision* to *Provisioned* before you go to the next step.
11. Repeat this process to create another subnet called "prod-subnet-pool".

At this point, if you want to make this subnet pool available to other Amazon accounts, you can share the subnet pool. For instructions on how to do that, see [Share an IPAM pool using Amazon RAM](#). Then return here to complete the tutorial.

## Step 4: Create subnets

Complete these steps to create two subnets.

### To create subnets

1. Using the appropriate account, open the VPC console at <https://console.aws.amazon.com/vpc/>.
2. Choose **Subnets > Create subnet**.
3. Choose the VPC you created at the start of this tutorial.
4. Enter a name for the subnet, such as "tutorial-subnet".
5. (optional) Choose an **Availability Zone**.
6. Under **IPv4 CIDR block**, choose **IPAM-allocated IPV4 CIDR block** and choose the dev subnet pool and a /28 netmask.
7. Choose **Create subnet**.
8. Repeat this process to create another subnet. This time choose the prod subnet pool and a /28 netmask.
9. Return to the IPAM console and choose **Resources** in the left navigation pane.
10. Look for the subnet pools you created and wait for the subnets that you created to appear beneath it. This takes some time to happen and you may need to refresh the window to see it appear.

The tutorial is complete. You can create additional subnet pools as needed or you can launch in EC2 instance into one of the subnets.

IPAM publishes metrics related to IP address usage in subnets. You can set CloudWatch alarms on the SubnetIPUsage metric, thereby allowing you to take action when IP utilization thresholds are

breached. If, for example, you have a /24 CIDR (256 IP addresses) assigned to a subnet and you want to be notified when 80% of the IPs have been utilized, you can set up a CloudWatch alarm to alert you when this threshold is reached. For more information on creating an alarm for subnet IP usage, see [Quick tip for creating alarms](#).

## Step 5: Cleanup

Complete these steps to delete the resources you created with this tutorial.

### To clean up the resources

1. Using the IPAM admin account, open the IPAM console at <https://console.aws.amazon.com/ipam/>.
2. In the navigation pane, choose **Pools**.
3. Choose the private scope.
4. Choose the resource planning pool and choose **Action > Delete**.
5. Select **Cascade delete**. The resource planning pool and the subnet pools will be deleted. This will not delete the subnets themselves. They will stay with CIDRs provisioned to them, though the CIDRs will no longer be from an IPAM pool.
6. Choose **Delete**.
7. [Delete the subnets](#).
8. [Delete the VPC](#).

Cleanup is complete.

# Identity and access management in IPAM

Amazon uses security credentials to identify you and to grant you access to your Amazon resources. You can use features of Amazon Identity and Access Management (IAM) to allow other users, services, and applications to use your Amazon resources fully or in a limited way, without sharing your security credentials.

This section describes the Amazon service-linked roles that are created specifically for IPAM and the managed policies attached to the IPAM service-linked roles. For more information about Amazon IAM roles and policies, see [Roles terms and concepts](#) in the *IAM User Guide*.

For more information on identity and access management for VPC, see [Identity and access management for Amazon VPC](#) in the *Amazon VPC User Guide*.

## Contents

- [Service-linked roles for IPAM](#)
- [Amazon managed policies for IPAM](#)
- [Example policy](#)

## Service-linked roles for IPAM

Service-linked roles in Amazon Identity and Access Management (IAM) enable Amazon services to call other Amazon services on your behalf. For more information about service-linked roles, see [Using service-linked roles](#) in the *IAM User Guide*.

There is currently only one service-linked role for IPAM: **AWSServiceRoleForIPAM**.

## Permissions granted to the service-linked role

IPAM uses the **AWSServiceRoleForIPAM** service-linked role to call the actions in the attached **AWSIPAMServiceRolePolicy** managed policy. For more information on the allowed actions in that policy, see [Amazon managed policies for IPAM](#).

Also attached to the service-linked role is an [IAM trusted policy](#) that allows the `ipam.amazonaws.com` service to assume the service-linked role.

## Create the service-linked role

IPAM monitors the IP address usage in one or more accounts by assuming the service-linked role in an account, discovering the resources and their CIDRs, and integrating the resources with IPAM.

The service-linked role is created in one of two ways:

- **When you integrate with Amazon Organizations**

If you [Integrate IPAM with accounts in an Amazon Organization](#) using the IPAM console or using the `enable-ipam-organization-admin-account` Amazon CLI command, the **AWSServiceRoleForIPAM** service-linked role is automatically created in each of your Amazon Organizations member accounts. As a result, the resources within all member accounts are discoverable by IPAM.

### Important

For IPAM to create the service-linked role on your behalf:

- The Amazon Organizations management account that enables IPAM integration with Amazon Organizations must have an IAM policy attached to it that permits the following actions:
  - `ec2:EnableIpamOrganizationAdminAccount`
  - `organizations:EnableAwsServiceAccess`
  - `organizations:RegisterDelegatedAdministrator`
  - `iam:CreateServiceLinkedRole`
- The IPAM account must have an IAM policy attached to it that permits the `iam:CreateServiceLinkedRole` action.

- **When you create an IPAM using a single Amazon account**

If you [Use IPAM with a single account](#), the **AWSServiceRoleForIPAM** service-linked role is automatically created when you create an IPAM as that account.

### Important

If you use IPAM with a single Amazon account, before you create an IPAM, you must ensure that the Amazon account you are using has an IAM policy attached to it that permits the `iam:CreateServiceLinkedRole` action. When you create the IPAM,



you automatically create the **AWSServiceRoleForIPAM** service-linked role. For more information on managing IAM policies, see [Editing IAM policies](#) in the *IAM User Guide*.

## Edit the service-linked role

You cannot edit the **AWSServiceRoleForIPAM** service-linked role.

## Delete the service-linked role

If you no longer need to use IPAM, we recommend that you delete the **AWSServiceRoleForIPAM** service-linked role.

### Note

You can delete the service-linked role only after you delete all IPAM resources in your Amazon account. This ensures that you can't inadvertently remove the monitoring capability of IPAM.

Follow these steps to delete the service-linked role via the Amazon CLI:

1. Delete your IPAM resources using [deprovision-ipam-pool-cidr](#) and [delete-ipam](#). For more information, see [Deprovision CIDRs from a pool](#) and [Delete an IPAM](#).
2. Disable the IPAM account with [disable-ipam-organization-admin-account](#).
3. Disable the IPAM service with [disable-aws-service-access](#) using the `--service-principal ipam.amazonaws.com` option.
4. Delete the service-linked role: [delete-service-linked-role](#). When you delete the service-linked role, the IPAM managed policy is also deleted. For more information, see [Deleting a service-linked role](#) in the *IAM User Guide*.

## Amazon managed policies for IPAM

If you are using IPAM with a single Amazon account and you create an IPAM, the **AWSIPAMServiceRolePolicy** managed policy is automatically created in your IAM account and attached to the **AWSServiceRoleForIPAM** [service-linked role](#).

If you enable IPAM integration with Amazon Organizations, the **AWSIPAMServiceRolePolicy** managed policy is automatically created in your IAM account and in each of your Amazon Organizations member accounts, and the managed policy is attached to the **AWSServiceRoleForIPAM** service-linked role.

This managed policy enables IPAM to do the following:

- Monitor CIDRs associated with networking resources across all members of your Amazon Organization.
- Store metrics related to IPAM in Amazon CloudWatch, such as the IP address space available in your IPAM pools and the number of resource CIDRs that comply with allocation rules.

The following example shows the details of the managed policy that's created.

```
{
 "Version": "2012-10-17",
 "Statement": [
 {
 "Sid": "IPAMDiscoveryDescribeActions",
 "Effect": "Allow",
 "Action": [
 "ec2:DescribeAccountAttributes",
 "ec2:DescribeAddresses",
 "ec2:DescribeByoipCidrs",
 "ec2:DescribeIpv6Pools",
 "ec2:DescribeNetworkInterfaces",
 "ec2:DescribePublicIpv4Pools",
 "ec2:DescribeSecurityGroups",
 "ec2:DescribeSecurityGroupRules",
 "ec2:DescribeSubnets",
 "ec2:DescribeVpcs",
 "ec2:DescribeVpnConnections",
 "ec2:GetIpamDiscoveredAccounts",
 "ec2:GetIpamDiscoveredPublicAddresses",
 "ec2:GetIpamDiscoveredResourceCidrs",
 "globalaccelerator:ListAccelerators",
 "globalaccelerator:ListByoipCidrs",
 "organizations:DescribeAccount",
 "organizations:DescribeOrganization",
 "organizations:ListAccounts",
 "organizations:ListDelegatedAdministrators"
]
 }
]
}
```

```

],
 "Resource": "*"
 },
 {
 "Sid": "CloudWatchMetricsPublishActions",
 "Effect": "Allow",
 "Action": "cloudwatch:PutMetricData",
 "Resource": "*",
 "Condition": {
 "StringEquals": {
 "cloudwatch:namespace": "AWS/IPAM"
 }
 }
 }
]
}

```

The first statement in the preceding example enables IPAM to monitor the CIDRs used by your single Amazon account or by the members of your Amazon Organization.

The second statement in the preceding example uses the `cloudwatch:PutMetricData` condition key to allow IPAM to store IPAM metrics in your `AWS/IPAM` [Amazon CloudWatch namespace](#). These metrics are used by the Amazon Management Console to display data about the allocations in your IPAM pools and scopes. For more information, see [Monitor CIDR usage with the IPAM dashboard](#).

## Updates to the Amazon managed policy

View details about updates to Amazon managed policies for IPAM since this service began tracking these changes.

| Change                   | Description                                                                                                                                                                                         | Date              |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------|
| AWSIPAMServiceRolePolicy | Action added to the <code>AWSIPAMServiceRolePolicy</code> managed policy ( <code>ec2:GetIpamDiscoveredPublicAddresses</code> ) to enable IPAM to get public IP addresses during resource discovery. | November 13, 2023 |

| Change                   | Description                                                                                                                                                                                                                                                                                                                                                                | Date             |
|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------|
| AWSIPAMServiceRolePolicy | Actions added to the AWSIPAMServiceRole Policy managed policy (ec2:DescribeAccountAttributes , ec2:DescribeNetworkInterfaces , ec2:DescribeSecurityGroups , ec2:DescribeSecurityGroupRules , ec2:DescribeVpnConnections , globalaccelerator:ListAccelerators , and globalaccelerator:ListByoipCidrs ) to enable IPAM to get public IP addresses during resource discovery. | November 1, 2023 |
| AWSIPAMServiceRolePolicy | Two actions added to the AWSIPAMServiceRole Policy managed policy (ec2:GetIpamDiscoveredAccounts and ec2:GetIpamDiscoveredResourceCidrs ) to enable IPAM to get the Amazon accounts and resource CIDRs being monitored during resource discovery.                                                                                                                          | January 25, 2023 |

| Change                        | Description                                                    | Date             |
|-------------------------------|----------------------------------------------------------------|------------------|
| IPAM started tracking changes | IPAM started tracking changes for its Amazon managed policies. | December 2, 2021 |

## Example policy

The example policy in this section contains all the relevant Amazon Identity and Access Management (IAM) actions for full IPAM usage. Depending on how you are using IPAM, you may not need to include all of the IAM actions. For a full experience using the IPAM console, you may need to include additional IAM actions for services such as Amazon Organizations, Amazon Resource Access Manager (RAM), and Amazon CloudWatch.

```
{
 "Version": "2012-10-17",
 "Statement": [
 {
 "Effect": "Allow",
 "Action": [
 "ec2:AssociateIpamByoasn",
 "ec2:DeprovisionIpamByoasn",
 "ec2:DescribeIpamByoasn",
 "ec2:DisassociateIpamByoasn",
 "ec2:ProvisionIpamByoasn",
 "ec2:CreateIpam",
 "ec2:DescribeIpams",
 "ec2:ModifyIpam",
 "ec2>DeleteIpam",
 "ec2:CreateIpamScope",
 "ec2:DescribeIpamScopes",
 "ec2:ModifyIpamScope",
 "ec2>DeleteIpamScope",
 "ec2:CreateIpamPool",
 "ec2:DescribeIpamPools",
 "ec2:ModifyIpamPool",
 "ec2>DeleteIpamPool",
 "ec2:ProvisionIpamPoolCidr",
 "ec2:GetIpamPoolCidrs",
 "ec2:DeprovisionIpamPoolCidr",
```

```

 "ec2:AllocateIpamPoolCidr",
 "ec2:GetIpamPoolAllocations",
 "ec2:ReleaseIpamPoolAllocation",
 "ec2:CreateIpamResourceDiscovery",
 "ec2:DescribeIpamResourceDiscoveries",
 "ec2:ModifyIpamResourceDiscovery",
 "ec2>DeleteIpamResourceDiscovery",
 "ec2:AssociateIpamResourceDiscovery",
 "ec2:DescribeIpamResourceDiscoveryAssociations",
 "ec2:DisassociateIpamResourceDiscovery",
 "ec2:GetIpamResourceCidrs",
 "ec2:ModifyIpamResourceCidr",
 "ec2:GetIpamAddressHistory",
 "ec2:GetIpamDiscoveredResourceCidrs",
 "ec2:GetIpamDiscoveredAccounts",
 "ec2:GetIpamDiscoveredPublicAddresses"
],
 "Resource": "*"
},
{
 "Effect": "Allow",
 "Action": "iam:CreateServiceLinkedRole",
 "Resource": "arn:aws:iam::*:role/aws-service-role/ipam.amazonaws.com/
AWSServiceRoleForIPAM",
 "Condition": {
 "StringLike": {
 "iam:AWSServiceName": "ipam.amazonaws.com"
 }
 }
}
]
}

```

## Quotas for your IPAM

This section lists the quotas related to IPAM. The Service Quotas console also provides information about IPAM quotas. You can use the Service Quotas console to view default quotas and [request quota increases](#) for adjustable quotas. For more information, see [Requesting a quota increase](#) in the *Service Quotas User Guide*.

| Name                                                        | Default | Adjustable                                                                                                                                         |
|-------------------------------------------------------------|---------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| Amazon-provided IPv6 CIDR block netmask length              | /52     | Yes. Contact the Amazon Support Center as described in <a href="#">Amazon service quotas</a> in the <i>Amazon Web Services General Reference</i> . |
| Amazon-provided IPv6 CIDR blocks per Regional pool          | 1       | Yes. Contact the Amazon Support Center as described in <a href="#">Amazon service quotas</a> in the <i>Amazon Web Services General Reference</i> . |
| Autonomous System Numbers (ASNs) that you can bring to IPAM | 5       | Yes. Contact the Amazon Support Center as described in <a href="#">Amazon service quotas</a> in the <i>Amazon Web Services General Reference</i> . |
| CIDRs per pool                                              | 50      | <a href="#">Yes</a>                                                                                                                                |
| IPAM administrators per organization                        | 1       | No                                                                                                                                                 |

| Name                                          | Default | Adjustable                                                                                                                                                                                                               |
|-----------------------------------------------|---------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| IPAMs per Region                              | 1       | <a href="#">No</a>                                                                                                                                                                                                       |
| Pool depth (the number of pools within pools) | 10      | <a href="#">Yes</a>                                                                                                                                                                                                      |
| Pools per scope                               | 50      | <a href="#">Yes</a>                                                                                                                                                                                                      |
| Resource discovery associations per IPAM      | 5       | <a href="#">Yes</a>                                                                                                                                                                                                      |
| Resource discoveries per Region               | 1       | <a href="#">No</a>                                                                                                                                                                                                       |
| <a href="#">Resource utilization metrics</a>  | 50      | Yes. Contact the Amazon Support Center as described in <a href="#">Amazon service quotas</a> in the <i>Amazon Web Services General Reference</i> .                                                                       |
| Scopes per IPAM                               | 5       | <a href="#">Yes</a> . When you create an IPAM, a private and public default scope are created for you. If you want to create additional scopes, they will be private scopes. You cannot create additional public scopes. |



# Pricing for IPAM

This section describes how to view pricing-related information and your current IPAM costs.

## View pricing information

IPAM is offered in two tiers: Free and Advanced Tier. For more information about the features available in each tier and the costs associated with the tiers, see the **IPAM** tab on the [Amazon VPC pricing page](#).

## View your current costs and usage using Amazon Cost Explorer

When you use the IPAM Advanced Tier, you pay an hourly price per active IP address managed by IPAM. If you want to view and analyze your IPAM costs and usage, you can use the Amazon Cost Explorer.

1. Open the Amazon Cost Management console at <https://console.amazonaws.cn/cost-management/home>.
2. Choose **Cost Explorer**.
3. Filter for IPAM usage by choosing **Usage type** and entering **IPAddressManager**.
4. Select one or more checkboxes. Each of them represents a different Amazon Region.
5. Click **Apply**.

If, for example, you select *USE1-IPAddressManager-IP-Hours(Hrs)*, you'll see the number of active IP hours billed by IPAM in the us-east-1 Region and the cost. If, say, the usage in hours is 18, this means that you could have 1 active IP address for 18 hours, 3 IP address each active for 6 hours, or any combination of these that add up to 18 hours.

For more information about Amazon Cost Explorer, see [Analyzing your costs with Amazon Cost Explorer](#) in the *Amazon Cost Management User Guide*.

## Related information

The following related resources can help you as you work with this service.

- [Amazon VPC IP Address Manager Best Practices](#): An Amazon blog on best practices for planning and creating a scalable address scheme with Amazon VPC IP Address Manager.
- [Network Address Management and Auditing at Scale with Amazon VPC IP Address Manager](#): An Amazon blog that introduces Amazon VPC IP Address Manager and shows you how to use the service in the Amazon console.
- [Configure fine-grained access to your resources shared using Amazon Resource Access Manager](#): An Amazon blog that explains how to share an IPAM pool with the accounts in an Amazon Organizations organization unit.

# Document history for IPAM

The following table describes the releases for IPAM.

| Feature                                                                      | Description                                                                                                                                                                                                                | Release Date      |
|------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------|
| <a href="#">IPAM Free and Advanced Tiers</a>                                 | You can now choose between Free Tier and Advanced Tier for your IPAM.                                                                                                                                                      | November 17, 2023 |
| <a href="#">Public IP insights</a>                                           | Previously, you could only view public IP insights in a single Region. You can now view public IP insights across Regions. In addition, you can now view <a href="#">public IP address insights in Amazon CloudWatch</a> . | November 17, 2023 |
| <a href="#">Plan VPC IP address space for subnet IP allocations</a>          | You can now use IPAM to plan for subnet IP space within a VPC and monitor IP address-related metrics at the subnet and VPC level.                                                                                          | November 17, 2023 |
| <a href="#">Bring your own ASN (BYOASN)</a>                                  | You can now bring your own autonomous system number (ASN) to Amazon.                                                                                                                                                       | November 17, 2023 |
| <a href="#">Amazon managed policy updates</a> - Update to an existing policy | Existing AWSIPAMServiceRolePolicy updated.                                                                                                                                                                                 | November 17, 2023 |
| <a href="#">Amazon managed policy updates</a> - Update to an existing policy | Existing AWSIPAMServiceRolePolicy updated.                                                                                                                                                                                 | November 1, 2023  |
| <a href="#">Resource utilization metrics</a>                                 | IPAM now publishes IP utilization metrics for resources that the IPAM monitors to Amazon CloudWatch.                                                                                                                       | August 2, 2023    |

| Feature                                                                      | Description                                                                                                                                                                                                                               | Release Date     |
|------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------|
| <a href="#">Public IP insights</a>                                           | Public IP insights shows you all public IPv4 addresses used by services in this Region in your account. You can use these insights to identify public IPv4 address usage and view recommendations to release unused Elastic IP addresses. | July 28, 2023    |
| <a href="#">Amazon managed policy updates</a> - Update to an existing policy | Existing AWSIPAMServiceRolePolicy updated.                                                                                                                                                                                                | January 25, 2023 |
| <a href="#">Integrate IPAM with accounts outside of your organization</a>    | You can now manage IP addresses outside of your organization from a single IPAM account and share IPAM pools with the accounts of other Amazon Organizations.                                                                             | January 25, 2023 |
| Amazon-provided IPv6 contiguous CIDR block for IPAM pools                    | When you create an IPAM pool in the public scope, you can now provision an Amazon-provided IPv6 contiguous CIDR block to the pool. For more information, see <a href="#">Create IPv6 pools</a> .                                          | January 25, 2023 |
| Initial release                                                              | This release introduces Amazon VPC IP Address Manager.                                                                                                                                                                                    | December 2, 2021 |