

Amazon IoT Events



Amazon IoT Events: Developer Guide

Table of Contents

What is Amazon IoT Events?	1
Benefits and features	1
Use cases	2
Monitor and maintain remote devices	2
Manage industrial robots	3
Track building automation systems	3
Setting up	4
Setting up an Amazon Web Services account	4
Sign up for an Amazon Web Services account	4
Secure IAM users	4
Setting up permissions for Amazon IoT Events	5
Action permissions	5
Securing input data	7
Amazon CloudWatch logging role policy	8
Amazon SNS messaging role policy	10
Getting started	12
Prerequisites	14
Create an input	15
Create a JSON input file	15
Create and configure an input	15
Create an input within the Detector Model	16
Create a detector model	17
Test the detector model	24
Best practices	28
Enable Amazon CloudWatch logging when developing Amazon IoT Events detector models ...	28
Publish regularly to save your detector model when working in the Amazon IoT Events console	29
Tutorials	30
Using Amazon IoT Events to monitor your IoT devices	30
How do you know which states you need in a detector model?	32
How do you know if you need one instance of a detector or several?	33
Simple step-by-step example	34
Create an input to capture device data	36
Create a detector model to represent device states	37

Send messages as inputs to a detector	41
Detector model restrictions and limitations	44
A commented example: HVAC temperature control	48
Input definitions for detector models	49
Create a detector model definition	52
Use BatchUpdateDetector	72
Use BatchPutMessage for inputs	74
Ingest MQTT messages	77
Generate Amazon SNS messages	78
Configure the DescribeDetector API	79
Use the Amazon IoT Core rules engine	81
Supported actions	85
Use built-in actions	86
Set timer action	86
Reset timer action	86
Clear timer action	87
Set variable action	87
Work with other Amazon services	88
Amazon IoT Core	89
Amazon IoT Events	90
Amazon IoT SiteWise	91
Amazon DynamoDB	93
Amazon DynamoDB(v2)	96
Amazon Data Firehose	97
Amazon Lambda	98
Amazon Simple Notification Service	99
Amazon Simple Queue Service	100
Expressions	102
Syntax to filter device data	102
Literals	102
Operators	102
Functions for expressions	104
Reference for inputs and variables in expressions	108
Substitution templates	111
Usage	112
Writing Amazon IoT Events expressions	112


Detector model examples	114
HVAC temperature control	114
Background story	114
Input definitions	115
Detector model definition	117
BatchPutMessage examples	135
BatchUpdateDetector example	141
Amazon IoT Core rules engine	143
Cranes	146
Send commands	147
Detector models	148
Inputs	155
Messages	155
Example: Event detection with sensors	157
Device HeartBeat	159
ISA alarm	162
Simple alarm	172
Monitoring with alarms	177
Working with Amazon IoT SiteWise	177
Acknowledge flow	178
Creating an alarm model	178
Requirements	179
Creating an alarm model (console)	179
Responding to alarms	182
Managing alarm notifications	184
Creating a Lambda function	184
Using the Lambda function	193
Manage alarm recipients	194
Security	196
Identity and access management	196
Audience	197
Authenticating with identities	198
Managing access using policies	200
More about identity and access management	202
How Amazon IoT Events works with IAM	202
Identity-based policy examples	206

Cross-service confused deputy prevention for Amazon IoT Events	212
Troubleshooting	216
Monitoring	218
Available tools to monitor Amazon IoT Events	219
Monitoring Amazon IoT Events with Amazon CloudWatch	220
Logging Amazon IoT Events API calls with Amazon CloudTrail	222
Compliance validation	241
Resilience	242
Infrastructure security	243
Quotas	244
Tagging	245
Tag basics	245
Tag restrictions and limitations	246
Using tags with IAM policies	246
Troubleshooting	250
Common Amazon IoT Events issues and solutions	250
Detector model creation errors	251
Updates from a deleted detector model	251
Action trigger failure (when meeting a condition)	251
Action trigger failure (when breaching a threshold)	252
Incorrect state usage	252
Connection message	252
InvalidRequestException message	253
Amazon CloudWatch Logs <code>action.setTimer</code> errors	253
Amazon CloudWatch payload errors	254
Incompatible data types	256
Failed to send message to Amazon IoT Events	257
Troubleshooting a detector model	258
Diagnostic information	258
Analyze a detector model (Console)	270
Analyze a detector model (Amazon CLI)	271
Commands	277
Amazon IoT Events actions	277
Amazon IoT Events data	277
Document history	278
Earlier updates	279

What is Amazon IoT Events?

Amazon IoT Events enables you to monitor your equipment or device fleets for failures or changes in operation, and to trigger actions when such events occur. Amazon IoT Events continuously watches IoT sensor data from devices, processes, applications, and other Amazon services to identify significant events so you can take action.

Use Amazon IoT Events to build complex event monitoring applications in the Amazon Cloud that you can access through the Amazon IoT Events console or APIs.



Topics

- [Benefits and features](#)
- [Use cases](#)

Benefits and features

Accept inputs from multiple sources

Amazon IoT Events accepts inputs from many IoT telemetry data sources. These include sensor devices, management applications, and other Amazon IoT services, such as Amazon IoT Core and Amazon IoT Analytics. You can push any telemetry data input to Amazon IoT Events by using a standard API interface (BatchPutMessage API) or the Amazon IoT Events console.

For more information on getting started with Amazon IoT Events, see [Getting started with the Amazon IoT Events console](#).

Use simple logical expressions to recognize complex patterns of events

Amazon IoT Events can recognize patterns of events that involve multiple inputs from a single IoT device or application, or from diverse equipment and many independent sensors. This is especially useful because each sensor and application provides important information. But only by combining diverse sensor and application data can you get a complete picture of the performance and quality of operations. You can configure Amazon IoT Events detectors to recognize these events using simple logical expressions instead of complex code.

For more information on logical expressions, see [Expressions to filter, transform, and process event data](#).

Trigger actions based on events

Amazon IoT Events enables you to directly trigger actions in Amazon Simple Notification Service (Amazon SNS), Amazon IoT Core, Lambda, Amazon SQS and Amazon Kinesis Firehose. You can also trigger an Amazon Lambda function using the Amazon IoT rules engine which makes it possible to take actions using other services, such as Amazon Connect, or your own enterprise resource planning (ERP) applications.

Amazon IoT Events includes a prebuilt library of actions you can take, and also enables you to define your own.

To learn more about triggering actions based on events, see [Supported actions to receive data and trigger actions in Amazon IoT Events](#).

Automatically scale to meet the demands of your fleet

Amazon IoT Events scales automatically when you are connecting homogeneous devices. You can define a detector once for a specific type of device, and the service will automatically scale and manage all instances of that device that connect to Amazon IoT Events.

To explore examples of detector models, see [Amazon IoT Events detector model examples](#).

Use cases

Amazon IoT Events has many uses. Here are a few example use cases.

Monitor and maintain remote devices

Monitoring a fleet of remotely deployed machines can be challenging, especially when a malfunction occurs without clear context. If one machine stops functioning, this might mean

replacing the entire processing unit or machine. But this isn't sustainable. With Amazon IoT Events you can receive messages from multiple sensors on each machine to help you diagnose specific issues over time. Instead of replacing the whole unit, you now have the necessary information to send a technician with the exact part that needs replacement. With millions of machines, savings can add up to millions of dollars, lowering your total cost of owning or maintaining each machine.

Manage industrial robots

Deploying robots in your facilities to automate package movement can greatly enhance efficiency. To minimize costs, robots can be equipped with simple, low-cost sensors that report data to the cloud. However, with dozens of sensors and hundreds of operating modes, detecting issues in real time can be challenging. Using Amazon IoT Events, you can build an expert system that processes this sensor data in the cloud, creating alerts to automatically notify technical staff if a failure is imminent.

Track building automation systems

In data centers, monitoring for high temperatures and low humidity helps to prevent equipment failures. Sensors are often purchased from many manufacturers and each type comes with its own management software. However, management software from different vendors sometimes isn't compatible, making it difficult to detect problems. Using Amazon IoT Events, you can set up alerts to notify your operations analysts of issues with your heating and cooling systems well in advance of failures. In this way, you can prevent an unscheduled data center shutdown that would cost thousands of dollars in equipment replacement and potential lost revenue.

Setting up Amazon IoT Events

This section provides a guide to setting up Amazon IoT Events, including creating an Amazon account, configuring necessary permissions, and establishing roles for managing access to resources.

Topics

- [Setting up an Amazon Web Services account](#)
- [Setting up permissions for Amazon IoT Events](#)

Setting up an Amazon Web Services account

Sign up for an Amazon Web Services account

If you do not have an Amazon Web Services account, use the following procedure to create one.

To sign up for Amazon Web Services

1. Open <http://www.amazonaws.cn/> and choose **Sign Up**.
2. Follow the on-screen instructions.

Amazon sends you a confirmation email after the sign-up process is complete. At any time, you can view your current account activity and manage your account by going to <http://www.amazonaws.cn/> and choosing **My Account**.

Secure IAM users

After you sign up for an Amazon Web Services account, safeguard your administrative user by turning on multi-factor authentication (MFA). For instructions, see [Enable a virtual MFA device for an IAM user \(console\)](#) in the *IAM User Guide*.

To give other users access to your Amazon Web Services account resources, create IAM users. To secure your IAM users, turn on MFA and only give the IAM users the permissions needed to perform their tasks.

For more information about creating and securing IAM users, see the following topics in the *IAM User Guide*:

- [Creating an IAM user in your Amazon Web Services account](#)
- [Access management for Amazon resources](#)
- [Example IAM identity-based policies](#)

Setting up permissions for Amazon IoT Events

Implementing proper permissions is important for secure and effective use of Amazon IoT Events. This section describes the permissions that are required to use some features of Amazon IoT Events. You can use Amazon CLI commands or the Amazon Identity and Access Management (IAM) console to create roles and associated permission policies to access resources or perform certain functions in Amazon IoT Events.

The [IAM User Guide](#) has more detailed information about securely controlling permissions to access Amazon resources. For information specific to Amazon IoT Events, see [Actions, resources, and condition keys for Amazon IoT Events](#).

To use the IAM console to create and manage roles and permissions, see [IAM tutorial: Delegate access across Amazon accounts using IAM roles](#).

Note

Keys can be 1-128 characters and can include:

- uppercase or lowercase letters a-z
- numbers 0-9
- special characters -, _, or :.

Action permissions for Amazon IoT Events

Amazon IoT Events enables you to trigger actions which use other Amazon services. To do so, you must grant Amazon IoT Events permission to perform these actions on your behalf. This section contains a list of the actions and an example policy which grants permission to perform all these actions on your resources. Change the *region* and *account-id* references as required. When possible, you should also change the wildcards (*) to refer to specific resources that will be accessed. You can use the IAM console to grant permission to Amazon IoT Events to send an Amazon SNS alert that you have defined. .

Amazon IoT Events supports the following actions that let you use a timer or set a variable:

- [setTimer](#) to create a timer.
- [resetTimer](#) to reset the timer.
- [clearTimer](#) to delete the timer.
- [setVariable](#) to create a variable.

Amazon IoT Events supports the following actions that let you work with Amazon services:

- [iotTopicPublish](#) to publish a message on an MQTT topic.
- [iotEvents](#) to send data to Amazon IoT Events as an input value.
- [iotSiteWise](#) to send data to an asset property in Amazon IoT SiteWise.
- [dynamoDB](#) to send data to an Amazon DynamoDB table.
- [dynamoDBv2](#) to send data to an Amazon DynamoDB table.
- [firehose](#) to send data to an Amazon Data Firehose stream.
- [lambda](#) to invoke an Amazon Lambda function.
- [sns](#) to send data as a push notification.
- [sqs](#) to send data to an Amazon SQS queue.

Example Policy

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": "iot:Publish",
      "Resource": "arn:aws-cn:iot:<region>:<account_id>:topic/*"
    },
    {
      "Effect": "Allow",
      "Action": "iotevents:BatchPutMessage",
      "Resource": "arn:aws-cn:iotevents:<region>:<account_id>:input/*"
    },
    {
      "Effect": "Allow",
      "Action": "iotsitewise:BatchPutAssetPropertyValue",
```

```

    "Resource": "*"
  },
  {
    "Effect": "Allow",
    "Action": "dynamodb:PutItem",
    "Resource": "arn:aws-cn:dynamodb:<region>:<account_id>:table/*"
  },
  {
    "Effect": "Allow",
    "Action": [
      "firehose:PutRecord",
      "firehose:PutRecordBatch"
    ],
    "Resource": "arn:aws-cn:firehose:<region>:<account_id>:deliverystream/*"
  },
  {
    "Effect": "Allow",
    "Action": "lambda:InvokeFunction",
    "Resource": "arn:aws-cn:lambda:<region>:<account_id>:function:*"
  },
  {
    "Effect": "Allow",
    "Action": "sns:Publish",
    "Resource": "arn:aws-cn:sns:<region>:<account_id>:*"
  },
  {
    "Effect": "Allow",
    "Action": "sqs:SendMessage",
    "Resource": "arn:aws-cn:sqs:<region>:<account_id>:*"
  }
]
}

```

Securing input data in Amazon IoT Events

It's important to consider who can grant access to input data for use in a detector model. If you have a user or entity whose overall permissions you want to restrict, but that is permitted to create or update a detector model, you must also grant permission for that user or entity to update input routing. This means that in addition to granting permission for `iotevents:CreateDetectorModel` and `iotevents:UpdateDetectorModel`, you must also grant permission for `iotevents:UpdateInputRouting`.

Example

The following policy adds permission for `iotevents:UpdateInputRouting`.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "updateRoutingPolicy",
      "Effect": "Allow",
      "Action": [
        "iotevents:UpdateInputRouting"
      ],
      "Resource": "*"
    }
  ]
}
```

You can specify a list of input Amazon Resource Names (ARNs) instead of the wildcard "*" for the "Resource" to limit this permission to specific inputs. This enables you to restrict access to the input data that is consumed by detector models created or updated by the user or entity.

Amazon CloudWatch logging role policy for Amazon IoT Events

The following policy documents provide the role policy and trust policy that allow Amazon IoT Events to submit logs to CloudWatch on your behalf.

Role policy:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "logs:CreateLogGroup",
        "logs:CreateLogStream",
        "logs:PutLogEvents",
        "logs:PutMetricFilter",
        "logs:PutRetentionPolicy",
        "logs:GetLogEvents",
        "logs>DeleteLogStream"
      ]
    }
  ]
}
```

```

        ],
        "Resource": [
            "arn:aws-cn:logs:*:*:*"
        ]
    }
]
}

```

Trust policy:

```

{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "Service": [
          "iotevents.amazonaws.com"
        ]
      },
      "Action": "sts:AssumeRole"
    }
  ]
}

```

You also need an IAM permissions policy attached to the user that allows the user to pass roles, as follows. For more information, see [Granting a user permissions to pass a role to an Amazon service](#) in the *IAM User Guide*.

```

{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "",
      "Effect": "Allow",
      "Action": [
        "iam:GetRole",
        "iam:PassRole"
      ],
      "Resource": "arn:aws-cn:iam::<account-id>:role/Role_To_Pass"
    }
  ]
}

```

```
]
}
```

You can use the following command to put the resource policy for CloudWatch logs. This allows Amazon IoT Events to put log events into CloudWatch streams.

```
aws logs put-resource-policy --policy-name ioteventsLoggingPolicy --policy-
document "{ \"Version\": \"2012-10-17\", \"Statement\": [ { \"Sid\":
  \"IoTEventsToCloudWatchLogs\", \"Effect\": \"Allow\", \"Principal\": { \"Service\":
  [ \"iotevents.amazonaws.com\" ] }, \"Action\": \"logs:PutLogEvents\", \"Resource\": \"*
  \" } ] }"
```

Use the following command to put logging options. Replace the `roleArn` with the logging role that you created.

```
aws iotevents put-logging-options --cli-input-json "{ \"loggingOptions\": {\"roleArn\":
  \"arn:aws-cn:iam::123456789012:role/testLoggingRole\", \"level\": \"INFO\", \"enabled
  \": true } }"
```

Amazon SNS messaging role policy for Amazon IoT Events

Integrating Amazon IoT Events with Amazon SNS requires careful permission management for secure and efficient notification delivery. This guide walks you through the process of configuring IAM roles and policies to allow Amazon IoT Events to publish messages to Amazon SNS topics.

The following policy documents provide the role policy and trust policy that allow Amazon IoT Events to send SNS messages.

Role policy:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Action": [
        "sns:*"
      ],
      "Effect": "Allow",
      "Resource": "arn:aws-cn:sns:us-east-1:123456789012:testAction"
```



```
    }  
  ]  
}
```

Trust policy:

```
{  
  "Version": "2012-10-17",  
  "Statement": [  
    {  
      "Sid": "",  
      "Effect": "Allow",  
      "Principal": {  
        "Service": [  
          "iotevents.amazonaws.com"  
        ]  
      },  
      "Action": "sts:AssumeRole"  
    }  
  ]  
}
```

Getting started with the Amazon IoT Events console

This section shows you how to create an input and a detector model using the [Amazon IoT Events console](#). You model two states of an engine: a normal state and an over-pressure condition. When the measured pressure in the engine exceeds a certain threshold, the model transitions from the normal state to the over-pressure state. Then it sends an Amazon SNS message to alert a technician about the condition. When the pressure again drops below the threshold for three consecutive pressure readings, the model returns to the normal state and sends another Amazon SNS message as a confirmation.

We check for three consecutive readings below the pressure threshold to eliminate possible stuttering of over-pressure or normal messages, in case of a nonlinear recovery phase or an anomalous pressure reading.

On the console, you can also find several pre-made detector model templates which you can customize. You can also use the console to import detector models that others have written or export your detector models and use them in different Amazon Regions. If you import a detector model, make sure that you create the required inputs or recreate them for the new Region, and update any role ARNs used.

Use the Amazon IoT Events console to learn about the following.

Define inputs

To monitor your devices and processes, they must have a way to get telemetry data into Amazon IoT Events. This is done by sending messages as *inputs* to Amazon IoT Events. You can do this in several ways:

- Use the [BatchPutMessage](#) operation.
- In Amazon IoT Core, write an [Amazon IoT Events action](#) rule for the Amazon IoT rules engine that forwards your message data into Amazon IoT Events. You must identify the input by name.
- In Amazon IoT Analytics, use the [CreateDataset](#) operation to create a data set with `contentDeliveryRules`. These rules specify the Amazon IoT Events input where data set contents are sent automatically.

Before your devices can send data in this way, you must define one or more inputs. To do so, give each input a name and specify which fields in the incoming message data the input monitors.

Create a detector model

Define a *detector model* (a model of your equipment or process) using *states*. For each state, define conditional (Boolean) logic that evaluates the incoming inputs to detect significant events. When the detector model detects an event, it can change the state or initiate custom-built or predefined actions using other Amazon services. You can define additional events that initiate actions when entering or exiting a state and, optionally, when a condition is met.

In this tutorial, you send an Amazon SNS message as the action when the model enters or exits a certain state.

Monitor a device or process

If you monitor several devices or processes, specify a field in each input that identifies the particular device or process from which the input comes. See the `key` field in `CreateDetectorModel`. When the input field identified by the key recognizes a new value, a new device is identified and a detector is created. Each detector is an instance of the detector model. The new detector continues responding to inputs coming from that device until its detector model is updated or deleted.

If you monitor a single process (even if several devices or subprocesses are sending inputs), you don't specify a unique identifying key field. In this case, the model creates a single detector (instance) when the first input arrives.

Send messages as inputs to your detector model

There are several ways to send a message from a device or process as an input into an Amazon IoT Events detector that don't require you to perform additional formatting on the message. In this tutorial, you use the Amazon IoT console to write an [Amazon IoT Events action](#) rule for the Amazon IoT rules engine that forwards your message data into Amazon IoT Events.

To do this, identify the input by name and continue to use the Amazon IoT console to generate messages that are forwarded as inputs to Amazon IoT Events.

Note

This tutorial uses the console to create the same `input` and `detector_model` shown in the example at [Tutorials for Amazon IoT Events uses cases](#). You can use the this JSON example to help you follow the tutorial.

Topics

- [Prerequisites to get started with Amazon IoT Events](#)
- [Create an input for models in Amazon IoT Events](#)
- [Create a detector model in Amazon IoT Events](#)
- [Send inputs to test the detector model in Amazon IoT Events](#)

Prerequisites to get started with Amazon IoT Events

If you don't have an Amazon account, create one.

1. Follow the step in [Setting up Amazon IoT Events](#) to ensure proper account setup and permissions.
2. Create two Amazon Simple Notification Service (Amazon SNS) topics.

This tutorial (and the corresponding example) assume that you created two Amazon SNS topics. The ARNs of these topics are shown as: `arn:aws-cn:sns:us-east-1:123456789012:underPressureAction` and `arn:aws-cn:sns:us-east-1:123456789012:pressureClearedAction`. Replace these values with the ARNs of Amazon SNS topics that you create. For more information, see the [Amazon Simple Notification Service Developer Guide](#).

As an alternative to publishing alerts to Amazon SNS topics, you can have the detectors send MQTT messages with a topic that you specify. With this option, you can verify that your detector model is creating instances and that those instances are sending alerts by using the Amazon IoT Core console to subscribe to and monitor messages sent to those MQTT topics. You can also define the MQTT topic name dynamically at runtime by using an input or variable created in the detector model.

3. Choose an Amazon Web Services Region that supports Amazon IoT Events. For more information, see [Amazon IoT Events](#) in the *Amazon Web Services General Reference*. For help, see [Getting started with a service in the Amazon Web Services Management Console](#) in the *Getting Started with the Amazon Web Services Management Console*.

Create an input for models in Amazon IoT Events

When you construct the inputs for your models, we recommend gathering files that contain sample message payloads that your devices or processes send to report their health status. Having these files helps you define the inputs that are required.

You can create an input through multiple methods that are described in this section.

Create a JSON input file

1. To get started, create a file named `input.json` on your local file system with the following contents:

```
{
  "motorid": "Fulton-A32",
  "sensorData": {
    "pressure": 23,
    "temperature": 47
  }
}
```

2. Now that you have this starter `input.json` file, you can create an input. There are two ways to create an input. You can create an input by using the navigation pane in the [Amazon IoT Events console](#). Or, you can create an input within the detector model after it's created.

Create and configure an input

Learn how to create an *input*, for an alarm model or a detector model.

1. Log into the [Amazon IoT Events console](#) or select the option to Create a new Amazon IoT Events account.
2. In the Amazon IoT Events console, in the upper left corner, select and expand the navigation pane.
3. In the left navigation pane, select **Inputs**.
4. In the right corner of the console, choose **Create input**.
5. Provide a unique **InputName**.
6. *Optional* – enter a **Description** for your input.

7. To **Upload a JSON file**, select the `input.json` file that you created in the overview for [Create a JSON input file](#). **Choose input attributes** appears with a list of your entered attributes.
8. For **Choose input attributes**, select the attributes to use, and choose **Create**. In this example, we select **motorid** and **sensorData.pressure**.
9. *Optional* – Add relevant **Tags** to the input.

Note

You can also create additional inputs within the detector model in the [Amazon IoT Events console](#). For more information, see [Create an input within the Detector Model in Amazon IoT Events](#).

Create an input within the Detector Model in Amazon IoT Events

Detector inputs in Amazon IoT Events serve as the bridge between your data sources and detector models. Detector inputs provide the raw data that powers the event detection and automation capabilities of Amazon IoT Events. Learn to configure detector inputs to help your models respond accurately to real-world events and conditions in your IoT ecosystem.

This section shows how to define an *input* for a detector model to receive telemetry data, or messages.

To define an input for a detector model

1. Open the [Amazon IoT Events console](#).
2. In the Amazon IoT Events console, choose **Create detector model**.
3. Choose **Create new**.
4. Choose **Create input**.
5. For the input, enter an **InputName**, an optional **Description**, and choose **Upload file**. In the dialog box that displays, select the `input.json` file that you created in the overview for [Create a JSON input file](#).
6. For **Choose input attributes**, select the attributes to use, and choose **Create**. In this example, we select **motorid** and **sensorData.pressure**.

Create a detector model in Amazon IoT Events

In this topic, you define a *detector model* (a model of your equipment or process) using *states*.

For each state, you define conditional (Boolean) logic that evaluates the incoming inputs to detect a significant event. When an event is detected, it changes the state and can initiate additional actions. These events are known as transition events.

In your states, you also define events that can run actions whenever the detector enters or exits that state or when an input is received (these are known as `OnEnter`, `OnExit` and `OnInput` events). The actions run only if the event's conditional logic evaluates to `true`.

To create a detector model

1. The first detector state has been created for you. To modify it, select the circle with label **State_1** in the main editing space.
2. In the **State** pane, enter the **State name** and **OnEnter**, choose **Add event**.
3. On the **Add OnEnter event** page, enter an **Event name** and the **Event condition**. In this example, enter `true` to indicate the event is always initiated when the state is entered.
4. Under **Event actions**, choose **Add action**.
5. Under **Event actions**, do the following:
 - a. Select **Set variable**
 - b. For **Variable operation**, choose **Assign value**.
 - c. For **Variable name**, enter the name of the variable to set.
 - d. For **Variable value**, enter the value `0` (zero).
6. Choose **Save**.

A variable, like the one you defined, can be set (given a value) in any event in the detector model. The variable's value can only be referenced (for example, in an event's conditional logic) after the detector has reached a state and run an action where it is defined or set.

7. In the **State** pane, choose the **X** next to **State** to return to the **Detector model palette**.
8. To create a second detector state, in the **Detector model palette**, choose **State** and drag it into the main editing space. This creates a state titled `untitled_state_1`.
9. Pause on the first state (**Normal**). An arrow appears on the circumference of the state.

10. Click and drag the arrow from the first state to the second state. A directed line from the first state to the second state (labeled **Untitled**) appears.
11. Select the **Untitled** line. In the **Transition event** pane, enter an **Event name** and **Event trigger logic**.
12. In the **Transition event** pane, choose **Add action**.
13. On the **Add transition event actions** pane, choose **Add action**.
14. For **Choose an action**, choose **Set variable**.
 - a. For **Variable operation**, choose **Assign value**.
 - b. For **Variable name**, enter the name of the variable.
 - c. For **Assign value**, enter the value such as: `$variable.pressureThresholdBreached + 3`
 - d. Choose **Save**.
15. Select the second state **untitled_state_1**.
16. In the **State** pane, enter the **State name** and for **On Enter**, choose **Add event**.
17. On the **Add OnEnter event** page, enter the **Event name** and **Event condition**. Choose **Add action**.
18. For **Choose an action**, choose **Send SNS message**.
 - a. For **SNS topic**, enter the target ARN of your Amazon SNS topic.
 - b. Choose **Save**.
19. Continue to add the events in the example.
 - a. For **OnInput**, choose **Add event**, and enter and save the following event information.

```
Event name: Overpressurized
Event condition: $input.PressureInput.sensorData.pressure > 70
Event actions:
  Set variable:
    Variable operation: Assign value
    Variable name: pressureThresholdBreached
    Assign value: 3
```

- b. For **OnInput**, choose **Add event**, and enter and save the following event information.

```
Event name: Pressure Okay
```



```

Event condition: $input.PressureInput.sensorData.pressure <= 70
Event actions:
  Set variable:
    Variable operation: Decrement
    Variable name: pressureThresholdBreached

```

- c. For **OnExit**, choose **Add event**, and enter and save the following event information using the ARN of the Amazon SNS topic that you created.

```

Event name: Normal Pressure Restored
Event condition: true
Event actions:
  Send SNS message:
    Target arn: arn:aws:sns:us-east-1:123456789012:pressureClearedAction

```

20. Pause on the second state (**Dangerous**). An arrow appears on the circumference of the state
21. Click and drag the arrow from the second state to the first state. A directed line with label **Untitled** appears.
22. Choose the **Untitled** line and in the **Transition event** pane, enter an **Event name** and **Event trigger logic** using the following information.

```

{
  Event name: BackToNormal
  Event trigger logic: $input.PressureInput.sensorData.pressure <= 70 &&
    $variable.pressureThresholdBreached <= 0
}

```

For more information about why we test for the `$input` value and the `$variable` value in the trigger logic, see the entry for availability of variable values in [Amazon IoT Events detector model restrictions and limitations](#).

23. Select the **Start** state. By default, this state was created when you created a detector model). In the **Start** pane, choose the **Destination state** (for example, **Normal**).
24. Next, configure your detector model to listen for inputs. In the upper-right corner, choose **Publish**.
25. On the **Publish detector model** page, do the following.
 - a. Enter a **Detector model name**, a **Description**, and the name of a **Role**. This role is created for you.

- b. Choose **Create a detector for each unique key value**. To create and use your own **Role**, follow the steps in [Setting up permissions for Amazon IoT Events](#) and enter it as the **Role** here.
26. For **Detector creation key**, choose the name of one of the attributes of the input you defined earlier. The attribute that you choose as the detector creation key must be present in each message input, and must be unique to each device that sends messages. This example uses the **motorid** attribute.
27. Choose **Save and publish**.

Note

The number of unique detectors created for a given detector model is based on the input messages sent. When a detector model is created, a key is selected from the input attributes. This key determines which detector instance to use. If the key hasn't been seen before (for this detector model), a new detector instance is created. If the key has been seen before, we use the existing detector instance corresponding to this key value.

You can make a backup copy of your detector model definition (in JSON) recreate or update the detector model or use as a template to create another detector model.

You can do this from the console or by using the following CLI command. If necessary, change the name of the detector model to match what you used when you published it in the previous step.

```
aws iotevents describe-detector-model --detector-model-name motorDetectorModel >
motorDetectorModel.json
```

This creates a file (`motorDetectorModel.json`) that has contents similar to the following.

```
{
  "detectorModel": {
    "detectorModelConfiguration": {
      "status": "ACTIVE",
      "lastUpdateTime": 1552072424.212,
      "roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole",
      "creationTime": 1552072424.212,
      "detectorModelArn": "arn:aws:iotevents:us-
west-2:123456789012:detectorModel/motorDetectorModel",
```

```

        "key": "motorid",
        "detectorModelName": "motorDetectorModel",
        "detectorModelVersion": "1"
    },
    "detectorModelDefinition": {
        "states": [
            {
                "onInput": {
                    "transitionEvents": [
                        {
                            "eventName": "Overpressurized",
                            "actions": [
                                {
                                    "setVariable": {
                                        "variableName":
"pressureThresholdBreached",
                                        "value":
"$variable.pressureThresholdBreached + 3"
                                    }
                                }
                            ],
                            "condition": "$input.PressureInput.sensorData.pressure
> 70",
                            "nextState": "Dangerous"
                        }
                    ],
                    "events": []
                },
                "stateName": "Normal",
                "onEnter": {
                    "events": [
                        {
                            "eventName": "init",
                            "actions": [
                                {
                                    "setVariable": {
                                        "variableName":
"pressureThresholdBreached",
                                        "value": "0"
                                    }
                                }
                            ],
                            "condition": "true"
                        }
                    ]
                }
            }
        ]
    }
}

```

```

    ]
  },
  "onExit": {
    "events": []
  }
},
{
  "onInput": {
    "transitionEvents": [
      {
        "eventName": "Back to Normal",
        "actions": [],
        "condition": "$variable.pressureThresholdBreachd <= 1
&& $input.PressureInput.sensorData.pressure <= 70",
        "nextState": "Normal"
      }
    ],
    "events": [
      {
        "eventName": "Overpressurized",
        "actions": [
          {
            "setVariable": {
              "variableName":
"pressureThresholdBreachd",
              "value": "3"
            }
          }
        ],
        "condition": "$input.PressureInput.sensorData.pressure
> 70"
      },
      {
        "eventName": "Pressure Okay",
        "actions": [
          {
            "setVariable": {
              "variableName":
"pressureThresholdBreachd",
              "value":
"$variable.pressureThresholdBreachd - 1"
            }
          }
        ]
      }
    ]
  }
}

```

```

        "condition": "$input.PressureInput.sensorData.pressure
<= 70"
    }
  ]
},
"stateName": "Dangerous",
"onEnter": {
  "events": [
    {
      "eventName": "Pressure Threshold Breached",
      "actions": [
        {
          "sns": {
            "targetArn": "arn:aws:sns:us-
west-2:123456789012:MyIoTButtonSNSTopic"
          }
        }
      ],
      "condition": "$variable.pressureThresholdBreached > 1"
    }
  ]
},
"onExit": {
  "events": [
    {
      "eventName": "Normal Pressure Restored",
      "actions": [
        {
          "sns": {
            "targetArn": "arn:aws:sns:us-
west-2:123456789012:IoTVirtualButtonTopic"
          }
        }
      ],
      "condition": "true"
    }
  ]
}
},
"initialStateName": "Normal"
}
}

```

```
}
```

Send inputs to test the detector model in Amazon IoT Events

There are several ways to receive telemetry data in Amazon IoT Events (see [Supported actions to receive data and trigger actions in Amazon IoT Events](#)). This topic shows you how to create an Amazon IoT rule in the Amazon IoT console that forwards messages as inputs to your Amazon IoT Events detector. You can use the Amazon IoT console's MQTT client to send test messages. You can use this method to get telemetry data into Amazon IoT Events when your devices are able to send MQTT messages using the Amazon IoT message broker.

To send inputs to test the detector model

1. Open the [Amazon IoT Core console](#). In the left navigation pane, under **Manage**, choose **Message routing**, then choose **Rules**.
2. Choose **Create rule** in the upper right.
3. On the **Create a rule** page, complete the following steps:

1. Step 1. Specify rule properties. Complete the following fields:

- **Rule name.** Enter a name for your rule, such as `MyIoTEventsRule`.

Note

Do not use spaces.

- **Rule description.** This is optional.
- Choose **Next**.

2. Step 2. Configure SQL statement. Complete the following fields:

- **SQL version.** Select the appropriate option from the list.
- **SQL statement.** Enter `SELECT *, topic(2) as motorid FROM 'motors/+/' status'`.

Choose **Next**.

3. Step 3. Attach rule actions. In the **Rule actions** section, complete the following:

- **Action 1. Select IoT Events.** The following fields appear:

- a. **Input name.** Select the appropriate option from the list. If your input doesn't appear, choose **Refresh**.

To create a new input, choose **Create IoT Events input**. Complete the following fields:

- **Input name.** Enter PressureInput.
- **Description.** This is optional.
- **Upload a JSON file.** Upload a copy of your JSON file. There is a link to a sample file on this screen, if you don't have a file. The code includes:

```
{
  "motorid": "Fulton-A32",
  "sensorData": {
    "pressure": 23,
    "temperature": 47
  }
}
```

- **Choose input attributes.** Select the appropriate option(s).
- **Tags.** This is optional.

Choose **Create**.

Return to the **Create rule** screen and refresh the **Input name** field. Select the input you just created.

- b. **Batch mode.** This is optional. If the payload is an array of messages, select this option.
- c. **Message ID.** This is optional, but recommended.
- d. **IAM role.** Select the appropriate role from the list. If the role isn't listed, choose **Create new role**.

Type a **Role name** and choose **Create**.

To add another rule, choose **Add rule action**


- **Error action.** This section is optional. To add an action, choose **Add error action** and select the appropriate action from the list.

Complete the fields that appear.

- Choose **Next**.

4. In the left navigation pane, under **Test**, choose **MQTT test client**.
5. Choose **Publish to a topic**. Complete the following fields:
 - **Topic name**. Enter a name to identify the message, such as `motors/Fulton-A32/status`.
 - **Message payload**. Enter the following:

```
{
  "messageId": 100,
  "sensorData": {
    "pressure": 39
  }
}
```

 **Note**

Change the `messageId` each time you publish a new message.

6. For **Publish**, keep the topic the same, but change the "pressure" in the payload to a value greater than the threshold value that you specified in the detector model (such as **85**).
7. Choose **Publish**.

The detector instance that you created generates and sends you an Amazon SNS message. Continue to send messages with pressure readings above or below the pressure threshold (70 for this example) to see the detector in operation.

In this example, you must send three messages with pressure readings below the threshold to transition back to the **Normal** state and receive an Amazon SNS message that indicates the overpressure condition has cleared. Once back in the **Normal** state, one message with a pressure reading above the limit causes the detector to enter the **Dangerous** state and send an Amazon SNS message indicating that condition.

Now that you have created a simple input and detector model, try the following.

- See more detector model examples (templates) on the console.
- Follow the steps in [Create an Amazon IoT Events detector for two states using CLI](#) to create an input and detector model using the Amazon CLI
- Learn details of the [Expressions to filter, transform, and process event data](#) used in events.

- Learn about [Supported actions to receive data and trigger actions in Amazon IoT Events](#).
- If something isn't working, see [Troubleshooting Amazon IoT Events](#).

Best practices for Amazon IoT Events

Follow these best practices to get the maximum benefit from Amazon IoT Events.

Topics

- [Enable Amazon CloudWatch logging when developing Amazon IoT Events detector models](#)
- [Publish regularly to save your detector model when working in the Amazon IoT Events console](#)

Enable Amazon CloudWatch logging when developing Amazon IoT Events detector models

Amazon CloudWatch monitors your Amazon resources and the applications that you run on Amazon in real time. With CloudWatch, you gain system-wide visibility into resource use, application performance, and operational health. When you develop or debug an Amazon IoT Events detector model, CloudWatch helps you know what Amazon IoT Events is doing, and any errors that it encounters.

To enable CloudWatch

1. If you haven't already, follow the steps in [Setting up permissions for Amazon IoT Events](#) to create a role with an attached policy that grants permission to create and manage CloudWatch logs for Amazon IoT Events.
2. Go to the [Amazon IoT Events console](#).
3. In the navigation pane, choose **Settings**.
4. On the **Settings** page, choose **Edit**.
5. On the **Edit logging options** page, in the **Logging options** section, do the following:
 - a. For **Level of verbosity**, select an option.
 - b. For **Select role**, select a role with sufficient permissions to perform the logging actions that you chose.
 - c. (Optional) If you chose **Debug** for the **Level of verbosity**, you can add Debug targets by doing the following:
 - i. Under **Debug targets**, choose **Add Model Option**.

- ii. Enter a **Detector Model Name** and (optional) **KeyValue** to specify the detector models and specific detectors (instances) to log.
6. Choose **Update**.

Your logging options are successfully updated.

Publish regularly to save your detector model when working in the Amazon IoT Events console

When you use the Amazon IoT Events console, your work in progress is saved locally in your browser. However, you must choose **Publish** to save your detector model to Amazon IoT Events. After you publish a detector model, your published work will become available in any browser that you use to access your account.

Note

If you don't publish your work, it will not be saved. After you publish a detector model, you can't change its name. However, you can continue modifying its definition.

Tutorials for Amazon IoT Events uses cases

Amazon IoT Events tutorials provide a collection of procedures covering various aspects of Amazon IoT Events, from basic setup to more specific use cases. Each tutorial shows examples of practical scenarios, helping you build real-world skills in creating detector models, configuring inputs, setting up actions, and integrating with other Amazon services to create powerful IoT solutions.

This chapter shows you how to:

- Get help to decide which states to include in your detector model, and determine whether you need one detector instance or several.
- Follow an example that uses the Amazon CLI.
- Create an input to receive telemetry data from a device and a detector model to monitor and report on the state of the device that sends that data.
- Review restrictions and limitations on inputs, detector models, and the Amazon IoT Events service.
- See a more complex example of a detector model, with comments included.

Topics

- [Using Amazon IoT Events to monitor your IoT devices](#)
- [Create an Amazon IoT Events detector for two states using CLI](#)
- [Amazon IoT Events detector model restrictions and limitations](#)
- [A commented example: HVAC temperature control with Amazon IoT Events](#)

Using Amazon IoT Events to monitor your IoT devices

You can use Amazon IoT Events to monitor your devices or processes, and take action based on significant events. To do so, follow these basic steps:

Create inputs

You must have a way for your devices and processes to get telemetry data into Amazon IoT Events. You do this by sending messages as *inputs* to Amazon IoT Events. You can send messages as inputs in several ways:

- Use the [BatchPutMessage](#) operation.

- Define an [iotEvents rule-action](#) for the [Amazon IoT Core rules engine](#). The rule-action forwards message data from your input into Amazon IoT Events.
- In Amazon IoT Analytics, use the [CreateDataset](#) operation to create a data set with `contentDeliveryRules`. These rules specify the Amazon IoT Events input where data set contents are sent automatically.
- Define an [iotEvents action](#) in an Amazon IoT Events detector model's `onInput`, `onExit` or `transitionEvents` event. Information about the detector model instance and the event that initiated the action are fed back into the system as an input with the name that you specify.

Before your devices start sending data in this way, you must define one or more inputs. To do so, give each input a name and specify which fields in the incoming message data the input monitors. Amazon IoT Events receives its input, in the form of JSON payload, from many sources. Each input can be acted on by itself, or combined with other inputs to detect more complex events.

Create a detector model

Define a *detector model* (a model of your equipment or process) using *states*. For each state, you define conditional (Boolean) logic that evaluates the incoming inputs to detect significant events. When an event is detected, it can change the state or initiate custom-built or predefined actions using other Amazon services. You can define additional events that initiate actions when entering or exiting a state and, optionally, when a condition is met.

In this tutorial, you send an Amazon SNS message as the action when the model enters or exits a certain state.

Monitor a device or process

If you're monitoring several devices or processes, you specify a field in each input that identifies the particular device or process the input comes from. (See the `key` field in `CreateDetectorModel`.) When a new device is identified (a new value is seen in the input field identified by the key), a detector is created. (Each detector is an instance of the detector model.) Then the new detector continues responding to inputs coming from that device until its detector model is updated or deleted.

If you're monitoring a single process (even if several devices or subprocesses are sending inputs), you don't specify a unique identifying key field. In this case, a single detector (instance) is created when the first input arrives.

Send messages as inputs to your detector model

There are several ways to send a message from a device or process as an input into an Amazon IoT Events detector that don't require you to perform additional formatting on the message. In this tutorial, you use the Amazon IoT console to write an [Amazon IoT Events action](#) rule for the Amazon IoT Core rules engine that forwards your message data into Amazon IoT Events. To do this, you identify the input by name. Then you continue to use the Amazon IoT console to generate some messages that are forwarded as inputs to Amazon IoT Events.

How do you know which states you need in a detector model?

To determine what states your detector model should have, first decide what actions you can take. For example, if your automobile runs on gasoline, you look at the fuel gauge when you start a trip to see if you need to refuel. Here you have one action: tell the driver to "go get gas". Your detector model needs two states: "car doesn't need fuel", and "car does need fuel". In general, you want to define one state for each possible action, plus one more for when no action is required. This works even if the action itself is more complicated. For example, you might want to look up and include information on where to find the closest gas station, or the cheapest price, but you do this when you send the message to "go get gas".

To decide which state to enter next, you look at inputs. Inputs contain the information that you need to decide what state you should be in. To create an input, you select one or more fields in a message sent by your device or process that help you decide. In this example, you need one input that tells you the current fuel level ("percent full"). Maybe your car is sending you several different messages, each with several different fields. To create this input, you must select the message and the field that reports the current gas gauge level. The length of the trip you are about to take ("distance to destination") can be hardcoded to keep things simple; you can use your average trip length. You'll do some calculations based on the input (how many gallons does that percent full translate to? is the average trip length greater than the miles you can travel, given the gallons you have and your average "miles per gallon"). You perform these calculations and send messages in *events*.

So far you have two states and one input. You need an event in the first state that performs the calculations based on the input and decides whether to go to the second state. That is a transition event. (transitionEvents are in a state's onInput event list. *On* receiving an *input* in this first state, the *event* performs a *transition* to the second state, if the event's condition is met.) When you reach the second state, you send the message as soon as you enter the state. (You use an onEnter event. On entering the second state, this event sends the message. No need to wait

for another input to arrive.) There are other types of events, but that's all you need for a simple example.

The other types of events are `onExit` and `onInput`. As soon as an input is received, and the condition is met, an `onInput` event performs the specified actions. When an operation exits its current state, and the condition is met, the `onExit` event performs the specified actions.

Are you missing anything? Yes, how do you get back to the first "car doesn't need fuel" state? After you fill your gas tank, the input shows a full tank. In your second state you need a transition event back to the first state that happens when the input is received (in the second state's `onInput` : events). It should transition back to the first state if its calculations show you now have enough gas to get you where you want to go.

That's the basics. Some detector models get more complex by adding states that reflect important inputs, not just possible actions. For example, you might have three states in a detector model that keeps track of the temperature: a "normal" state, a "too hot" state, and a "potential problem" state. You transition to the potential problem state when the temperature rises above a certain level, but hasn't become too hot yet. You don't want to send an alarm unless it stays at this temperature for more than 15 minutes. If the temperature returns to normal before then, the detector transitions back to the normal state. If the timer expires, the detector transitions to the too hot state and sends an alarm, just to be cautious. You could do the same thing using variables and a more complex set of event conditions. But often it is easier to use another state to, in effect, store the results of your calculations.

How do you know if you need one instance of a detector or several?

To decide how many instances you need, ask yourself "What are you interested in knowing?" Let's say you want to know what the weather is like today. Is it raining (state)? Do you need to take an umbrella (action)? You can have a sensor that reports the temperature, another that reports the humidity, and others that report the barometric pressure, wind speed and direction, and precipitation. But you must monitor all these sensors together to determine the state of the weather (rain, snow, overcast, sunny) and the appropriate action to take (grab an umbrella or apply sunscreen). In spite of the number of sensors, you want one detector instance to monitor the state of the weather and inform you which action to take.

But if you're the weather forecaster for your region, you might have multiple instances of such sensor arrays, situated at different locations throughout the region. People at each location need to know what the weather is like in that location. In this case, you need multiple instances of your detector. The data reported by each sensor in each location must include a field that you have

designated as the key field. This field enables Amazon IoT Events to create a detector instance for the area, and then to continue to route this information to that detector instance as it continues to arrive. No more ruined hair or sunburned noses!

Essentially, you need one detector instance if you have one situation (one process or one location) to monitor. If you have many situations (locations, processes) to monitor, you need multiple detector instances.

Create an Amazon IoT Events detector for two states using CLI

In this example, we call the Amazon IoT Events APIs using Amazon CLI commands to create a detector that models two states of an engine: a normal state and an over-pressure condition.

When the measured pressure in the engine exceeds a certain threshold, the model transitions to the over-pressure state and sends an Amazon Simple Notification Service (Amazon SNS) message to alert a technician to the condition. When the pressure drops below the threshold for three consecutive pressure readings, the model returns to the normal state and sends another Amazon SNS message as a confirmation that the condition has cleared. We require three consecutive readings below the pressure threshold to eliminate possible stuttering of over-pressure/normal messages in case of a nonlinear recovery phase or a one-off anomalous recovery reading.

The following is an overview of the steps to create the detector.

Create *inputs*.

To monitor your devices and processes, they must have a way to get telemetry data into Amazon IoT Events. This is done by sending messages as *inputs* to Amazon IoT Events. You can do this in several ways:

- Use the [BatchPutMessage](#) operation. This method is easy but requires that your devices or processes are able to access the Amazon IoT Events API through an SDK or the Amazon CLI.
- In Amazon IoT Core, write an [Amazon IoT Events action](#) rule for the Amazon IoT Core rules engine that forwards your message data into Amazon IoT Events. This identifies the input by name. Use this method if your devices or processes can, or already are, sending messages through Amazon IoT Core. This method generally requires less computing power from a device.
- In Amazon IoT Analytics, use the [CreateDataset](#) operation to create a data set with `contentDeliveryRules` that specify the Amazon IoT Events input, where data set contents

are sent automatically. Use this method if you want to control your devices or processes based on data aggregated or analyzed in Amazon IoT Analytics.

Before your devices can send data in this way, you must define one or more inputs. To do so, give each input a name and specify which fields in the incoming message data that the input monitors.

Create a detector model

Create a *detector model* (a model of your equipment or process) using *states*. For each state, define conditional (Boolean) logic that evaluates the incoming inputs to detect significant events. When an event is detected, it can change the state or initiate custom-built or predefined actions using other Amazon services. You can define additional events that initiate actions when entering or exiting a state and, optionally, when a condition is met.

Monitor several devices or processes

If you're monitoring several devices or processes and you want to keep track of each of them separately, specify a field in each input that identifies the particular device or process the input comes from. See the `key` field in `CreateDetectorModel`. When a new device is identified (a new value is seen in the input field identified by the key), a detector instance is created. The new detector instance continues to respond to inputs coming from that particular device until its detector model is updated or deleted. You have as many unique detectors (instances) as there are unique values in input key fields.

Monitor a single device or process

If you're monitoring a single process (even if several devices or subprocesses are sending inputs), you don't specify a unique identifying key field. In this case, a single detector (instance) is created when the first input arrives. For example, you might have temperature sensors in each room of a house, but only one HVAC unit to heat or cool the entire house. So you can only control this as a single process, even if each room occupant wants their vote (input) to prevail.

Send messages from your devices or processes as inputs to your detector model

We described the several ways to send a message from a device or process as an input into an Amazon IoT Events detector in *inputs*. After you created the inputs and build the detector model, you're ready to start sending data.

Note

When you create a detector model, or update an existing one, it takes several minutes before the new or updated detector model begins receiving messages and creating detectors (instances). If the detector model is updated, during this time you might continue to see behavior based on the previous version.

Topics

- [Create an Amazon IoT Events input to capture device data](#)
- [Create a detector model to represent device states in Amazon IoT Events](#)
- [Send messages as inputs to a detector in Amazon IoT Events](#)

Create an Amazon IoT Events input to capture device data

When setting up inputs for Amazon IoT Events, you can leverage the Amazon CLI to define how your devices communicate sensor data. For example, if your devices send JSON-formatted messages with motor identifiers and sensor readings, you can capture this data by creating an input that maps specific attributes from the messages, such as the pressure and the motor ID. The process starts by defining an input in a JSON file, specifying the relevant data points, and using the Amazon CLI to register the input for Amazon IoT Events. This enables Amazon IoT to monitor and respond to critical conditions based on real-time sensor data.

As an example, suppose your devices send messages with the following format.

```
{
  "motorid": "Fulton-A32",
  "sensorData": {
    "pressure": 23,
    "temperature": 47
  }
}
```

You can create an input to capture the `pressure` data and the `motorid` (that identifies the specific device that sent the message) using the following Amazon CLI command.

```
aws iotevents create-input --cli-input-json file://pressureInput.json
```

The file `pressureInput.json` contains the following.

```
{
  "inputName": "PressureInput",
  "inputDescription": "Pressure readings from a motor",
  "inputDefinition": {
    "attributes": [
      { "jsonPath": "sensorData.pressure" },
      { "jsonPath": "motorid" }
    ]
  }
}
```

When you create your own inputs, remember to first collect example messages as JSON files from your devices or processes. You can use them to create an input from the console or the CLI.

Create a detector model to represent device states in Amazon IoT Events

In [Create an Amazon IoT Events input to capture device data](#), you created an input based on a message that reports pressure data from a motor. To continue with the example, here is a detector model that responds to an over-pressure event in a motor.

You create two states: "Normal", and "Dangerous". Each detector (instance) enters the "Normal" state when it's created. The instance is created when an input with a unique value for the key "motorid" arrives.

If the detector instance receives a pressure reading of 70 or greater, it enters the "Dangerous" state and sends an Amazon SNS message as a warning. If the pressure readings return to normal (less than 70) for three consecutive inputs, the detector returns to the "Normal" state and sends another Amazon SNS message as an all clear.

This example detector model assumes you have created two Amazon SNS topics whose Amazon Resource Names (ARNs) are shown in the definition as "targetArn": "arn:aws:sns:us-east-1:123456789012:underPressureAction" and "targetArn": "arn:aws:sns:us-east-1:123456789012:pressureClearedAction".

For more information, see the [Amazon Simple Notification Service Developer Guide](#) and, more specifically, the documentation of the [CreateTopic](#) operation in the *Amazon Simple Notification Service API Reference*.

This example also assumes you have created an Amazon Identity and Access Management (IAM) role with appropriate permissions. The ARN of this role is shown in the detector model definition as "roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole". Follow the steps in [Setting up permissions for Amazon IoT Events](#) to create this role and copy the ARN of the role in the appropriate place in the detector model definition.

You can create the detector model using the following Amazon CLI command.

```
aws iotevents create-detector-model --cli-input-json file://motorDetectorModel.json
```

The file "motorDetectorModel.json" contains the following.

```
{
  "detectorModelName": "motorDetectorModel",
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "Normal",
        "onEnter": {
          "events": [
            {
              "eventName": "init",
              "condition": "true",
              "actions": [
                {
                  "setVariable": {
                    "variableName": "pressureThresholdBreached",
                    "value": "0"
                  }
                }
              ]
            }
          ]
        },
        "onInput": {
          "transitionEvents": [
            {
```

```

        "eventName": "Overpressurized",
        "condition": "$input.PressureInput.sensorData.pressure > 70",
        "actions": [
            {
                "setVariable": {
                    "variableName": "pressureThresholdBreached",
                    "value": "$variable.pressureThresholdBreached + 3"
                }
            }
        ],
        "nextState": "Dangerous"
    }
]
},
{
    "stateName": "Dangerous",
    "onEnter": {
        "events": [
            {
                "eventName": "Pressure Threshold Breached",
                "condition": "$variable.pressureThresholdBreached > 1",
                "actions": [
                    {
                        "sns": {
                            "targetArn": "arn:aws:sns:us-
east-1:123456789012:underPressureAction"
                        }
                    }
                ]
            }
        ]
    },
    "onInput": {
        "events": [
            {
                "eventName": "Overpressurized",
                "condition": "$input.PressureInput.sensorData.pressure > 70",
                "actions": [
                    {
                        "setVariable": {
                            "variableName": "pressureThresholdBreached",
                            "value": "3"
                        }
                    }
                ]
            }
        ]
    }
}

```

```

    }
  ]
},
{
  "eventName": "Pressure Okay",
  "condition": "$input.PressureInput.sensorData.pressure <= 70",
  "actions": [
    {
      "setVariable": {
        "variableName": "pressureThresholdBreached",
        "value": "$variable.pressureThresholdBreached - 1"
      }
    }
  ]
}
],
"transitionEvents": [
  {
    "eventName": "BackToNormal",
    "condition": "$input.PressureInput.sensorData.pressure <= 70 &&
$variable.pressureThresholdBreached <= 1",
    "nextState": "Normal"
  }
]
},
"onExit": {
  "events": [
    {
      "eventName": "Normal Pressure Restored",
      "condition": "true",
      "actions": [
        {
          "sns": {
            "targetArn": "arn:aws:sns:us-
east-1:123456789012:pressureClearedAction"
          }
        }
      ]
    }
  ]
}
],
"initialStateName": "Normal"

```

```
},
"key" : "motorid",
"roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole"
}
```

Send messages as inputs to a detector in Amazon IoT Events

You have now defined an input that identifies the important fields in messages sent from a device (see [Create an Amazon IoT Events input to capture device data](#)). In the previous section, you created a detector `model` that responds to an over-pressure event in a motor (see [Create a detector model to represent device states in Amazon IoT Events](#)).

To complete the example, send messages from a device (in this case a computer with the Amazon CLI installed) as inputs to the detector.

Note

When you create a detector model or update an existing one, it takes several minutes before the new or updated detector model begins to receive messages and create detectors (instances). If you update the detector model, during this time you might continue to see behavior based on the previous version.

Use the following Amazon CLI command to send a message with data that breaches the threshold.

```
aws iotevents-data batch-put-message --cli-input-json file://highPressureMessage.json
--cli-binary-format raw-in-base64-out
```

The file `highPressureMessage.json` contains the following.

```
{
  "messages": [
    {
      "messageId": "00001",
      "inputName": "PressureInput",
      "payload": "{\"motorid\": \"Fulton-A32\", \"sensorData\": {\"pressure\": 80,
        \"temperature\": 39} }"
    }
  ]
}
```

```
]
}
```

You must change the `messageId` in each message sent. If you don't change it, the Amazon IoT Events system deduplicates the messages. Amazon IoT Events ignores a message if it has the same `messageID` as another message that was sent within the last five minutes.

At this point, a detector (instance) is created to monitor events for the motor "Fulton-A32". This detector enters the "Normal" state when it's created. But because we sent a pressure value above the threshold, it immediately transitions to the "Dangerous" state. As it does so, the detector sends a message to the Amazon SNS endpoint whose ARN is `arn:aws:sns:us-east-1:123456789012:underPressureAction`.

Run the following Amazon CLI command to send a message with data that is beneath the pressure threshold.

```
aws iotevents-data batch-put-message --cli-input-json file://normalPressureMessage.json
--cli-binary-format raw-in-base64-out
```

The file `normalPressureMessage.json` contains the following.

```
{
  "messages": [
    {
      "messageId": "00002",
      "inputName": "PressureInput",
      "payload": "{\"motorid\": \"Fulton-A32\", \"sensorData\": {\"pressure\": 60,
        \"temperature\": 29} }"
    }
  ]
}
```

You must change the `messageId` in the file each time you invoke the `BatchPutMessage` command within a five minute period. Send the message two more times. After the message is sent three times, the detector (instance) for the motor "Fulton-A32" sends a message to the Amazon SNS endpoint `arn:aws:sns:us-east-1:123456789012:pressureClearedAction` and reenters the "Normal" state.

Note

You can send multiple messages at one time with `BatchPutMessage`. However, the order in which these messages are processed isn't guaranteed. To guarantee messages (inputs) are processed in order, send them one at a time and wait for a successful response each time the API is called.

The following are example SNS message payloads created by the detector model example described in this section.

on event "Pressure Threshold Breached"

```
IoT> {
  "eventTime":1558129816420,
  "payload":{
    "actionExecutionId":"5d7444df-a655-3587-a609-dbd7a0f55267",
    "detector":{
      "detectorModelName":"motorDetectorModel",
      "keyValue":"Fulton-A32",
      "detectorModelVersion":"1"
    },
    "eventTriggerDetails":{
      "inputName":"PressureInput",
      "messageId":"00001",
      "triggerType":"Message"
    },
    "state":{
      "stateName":"Dangerous",
      "variables":{
        "pressureThresholdBreached":3
      },
      "timers":{}
    }
  },
  "eventName":"Pressure Threshold Breached"
}
```

on event "Normal Pressure Restored"

```
IoT> {
  "eventTime":1558129925568,
```

```
"payload":{
  "actionExecutionId":"7e25fd38-2533-303d-899f-c979792a12cb",
  "detector":{
    "detectorModelName":"motorDetectorModel",
    "keyValue":"Fulton-A32",
    "detectorModelVersion":"1"
  },
  "eventTriggerDetails":{
    "inputName":"PressureInput",
    "messageId":"00004",
    "triggerType":"Message"
  },
  "state":{
    "stateName":"Dangerous",
    "variables":{
      "pressureThresholdBreached":0
    },
    "timers":{}
  }
},
"eventName":"Normal Pressure Restored"
}
```

If you have defined any timers, their current state is also shown in the SNS message payloads.

The message payloads contain information about the state of the detector (instance) at the time the message was sent (that is, at the time the SNS action was run). You can use the https://docs.amazonaws.cn/iotevents/latest/apireference/API_iotevents-data_DescribeDetector.html operation to get similar information about the state of the detector.

Amazon IoT Events detector model restrictions and limitations

The following things are important to consider when creating a detector model.

How to use the actions field

The actions field is a list of objects. You can have more than one object, but only one action is allowed in each object.

Example

```
"actions": [  
  {  
    "setVariable": {  
      "variableName": "pressureThresholdBreached",  
      "value": "$variable.pressureThresholdBreached - 1"  
    }  
  }  
  {  
    "setVariable": {  
      "variableName": "temperatureIsTooHigh",  
      "value": "$variable.temperatureIsTooHigh - 1"  
    }  
  }  
]
```

How to use the condition field

The condition is required for transitionEvents and is optional in other cases.

If the condition field isn't present, it's equivalent to "condition": true.

The result of the evaluation of a condition expression should be a Boolean value. If the result isn't a Boolean value, it's equivalent to false and won't initiate the actions or transition to the nextState specified in the event.

Availability of variable values

By default, if the value of a variable is set in an event, its new value isn't available or used to evaluate conditions in other events in the same group. The new value isn't available or used in an event condition in the same onInput, onEnter or onExit field.

Set the evaluationMethod parameter in the detector model definition to change this behavior. When the evaluationMethod is set to SERIAL, variables are updated and event conditions are evaluated in the order that the events are defined. Otherwise, when the evaluationMethod is set to BATCH or defaults to it, variables within a state are updated and events within a state are performed only after all event conditions are evaluated.

In the "Dangerous" state, in the onInput field, "\$variable.pressureThresholdBreached" is decremented by one in the "Pressure Okay" event when the condition is met (when the current input has pressure less than or equal to 70).

```

{
  "eventName": "Pressure Okay",
  "condition": "$input.PressureInput.sensorData.pressure <= 70",
  "actions": [
    {
      "setVariable": {
        "variableName": "pressureThresholdBreached",
        "value": "$variable.pressureThresholdBreached - 1"
      }
    }
  ]
}

```

The detector should transition back to the "Normal" state when "\$variable.pressureThresholdBreached" reaches 0 (that is, when the detector has received three contiguous pressure readings less than or equal to 70). The "BackToNormal" event in transitionEvents must test that "\$variable.pressureThresholdBreached" is less than or equal to 1 (not 0), and also verify again that the current value given by "\$input.PressureInput.sensorData.pressure" is less than or equal to 70.

```

"transitionEvents": [
  {
    "eventName": "BackToNormal",
    "condition": "$input.PressureInput.sensorData.pressure <= 70 &&
$variable.pressureThresholdBreached <= 1",
    "nextState": "Normal"
  }
]

```

Otherwise, if the condition tests for only the value of the variable, two normal readings followed by an over-pressure reading would fulfill the condition and transition back to the "Normal" state. The condition is looking at the value that "\$variable.pressureThresholdBreached" was given during the previous time an input was processed. The value of the variable is reset to 3 in the "Overpressurized" event, but remember that this new value is not yet available to any condition.

By default, every time a control enters the onInput field, a condition can only see the value of a variable as it was at the start of processing the input, before it's changed by any

actions specified in `onInput`. The same is true for `onEnter` and `onExit`. Any change made to a variable when we enter or exit the state isn't available to other conditions specified in the same `onEnter` or `onExit` fields.

Latency when updating a detector model

If you update, delete, and recreate a detector model (see [UpdateDetectorModel](#)), there is some delay before all spawned detectors (instances) are deleted and the new model is used to recreate the detectors. They are recreated after the new detector model takes effect and new inputs arrive. During this time inputs might continue to be processed by the detectors spawned by the previous version of the detector model. During this period, you might continue to receive alerts defined by the previous detector model.

Spaces in input keys

Spaces are allowed in input keys, but references to the key must be enclosed in backticks, both in the definition of the input attribute and when the value of the key is referenced in an expression. For example, given a message payload like the following:

```
{
  "motor id": "A32",
  "sensorData" {
    "motor pressure": 56,
    "motor temperature": 39
  }
}
```

Use the following to define the input.

```
{
  "inputName": "PressureInput",
  "inputDescription": "Pressure readings from a motor",
  "inputDefinition": {
    "attributes": [
      { "jsonPath": "sensorData.`motor pressure`" },
      { "jsonPath": "`motor id`" }
    ]
  }
}
```

In a conditional expression, you must refer to the value of any such key using backticks also.

```
$input.PressureInput.sensorData.`motor pressure`
```

A commented example: HVAC temperature control with Amazon IoT Events

Some of the following example JSON files have comments inline, which makes them invalid JSON. Complete versions of these examples, without comments, are available at [Example: Using HVAC temperature control with Amazon IoT Events](#).

This example implements a thermostat control model that gives you the ability to do the following.

- Define just one detector model that can be used to monitor and control multiple areas. A detector instance is created for each area.
- Ingest temperature data from multiple sensors in each control area.
- Change the temperature set point for an area.
- Set operational parameters for each area and reset these parameters while the instance is in use.
- Dynamically add or delete sensors from an area.
- Specify a minimum runtime to protect heating and cooling units.
- Reject anomalous sensor readings.
- Define emergency set points that immediately engage heating or cooling if any one sensor reports a temperature above or below a given threshold.
- Report anomalous readings and temperature spikes.

Topics

- [Input definitions for detector models in Amazon IoT Events](#)
- [Create an Amazon IoT Events detector model definition](#)
- [Use BatchUpdateDetector to update an Amazon IoT Events detector model](#)
- [Use BatchPutMessage for inputs in Amazon IoT Events](#)
- [Ingest MQTT messages in Amazon IoT Events](#)
- [Generate Amazon SNS messages in Amazon IoT Events](#)
- [Configure the DescribeDetector API in Amazon IoT Events](#)

- [Use the Amazon IoT Core rules engine for Amazon IoT Events](#)

Input definitions for detector models in Amazon IoT Events

We want to create one detector model that we can use to monitor and control the temperature in several different areas. Each area can have several sensors that report the temperature. We assume each area is served by one heating unit and one cooling unit that can be turned on or off to control the temperature in the area. Each area is controlled by one detector instance.

Because the different areas we monitor and control might have different characteristics that demand different control parameters, we define the 'seedTemperatureInput' to provide those parameters for each area. When we send one of these input messages to Amazon IoT Events, a new detector model instance is created that has the parameters we want to use in that area. Here's the definition of that input.

CLI command:

```
aws iotevents create-input --cli-input-json file://seedInput.json
```

File: seedInput.json

```
{
  "inputName": "seedTemperatureInput",
  "inputDescription": "Temperature seed values.",
  "inputDefinition": {
    "attributes": [
      { "jsonPath": "areaId" },
      { "jsonPath": "desiredTemperature" },
      { "jsonPath": "allowedError" },
      { "jsonPath": "rangeHigh" },
      { "jsonPath": "rangeLow" },
      { "jsonPath": "anomalousHigh" },
      { "jsonPath": "anomalousLow" },
      { "jsonPath": "sensorCount" },
      { "jsonPath": "noDelay" }
    ]
  }
}
```

Response:

```
{
  "inputConfiguration": {
    "status": "ACTIVE",
    "inputArn": "arn:aws:iotevents:us-west-2:123456789012:input/seedTemperatureInput",
    "lastUpdateTime": 1557519620.736,
    "creationTime": 1557519620.736,
    "inputName": "seedTemperatureInput",
    "inputDescription": "Temperature seed values."
  }
}
```

Notes

- A new detector instance is created for each unique 'areaId' received in any message. See the 'key' field in the 'areaDetectorModel' definition.
- The average temperature can vary from the 'desiredTemperature' by the 'allowedError' before the heating or cooling units are activated for the area.
- If any sensor reports a temperature above the 'rangeHigh', the detector reports a spike and immediately starts the cooling unit.
- If any sensor reports a temperature below the 'rangeLow', the detector reports a spike and immediately starts the heating unit.
- If any sensor reports a temperature above the 'anomalousHigh' or below the 'anomalousLow', the detector reports an anomalous sensor reading, but ignores the reported temperature reading.
- The 'sensorCount' tells the detector how many sensors are reporting for the area. The detector calculates the average temperature in the area by giving the appropriate weight factor to each temperature reading it receives. Because of this, the detector won't have to keep track of what each sensor reports, and the number of sensors can be changed dynamically, as needed. However, if an individual sensor goes offline, the detector won't know this or make allowances for it. We recommend that you create another detector model specifically for monitoring the connection status of each sensor. Having two complementary detector models simplifies the design of both.
- The 'noDelay' value can be true or false. After a heating or cooling unit is turned on, it should remain on for a certain minimum time to protect the integrity of the unit and lengthen its operating life. If 'noDelay' is set to false, the detector instance enforces a delay before it turns off the cooling and heating units, to ensure that they are run for the minimum time. The

number of seconds of delay has been hardcoded in the detector model definition because we are unable to use a variable value to set a timer.

The 'temperatureInput' is used to transmit sensor data to a detector instance.

CLI command:

```
aws iotevents create-input --cli-input-json file://temperatureInput.json
```

File: temperatureInput.json

```
{
  "inputName": "temperatureInput",
  "inputDescription": "Temperature sensor unit data.",
  "inputDefinition": {
    "attributes": [
      { "jsonPath": "sensorId" },
      { "jsonPath": "areaId" },
      { "jsonPath": "sensorData.temperature" }
    ]
  }
}
```

Response:

```
{
  "inputConfiguration": {
    "status": "ACTIVE",
    "inputArn": "arn:aws:iotevents:us-west-2:123456789012:input/temperatureInput",
    "lastUpdateTime": 1557519707.399,
    "creationTime": 1557519707.399,
    "inputName": "temperatureInput",
    "inputDescription": "Temperature sensor unit data."
  }
}
```

Notes

- The 'sensorId' isn't used by an example detector instance to control or monitor a sensor directly. It's automatically passed into notifications sent by the detector instance. From there, it

can be used to identify the sensors that are failing (for example, a sensor that regularly sends anomalous readings might be about to fail), or that have gone offline (when it's used as an input to an additional detector model that monitors the device's heartbeat). The 'sensorId' can also help identify warm or cold zones in an area if its readings regularly differ from the average.

- The 'areaId' is used to route the sensor's data to the appropriate detector instance. A detector instance is created for each unique 'areaId' received in any message. See the 'key' field in the 'areaDetectorModel' definition.

Create an Amazon IoT Events detector model definition

The 'areaDetectorModel' example has comments inline.

CLI command:

```
aws iotevents create-detector-model --cli-input-json file://areaDetectorModel.json
```

File: areaDetectorModel.json

```
{
  "detectorModelName": "areaDetectorModel",
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "start",
        // In the 'start' state we set up the operation parameters of the new detector
instance.
        // We get here when the first input message arrives. If that is a
'seedTemperatureInput'
        // message, we save the operation parameters, then transition to the 'idle'
state. If
        // the first message is a 'temperatureInput', we wait here until we get a
        // 'seedTemperatureInput' input to ensure our operation parameters are set.
We can
        // also reenter this state using the 'BatchUpdateDetector' API. This enables
us to
        // reset the operation parameters without needing to delete the detector
instance.
        "onEnter": {
          "events": [
            {
```

```

        "eventName": "prepare",
        "condition": "true",
        "actions": [
            {
                "setVariable": {
                    // initialize 'sensorId' to an invalid value (0) until an actual
sensor reading
                    // arrives
                    "variableName": "sensorId",
                    "value": "0"
                }
            },
            {
                "setVariable": {
                    // initialize 'reportedTemperature' to an invalid value (0.1) until
an actual
                    // sensor reading arrives
                    "variableName": "reportedTemperature",
                    "value": "0.1"
                }
            },
            {
                "setVariable": {
                    // When using 'BatchUpdateDetector' to re-enter this state, this
variable should
                    // be set to true.
                    "variableName": "resetMe",
                    "value": "false"
                }
            }
        ]
    },
    "onInput": {
        "transitionEvents": [
            {
                "eventName": "initialize",
                "condition": "$input.seedTemperatureInput.sensorCount > 0",
                // When a 'seedTemperatureInput' message with a valid 'sensorCount' is
received,
                // we use it to set the operational parameters for the area to be
monitored.
                "actions": [

```

```
{
  "setVariable": {
    "variableName": "rangeHigh",
    "value": "$input.seedTemperatureInput.rangeHigh"
  }
},
{
  "setVariable": {
    "variableName": "rangeLow",
    "value": "$input.seedTemperatureInput.rangeLow"
  }
},
{
  "setVariable": {
    "variableName": "desiredTemperature",
    "value": "$input.seedTemperatureInput.desiredTemperature"
  }
},
{
  "setVariable": {
    // Assume we're at the desired temperature when we start.
    "variableName": "averageTemperature",
    "value": "$input.seedTemperatureInput.desiredTemperature"
  }
},
{
  "setVariable": {
    "variableName": "allowedError",
    "value": "$input.seedTemperatureInput.allowedError"
  }
},
{
  "setVariable": {
    "variableName": "anomalousHigh",
    "value": "$input.seedTemperatureInput.anomalousHigh"
  }
},
{
  "setVariable": {
    "variableName": "anomalousLow",
    "value": "$input.seedTemperatureInput.anomalousLow"
  }
},
{
```

```

        "setVariable": {
            "variableName": "sensorCount",
            "value": "$input.seedTemperatureInput.sensorCount"
        }
    },
    {
        "setVariable": {
            "variableName": "noDelay",
            "value": "$input.seedTemperatureInput.noDelay == true"
        }
    }
],
"nextState": "idle"
},
{
    "eventName": "reset",
    "condition": "($variable.resetMe == true) &&
($input.temperatureInput.sensorData.temperature < $variable.anomalousHigh &&
$input.temperatureInput.sensorData.temperature > $variable.anomalousLow)",
    // This event is triggered if we have reentered the 'start' state using
the
    // 'BatchUpdateDetector' API with 'resetMe' set to true. When we
reenter using
    // 'BatchUpdateDetector' we do not automatically continue to the 'idle'
state, but
    // wait in 'start' until the next input message arrives. This event
enables us to
    // transition to 'idle' on the next valid 'temperatureInput' message
that arrives.
    "actions": [
        {
            "setVariable": {
                "variableName": "averageTemperature",
                "value": "((( $variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount)"
            }
        }
    ],
    "nextState": "idle"
}
]
},
"onExit": {
    "events": [

```

```

    {
      "eventName": "resetHeatCool",
      "condition": "true",
      // Make sure the heating and cooling units are off before entering
      'idle'.
      "actions": [
        {
          "sns": {
            "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOff"
          }
        },
        {
          "sns": {
            "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOff"
          }
        },
        {
          "iotTopicPublish": {
            "mqttTopic": "hvac/Heating/Off"
          }
        },
        {
          "iotTopicPublish": {
            "mqttTopic": "hvac/Cooling/Off"
          }
        }
      ]
    }
  ],
},

{
  "stateName": "idle",
  "onInput": {
    "events": [
      {
        "eventName": "whatWasInput",
        "condition": "true",
        // By storing the 'sensorId' and the 'temperature' in variables, we make
        them
        // available in any messages we send out to report anomalies, spikes,
        or just

```

```
// if needed for debugging.
"actions": [
  {
    "setVariable": {
      "variableName": "sensorId",
      "value": "$input.temperatureInput.sensorId"
    }
  },
  {
    "setVariable": {
      "variableName": "reportedTemperature",
      "value": "$input.temperatureInput.sensorData.temperature"
    }
  }
]
},
{
  "eventName": "changeDesired",
  "condition": "$input.seedTemperatureInput.desiredTemperature !=
$variable.desiredTemperature",
  // This event enables us to change the desired temperature at any time by
  // sending a
  // 'seedTemperatureInput' message. But note that other operational
  // parameters are not
  // read or changed.
  "actions": [
    {
      "setVariable": {
        "variableName": "desiredTemperature",
        "value": "$input.seedTemperatureInput.desiredTemperature"
      }
    }
  ]
},
{
  "eventName": "calculateAverage",
  "condition": "$input.temperatureInput.sensorData.temperature <
$variable.anomalousHigh && $input.temperatureInput.sensorData.temperature >
$variable.anomalousLow",
  // If a valid temperature reading arrives, we use it to update the
  // average temperature.
  // For simplicity, we assume our sensors will be sending updates at
  // about the same rate,
```

```

        // so we can calculate an approximate average by giving equal weight to
each reading we receive.
        "actions": [
            {
                "setVariable": {
                    "variableName": "averageTemperature",
                    "value": "((( $variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount)"
                }
            }
        ]
    },
    "transitionEvents": [
        {
            "eventName": "anomalousInputArrived",
            "condition": "$input.temperatureInput.sensorData.temperature >=
$variable.anomalousHigh || $input.temperatureInput.sensorData.temperature <=
$variable.anomalousLow",
            // When an anomalous reading arrives, send an MQTT message, but stay in
the current state.
            "actions": [
                {
                    "iotTopicPublish": {
                        "mqttTopic": "temperatureSensor/anomaly"
                    }
                }
            ],
            "nextState": "idle"
        },
        {
            "eventName": "highTemperatureSpike",
            "condition": "$input.temperatureInput.sensorData.temperature >
$variable.rangeHigh",
            // When even a single temperature reading arrives that is above the
'rangeHigh', take
            // emergency action to begin cooling, and report a high temperature
spike.
            "actions": [
                {
                    "iotTopicPublish": {
                        "mqttTopic": "temperatureSensor/spike"
                    }
                }
            ]
        }
    ]
}

```



```

    },
    {
      "sns": {
        "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOn"
      }
    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Cooling/On"
      }
    },
    {
      "setVariable": {
        // This is necessary because we want to set a timer to delay the
shutoff
        //   of a cooling/heating unit, but we only want to set the timer
when we
        //   enter that new state initially.
        "variableName": "enteringNewState",
        "value": "true"
      }
    }
  ],
  "nextState": "cooling"
},
{
  "eventName": "lowTemperatureSpike",
  "condition": "$input.temperatureInput.sensorData.temperature <
$variable.rangeLow",
  // When even a single temperature reading arrives that is below the
'rangeLow', take
  //   emergency action to begin heating, and report a low-temperature
spike.
  "actions": [
    {
      "iotTopicPublish": {
        "mqttTopic": "temperatureSensor/spike"
      }
    },
    {
      "sns": {
        "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOn"
      }
    }
  ]
}

```

```

    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Heating/On"
      }
    },
    {
      "setVariable": {
        "variableName": "enteringNewState",
        "value": "true"
      }
    }
  ],
  "nextState": "heating"
},

{
  "eventName": "highTemperatureThreshold",
  "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) >
($variable.desiredTemperature + $variable.allowedError))",
  // When the average temperature is above the desired temperature plus the
allowed error factor,
  // it is time to start cooling. Note that we calculate the average
temperature here again
  // because the value stored in the 'averageTemperature' variable is not
yet available for use
  // in our condition.
  "actions": [
    {
      "sns": {
        "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOn"
      }
    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Cooling/On"
      }
    },
    {
      "setVariable": {
        "variableName": "enteringNewState",
        "value": "true"
      }
    }
  ]
}

```

```

    }
  ],
  "nextState": "cooling"
},

{
  "eventName": "lowTemperatureThreshold",
  "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) <
($variable.desiredTemperature - $variable.allowedError))",
  // When the average temperature is below the desired temperature minus
the allowed error factor,
  // it is time to start heating. Note that we calculate the average
temperature here again
  // because the value stored in the 'averageTemperature' variable is not
yet available for use
  // in our condition.
  "actions": [
    {
      "sns": {
        "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOn"
      }
    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Heating/On"
      }
    },
    {
      "setVariable": {
        "variableName": "enteringNewState",
        "value": "true"
      }
    }
  ],
  "nextState": "heating"
}
]
}
},

{
  "stateName": "cooling",

```

```

    "onEnter": {
      "events": [
        {
          "eventName": "delay",
          "condition": "!$variable.noDelay && $variable.enteringNewState",
          // If the operational parameters specify that there should be a minimum
time that the
          // heating and cooling units should be run before being shut off again,
we set
          // a timer to ensure the proper operation here.
          "actions": [
            {
              "setTimer": {
                "timerName": "coolingTimer",
                "seconds": 180
              }
            },
            {
              "setVariable": {
                // We use this 'goodToGo' variable to store the status of the timer
expiration
                // for use in conditions that also use input variable values. If
lost.
                // 'timeout()' is used in such mixed conditionals, its value is

                "variableName": "goodToGo",
                "value": "false"
              }
            }
          ]
        },
        {
          "eventName": "dontDelay",
          "condition": "$variable.noDelay == true",
          // If the heating/cooling unit shutoff delay is not used, no need to
wait.
          "actions": [
            {
              "setVariable": {
                "variableName": "goodToGo",
                "value": "true"
              }
            }
          ]
        }
      ],
    },
  ],
},

```

```

    {
      "eventName": "beenHere",
      "condition": "true",
      "actions": [
        {
          "setVariable": {
            "variableName": "enteringNewState",
            "value": "false"
          }
        }
      ]
    }
  ],
},

"onInput": {
  "events": [
    // These are events that occur when an input is received (if the condition
is
    // satisfied), but don't cause a transition to another state.
    {
      "eventName": "whatWasInput",
      "condition": "true",
      "actions": [
        {
          "setVariable": {
            "variableName": "sensorId",
            "value": "$input.temperatureInput.sensorId"
          }
        },
        {
          "setVariable": {
            "variableName": "reportedTemperature",
            "value": "$input.temperatureInput.sensorData.temperature"
          }
        }
      ]
    },
    {
      "eventName": "changeDesired",
      "condition": "$input.seedTemperatureInput.desiredTemperature !=
$variable.desiredTemperature",
      "actions": [
        {

```

```

        "setVariable": {
            "variableName": "desiredTemperature",
            "value": "$input.seedTemperatureInput.desiredTemperature"
        }
    }
]
},
{
    "eventName": "calculateAverage",
    "condition": "$input.temperatureInput.sensorData.temperature <
$variable.anomalousHigh && $input.temperatureInput.sensorData.temperature >
$variable.anomalousLow",
    "actions": [
        {
            "setVariable": {
                "variableName": "averageTemperature",
                "value": "(((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount)"
            }
        }
    ]
},
{
    "eventName": "areWeThereYet",
    "condition": "(timeout(\"coolingTimer\"))",
    "actions": [
        {
            "setVariable": {
                "variableName": "goodToGo",
                "value": "true"
            }
        }
    ]
}
],
"transitionEvents": [
    // Note that some tests of temperature values (for example, the test for an
    // anomalous value)
    // must be placed here in the 'transitionEvents' because they work
    // together with the tests
    // in the other conditions to ensure that we implement the proper
    // "if..elseif..else" logic.
    // But each transition event must have a destination state ('nextState'),
    // and even if that

```

```

        // is actually the current state, the "onEnter" events for this state
        will be executed again.
        // This is the reason for the 'enteringNewState' variable and related.
        {
            "eventName": "anomalousInputArrived",
            "condition": "$input.temperatureInput.sensorData.temperature >=
$variable.anomalousHigh || $input.temperatureInput.sensorData.temperature <=
$variable.anomalousLow",
            "actions": [
                {
                    "iotTopicPublish": {
                        "mqttTopic": "temperatureSensor/anomaly"
                    }
                }
            ],
            "nextState": "cooling"
        },
        {
            "eventName": "highTemperatureSpike",
            "condition": "$input.temperatureInput.sensorData.temperature >
$variable.rangeHigh",
            "actions": [
                {
                    "iotTopicPublish": {
                        "mqttTopic": "temperatureSensor/spike"
                    }
                }
            ],
            "nextState": "cooling"
        },
        {
            "eventName": "lowTemperatureSpike",
            "condition": "$input.temperatureInput.sensorData.temperature <
$variable.rangeLow",
            "actions": [
                {
                    "iotTopicPublish": {
                        "mqttTopic": "temperatureSensor/spike"
                    }
                }
            ],
            {
                "sns": {

```

```

        "targetArn": "arn:aws:sns:us-west-2:123456789012:cool0ff"
    }
},
{
    "sns": {
        "targetArn": "arn:aws:sns:us-west-2:123456789012:heat0n"
    }
},
{
    "iotTopicPublish": {
        "mqttTopic": "hvac/Cooling/Off"
    }
},
{
    "iotTopicPublish": {
        "mqttTopic": "hvac/Heating/On"
    }
},
{
    "setVariable": {
        "variableName": "enteringNewState",
        "value": "true"
    }
}
],
"nextState": "heating"
},

{
    "eventName": "desiredTemperature",
    "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) <=
($variable.desiredTemperature - $variable.allowedError)) && $variable.goodToGo ==
true",
    "actions": [
        {
            "sns": {
                "targetArn": "arn:aws:sns:us-west-2:123456789012:cool0ff"
            }
        },
        {
            "iotTopicPublish": {
                "mqttTopic": "hvac/Cooling/Off"
            }
        }
    ]
}

```



```

        }
      ],
      "nextState": "idle"
    }
  ]
}
},

{
  "stateName": "heating",
  "onEnter": {
    "events": [
      {
        "eventName": "delay",
        "condition": "!$variable.noDelay && $variable.enteringNewState",
        "actions": [
          {
            "setTimer": {
              "timerName": "heatingTimer",
              "seconds": 120
            }
          },
          {
            "setVariable": {
              "variableName": "goodToGo",
              "value": "false"
            }
          }
        ]
      },
      {
        "eventName": "dontDelay",
        "condition": "$variable.noDelay == true",
        "actions": [
          {
            "setVariable": {
              "variableName": "goodToGo",
              "value": "true"
            }
          }
        ]
      }
    ],
  },
}
{

```



```

        }
    ]
},
{
    "eventName": "calculateAverage",
    "condition": "$input.temperatureInput.sensorData.temperature <
$variable.anomalousHigh && $input.temperatureInput.sensorData.temperature >
$variable.anomalousLow",
    "actions": [
        {
            "setVariable": {
                "variableName": "averageTemperature",
                "value": "(((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount)"
            }
        }
    ]
},
{
    "eventName": "areWeThereYet",
    "condition": "(timeout(\"heatingTimer\"))",
    "actions": [
        {
            "setVariable": {
                "variableName": "goodToGo",
                "value": "true"
            }
        }
    ]
}
],
"transitionEvents": [
    {
        "eventName": "anomalousInputArrived",
        "condition": "$input.temperatureInput.sensorData.temperature >=
$variable.anomalousHigh || $input.temperatureInput.sensorData.temperature <=
$variable.anomalousLow",
        "actions": [
            {
                "iotTopicPublish": {
                    "mqttTopic": "temperatureSensor/anomaly"
                }
            }
        ]
    }
],

```

```
        "nextState": "heating"
    },
    {
        "eventName": "highTemperatureSpike",
        "condition": "$input.temperatureInput.sensorData.temperature >
$variable.rangeHigh",
        "actions": [
            {
                "iotTopicPublish": {
                    "mqttTopic": "temperatureSensor/spike"
                }
            },
            {
                "sns": {
                    "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOff"
                }
            },
            {
                "sns": {
                    "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOn"
                }
            },
            {
                "iotTopicPublish": {
                    "mqttTopic": "hvac/Heating/Off"
                }
            },
            {
                "iotTopicPublish": {
                    "mqttTopic": "hvac/Cooling/On"
                }
            },
            {
                "setVariable": {
                    "variableName": "enteringNewState",
                    "value": "true"
                }
            }
        ],
        "nextState": "cooling"
    },
    {
```

```

        "eventName": "lowTemperatureSpike",
        "condition": "$input.temperatureInput.sensorData.temperature <
$variable.rangeLow",
        "actions": [
            {
                "iotTopicPublish": {
                    "mqttTopic": "temperatureSensor/spike"
                }
            }
        ],
        "nextState": "heating"
    },

    {
        "eventName": "desiredTemperature",
        "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) >=
($variable.desiredTemperature + $variable.allowedError)) && $variable.goodToGo ==
true",
        "actions": [
            {
                "sns": {
                    "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOff"
                }
            },
            {
                "iotTopicPublish": {
                    "mqttTopic": "hvac/Heating/Off"
                }
            }
        ],
        "nextState": "idle"
    }
]
}

],

"initialStateName": "start"
},
"key": "areaId",
"roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole"

```

```
}
```

Response:

```
{
  "detectorModelConfiguration": {
    "status": "ACTIVATING",
    "lastUpdateTime": 1557523491.168,
    "roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole",
    "creationTime": 1557523491.168,
    "detectorModelArn": "arn:aws:iotevents:us-west-2:123456789012:detectorModel/
areaDetectorModel",
    "key": "areaId",
    "detectorModelName": "areaDetectorModel",
    "detectorModelVersion": "1"
  }
}
```

Use BatchUpdateDetector to update an Amazon IoT Events detector model

You can use the `BatchUpdateDetector` operation to put a detector instance into a known state, including timer and variable values. In the following example, the `BatchUpdateDetector` operation resets operational parameters for an area that is under temperature monitoring and control. This operation enables you to do this without having to delete, and recreate, or update the detector model.

CLI command:

```
aws iotevents-data batch-update-detector --cli-input-json file://areaDM.BUD.json
```

File: areaDM.BUD.json

```
{
  "detectors": [
    {
      "messageId": "0001",
      "detectorModelName": "areaDetectorModel",
      "keyValue": "Area51",
      "state": {
```

```
"stateName": "start",
"variables": [
  {
    "name": "desiredTemperature",
    "value": "22"
  },
  {
    "name": "averageTemperature",
    "value": "22"
  },
  {
    "name": "allowedError",
    "value": "1.0"
  },
  {
    "name": "rangeHigh",
    "value": "30.0"
  },
  {
    "name": "rangeLow",
    "value": "15.0"
  },
  {
    "name": "anomalousHigh",
    "value": "60.0"
  },
  {
    "name": "anomalousLow",
    "value": "0.0"
  },
  {
    "name": "sensorCount",
    "value": "12"
  },
  {
    "name": "noDelay",
    "value": "true"
  },
  {
    "name": "goodToGo",
    "value": "true"
  },
  {
    "name": "sensorId",
```

```
        "value": "0"
      },
      {
        "name": "reportedTemperature",
        "value": "0.1"
      },
      {
        "name": "resetMe",
        // When 'resetMe' is true, our detector model knows that we have reentered
the 'start' state
        //  to reset operational parameters, and will allow the next valid
temperature sensor
        //  reading to cause the transition to the 'idle' state.
        "value": "true"
      }
    ],
    "timers": [
    ]
  }
}
]
```

Response:

```
{
  "batchUpdateDetectorErrorEntries": []
}
```

Use BatchPutMessage for inputs in Amazon IoT Events

Example 1

Use the BatchPutMessage operation to send a "seedTemperatureInput" message that sets the operational parameters for a given area under temperature control and monitoring. Any message received by Amazon IoT Events that has a new "areaId" causes a new detector instance to be created. But the new detector instance won't change state to "idle" and begin monitoring the temperature and controlling heating or cooling units until a "seedTemperatureInput" message is received for the new area.

CLI command:


```
aws iotevents-data batch-put-message --cli-input-json file://seedExample.json --cli-binary-format raw-in-base64-out
```

File: seedExample.json

```
{
  "messages": [
    {
      "messageId": "00001",
      "inputName": "seedTemperatureInput",
      "payload": "{\"areaId\": \"Area51\", \"desiredTemperature\": 20.0, \"allowedError\": 0.7, \"rangeHigh\": 30.0, \"rangeLow\": 15.0, \"anomalousHigh\": 60.0, \"anomalousLow\": 0.0, \"sensorCount\": 10, \"noDelay\": false}"
    }
  ]
}
```

Response:

```
{
  "BatchPutMessageErrorEntries": []
}
```

Example

2

Use the BatchPutMessage operation to send a "temperatureInput" message to report temperature sensor data for a sensor in a given control and monitoring area.

CLI command:

```
aws iotevents-data batch-put-message --cli-input-json file://temperatureExample.json --cli-binary-format raw-in-base64-out
```

File: temperatureExample.json

```
{
  "messages": [
    {
```

```

    "messageId": "00005",
    "inputName": "temperatureInput",
    "payload": "{\"sensorId\": \"05\", \"areaId\": \"Area51\", \"sensorData\":
{\"temperature\": 23.12} }"
  }
]
}

```

Response:

```

{
  "BatchPutMessageErrorEntries": []
}

```

Example 3

Use the BatchPutMessage operation to send a "seedTemperatureInput" message to change the value of the desired temperature for a given area.

CLI command:

```

aws iotevents-data batch-put-message --cli-input-json file://seedSetDesiredTemp.json --
cli-binary-format raw-in-base64-out

```

File: seedSetDesiredTemp.json

```

{
  "messages": [
    {
      "messageId": "00001",
      "inputName": "seedTemperatureInput",
      "payload": "{\"areaId\": \"Area51\", \"desiredTemperature\": 23.0}"
    }
  ]
}

```

Response:

```

{
  "BatchPutMessageErrorEntries": []
}

```

Ingest MQTT messages in Amazon IoT Events

If your sensor computing resources can't use the "BatchPutMessage" API, but can send their data to the Amazon IoT Core message broker using a lightweight MQTT client, you can create an Amazon IoT Core topic rule to redirect message data to an Amazon IoT Events input. The following is a definition of an Amazon IoT Events topic rule that takes the "areaId" and "sensorId" input fields from the MQTT topic, and the "sensorData.temperature" field from the message payload "temp" field, and ingests this data into our Amazon IoT Events "temperatureInput".

CLI command:

```
aws iot create-topic-rule --cli-input-json file://temperatureTopicRule.json
```

File: seedSetDesiredTemp.json

```
{
  "ruleName": "temperatureTopicRule",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as areaId, topic(4) as sensorId, temp as
sensorData.temperature FROM 'update/temperature/#'",
    "description": "Ingest temperature sensor messages into IoT Events",
    "actions": [
      {
        "iotEvents": {
          "inputName": "temperatureInput",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/anotherRole"
        }
      }
    ],
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23"
  }
}
```

Response: [none]

If the sensor sends a message on the topic "update/temperature/Area51/03" with the following payload.

```
{ "temp": 24.5 }
```

This results in data being ingested into Amazon IoT Events as if the following "BatchPutMessage" API call had been made.

```
aws iotevents-data batch-put-message --cli-input-json file://spooferExample.json --cli-binary-format raw-in-base64-out
```

File: spooferExample.json

```
{
  "messages": [
    {
      "messageId": "54321",
      "inputName": "temperatureInput",
      "payload": "{\"sensorId\": \"03\", \"areaId\": \"Area51\", \"sensorData\": {\"temperature\": 24.5} }"
    }
  ]
}
```

Generate Amazon SNS messages in Amazon IoT Events

The following are examples of SNS messages generated by the "Area51" detector instance.

Amazon IoT Events can integrate with Amazon SNS to generate and publish notifications based on detected events. This section demonstrates how an Amazon IoT Events detector instance, specifically the "Area51" detector, generates Amazon SNS messages. These examples showcase the structure and content of Amazon SNS notifications triggered by various states and events within the Amazon IoT Events detector, illustrating the power of combining Amazon IoT Events with Amazon SNS for real-time alerting and communication.

```
Heating system off command> {
  "eventTime":1557520274729,
  "payload":{
    "actionExecutionId":"f3159081-bac3-38a4-96f7-74af0940d0a4",
    "detector":{

      "detectorModelName":"areaDetectorModel","keyValue":"Area51","detectorModelVersion":"1"},
    "inputName":"seedTemperatureInput","messageId":"00001","triggerType":"Message"},"state":{
      "stateName":"start","variables":
```

```
{"sensorCount":10,"rangeHigh":30.0,"resetMe":false,"enteringNewState":true,"averageTemperature":
{}}, "eventName": "resetHeatCool"}
```

```
Cooling system off command> {"eventTime":1557520274729,"payload":
{"actionExecutionId":"98f6a1b5-8f40-3cdb-9256-93afd4d66192","detector":
{"detectorModelName":"areaDetectorModel","keyValue":"Area51","detectorModelVersion":"1"},"event
{"inputName":"seedTemperatureInput","messageId":"00001","triggerType":"Message"},"state":
{"stateName":"start","variables":
{"sensorCount":10,"rangeHigh":30.0,"resetMe":false,"enteringNewState":true,"averageTemperature":
{}}, "eventName": "resetHeatCool"}
```

Configure the DescribeDetector API in Amazon IoT Events

The DescribeDetector API in Amazon IoT Events lets you to retrieve detailed information about a specific detector instance. This operation provides insights into the current state, variable values, and active timers of a detector. By using this API, you can monitor the real-time status of your Amazon IoT Events detectors, facilitating debugging, analysis, and management of your IoT event processing workflows.

CLI command:

```
aws iotevents-data describe-detector --detector-model-name areaDetectorModel --key-
value Area51
```

Response:

```
{
  "detector": {
    "lastUpdateTime": 1557521572.216,
    "creationTime": 1557520274.405,
    "state": {
      "variables": [
        {
          "name": "resetMe",
          "value": "false"
        },
        {
          "name": "rangeLow",
          "value": "15.0"
        }
      ]
    }
  }
}
```

```
    },
    {
      "name": "noDelay",
      "value": "false"
    },
    {
      "name": "desiredTemperature",
      "value": "20.0"
    },
    {
      "name": "anomalousLow",
      "value": "0.0"
    },
    {
      "name": "sensorId",
      "value": "\"01\""
    },
    {
      "name": "sensorCount",
      "value": "10"
    },
    {
      "name": "rangeHigh",
      "value": "30.0"
    },
    {
      "name": "enteringNewState",
      "value": "false"
    },
    {
      "name": "averageTemperature",
      "value": "19.572"
    },
    {
      "name": "allowedError",
      "value": "0.7"
    },
    {
      "name": "anomalousHigh",
      "value": "60.0"
    },
    {
      "name": "reportedTemperature",
      "value": "15.72"
    }
  ],
  {
    "name": "reportedTemperature",
    "value": "15.72"
  }
}
```

```
        },
        {
            "name": "goodToGo",
            "value": "false"
        }
    ],
    "stateName": "idle",
    "timers": [
        {
            "timestamp": 1557520454.0,
            "name": "idleTimer"
        }
    ]
},
"keyValue": "Area51",
"detectorModelName": "areaDetectorModel",
"detectorModelVersion": "1"
}
}
```

Use the Amazon IoT Core rules engine for Amazon IoT Events

The following rules republish Amazon IoT Core MQTT messages as shadow update request messages. We assume that Amazon IoT Core things are defined for a heating unit and a cooling unit for each area that is controlled by the detector model. In this example, we have defined things named "Area51HeatingUnit" and "Area51CoolingUnit".

CLI command:

```
aws iot create-topic-rule --cli-input-json file://ADMShadowCoolOffRule.json
```

File: ADMShadowCoolOffRule.json

```
{
  "ruleName": "ADMShadowCoolOff",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Cooling/Off'",
    "description": "areaDetectorModel mqtt topic publish to cooling unit shadow request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
```

```

    "actions": [
      {
        "republish": {
          "topic": "$$aws/things/${payload.detector.keyValue}CoolingUnit/shadow/
update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMShadowRole"
        }
      }
    ]
  }
}

```

Response: [empty]

CLI command:

```
aws iot create-topic-rule --cli-input-json file://ADMShadowCoolOnRule.json
```

File: ADMShadowCoolOnRule.json

```

{
  "ruleName": "ADMShadowCoolOn",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Cooling/On'",
    "description": "areaDetectorModel mqtt topic publish to cooling unit shadow
request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
    "actions": [
      {
        "republish": {
          "topic": "$$aws/things/${payload.detector.keyValue}CoolingUnit/shadow/
update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMShadowRole"
        }
      }
    ]
  }
}

```

Response: [empty]

CLI command:

```
aws iot create-topic-rule --cli-input-json file://ADMSHadowHeatOffRule.json
```

File: ADMSHadowHeatOffRule.json

```
{
  "ruleName": "ADMSHadowHeatOff",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Heating/Off'",
    "description": "areaDetectorModel mqtt topic publish to heating unit shadow
request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
    "actions": [
      {
        "republsh": {
          "topic": "$$aws/things/${payload.detector.keyValue}HeatingUnit/shadow/
update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMSHadowRole"
        }
      }
    ]
  }
}
```

Response: [empty]

CLI command:

```
aws iot create-topic-rule --cli-input-json file://ADMSHadowHeatOnRule.json
```

File: ADMSHadowHeatOnRule.json

```
{
  "ruleName": "ADMSHadowHeatOn",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Heating/On'",
    "description": "areaDetectorModel mqtt topic publish to heating unit shadow
request",
```

```
"ruleDisabled": false,
"awsIotSqlVersion": "2016-03-23",
"actions": [
  {
    "republish": {
      "topic": "$$aws/things/${payload.detector.keyValue}HeatingUnit/shadow/
update",
      "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMShadowRole"
    }
  }
]
```

Response: [empty]

Supported actions to receive data and trigger actions in Amazon IoT Events

Amazon IoT Events can trigger actions when it detects a specified event or transition event. You can define built-in actions to use a timer or set a variable, or send data to other Amazon resources. Learn how to configure and customize these actions to create automated responses to your various IoT events.

Note

When you define an action in a detector model, you can use expressions for parameters that are string data type. For more information, see [Expressions](#).

Amazon IoT Events supports the following actions that let you use a timer or set a variable:

- [setTimer](#) to create a timer.
- [resetTimer](#) to reset the timer.
- [clearTimer](#) to delete the timer.
- [setVariable](#) to create a variable.

Amazon IoT Events supports the following actions that let you work with Amazon services:

- [iotTopicPublish](#) to publish a message on an MQTT topic.
- [iotEvents](#) to send data to Amazon IoT Events as an input value.
- [iotSiteWise](#) to send data to an asset property in Amazon IoT SiteWise.
- [dynamoDB](#) to send data to an Amazon DynamoDB table.
- [dynamoDBv2](#) to send data to an Amazon DynamoDB table.
- [firehose](#) to send data to an Amazon Data Firehose stream.
- [lambda](#) to invoke an Amazon Lambda function.
- [sns](#) to send data as a push notification.
- [sqs](#) to send data to an Amazon SQS queue.

Use the Amazon IoT Events built-in timer and variable actions

Amazon IoT Events supports the following actions that let you use a timer or set a variable:

- [setTimer](#) to create a timer.
- [resetTimer](#) to reset the timer.
- [clearTimer](#) to delete the timer.
- [setVariable](#) to create a variable.

Set timer action

Set timer action

The `setTimer` action lets you create a timer with duration in seconds.

More information (2)

When you create a timer, you must specify the following parameters.

timerName

The name of the timer.

durationExpression

(Optional) The duration of the timer, in seconds.

The evaluated result of a duration expression is rounded down to the nearest whole number. For example, if you set the timer to 60.99 seconds, the evaluated result of the duration expression is 60 seconds.

For more information, see [SetTimerAction](#) in the *Amazon IoT Events API Reference*.

Reset timer action

Reset timer action

The `resetTimer` action lets you set the timer to the previously evaluated result of the duration expression.

More information (1)

When you reset a timer, you must specify the following parameter.

timerName

The name of the timer.

Amazon IoT Events doesn't reevaluate the duration expression when you reset the timer.

For more information, see [ResetTimerAction](#) in the *Amazon IoT Events API Reference*.

Clear timer action

Clear timer action

The `clearTimer` action lets you delete an existing timer.

More information (1)

When you delete a timer, you must specify the following parameter.

timerName

The name of the timer.

For more information, see [ClearTimerAction](#) in the *Amazon IoT Events API Reference*.

Set variable action

Set variable action

The `setVariable` action lets you create a variable with a specified value.

More information (2)

When you create a variable, you must specify the following parameters.

variableName

The name of the variable.

value

The new value of the variable.

For more information, see [SetVariableAction](#) in the *Amazon IoT Events API Reference*.

Amazon IoT Events working with other Amazon services

Amazon IoT Events supports the following actions that let you work with Amazon services:

- [iotTopicPublish](#) to publish a message on an MQTT topic.
- [iotEvents](#) to send data to Amazon IoT Events as an input value.
- [iotSiteWise](#) to send data to an asset property in Amazon IoT SiteWise.
- [dynamoDB](#) to send data to an Amazon DynamoDB table.
- [dynamoDBv2](#) to send data to an Amazon DynamoDB table.
- [firehose](#) to send data to an Amazon Data Firehose stream.
- [lambda](#) to invoke an Amazon Lambda function.
- [sns](#) to send data as a push notification.
- [sqs](#) to send data to an Amazon SQS queue.

Important

- You must choose the same Amazon Region for both Amazon IoT Events and the Amazon services to work with. For the list of supported Regions, see [Amazon IoT Events endpoints and quotas](#) in the *Amazon Web Services General Reference*.
- You must use the same Amazon Region when you create other Amazon resources for the Amazon IoT Events actions. If you switch Amazon Regions, you might have issues accessing the Amazon resources.

By default, Amazon IoT Events generates a standard payload in JSON for any action. This action payload contains all attribute-value pairs that have the information about the detector model instance and the event that triggered the action. To configure the action payload, you can use a

content expression. For more information, see [Expressions to filter, transform, and process event data](#) and the [Payload](#) data type in the *Amazon IoT Events API Reference*.

Amazon IoT Core

IoT topic publish action

The Amazon IoT Core action lets you publish an MQTT message through the Amazon IoT message broker. For the list of supported Regions, see [Amazon IoT Core endpoints and quotas](#) in the *Amazon Web Services General Reference*.

The Amazon IoT message broker connects Amazon IoT clients by sending messages from publishing clients to subscribing clients. For more information, see [Device communication protocols](#) in the *Amazon IoT Developer Guide*.

More information (2)

When you publish an MQTT message, you must specify the following parameters.

mqttTopic

The MQTT topic that receives the message.

You can define an MQTT topic name dynamically at runtime using variables or input values created in the detector model.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `iot:Publish` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [lotTopicPublishAction](#) in the *Amazon IoT Events API Reference*.

Amazon IoT Events

IoT Events action

The Amazon IoT Events action lets you send data to Amazon IoT Events as input. For the list of supported Regions, see [Amazon IoT Events endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon IoT Events lets you to monitor your equipment or device fleets for failures or changes in operation, and to trigger actions when such events occur. For more information, see [What is Amazon IoT Events?](#) in the *Amazon IoT Events Developer Guide*.

More information (2)

When you send data to Amazon IoT Events, you must specify the following parameters.

inputName

The name of the Amazon IoT Events input that receives the data.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `iotevents:BatchPutMessage` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [lotEventsAction](#) in the *Amazon IoT Events API Reference*.

Amazon IoT SiteWise

IoT SiteWise action

The Amazon IoT SiteWise action lets you send data to an asset property in Amazon IoT SiteWise. For the list of supported Regions, see [Amazon IoT SiteWise endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon IoT SiteWise is a managed service that lets you collect, organize, and analyze data from industrial equipment at scale. For more information, see [What is Amazon IoT SiteWise?](#) in the *Amazon IoT SiteWise User Guide*.

More information (11)

When you send data to an asset property in Amazon IoT SiteWise, you must specify the following parameters.

Important

To receive the data, you must use an existing asset property in Amazon IoT SiteWise.

- If you use the Amazon IoT Events console, you must specify `propertyAlias` to identify the target asset property.
- If you use the Amazon CLI, you must specify either `propertyAlias` or both `assetId` and `propertyId` to identify the target asset property.

For more information, see [Mapping industrial data streams to asset properties](#) in the *Amazon IoT SiteWise User Guide*.

propertyAlias

(Optional) The alias of the asset property. You can also specify an expression.

assetId

(Optional) The ID of the asset that has the specified property. You can also specify an expression.

propertyId

(Optional) The ID of the asset property. You can also specify an expression.

entryId

(Optional) A unique identifier for this entry. You can use the entry ID to track which data entry causes an error in case of failure. The default is a new unique identifier. You can also specify an expression.

propertyValue

A structure that contains details about the property value.

quality

(Optional) The quality of the asset property value. The value must be GOOD, BAD, or UNCERTAIN. You can also specify an expression.

timestamp

(Optional) A structure that contains timestamp information. If you don't specify this value, the default is the event time.

timeInSeconds

The timestamp, in seconds, in the Unix epoch format. The valid range is between 1-31556889864403199. You can also specify an expression.

offsetInNanos

(Optional) The nanosecond offset converted from `timeInSeconds`. The valid range is between 0-999999999. You can also specify an expression.

value

A structure that contains an asset property value.

 Important

You must specify one of the following value types, depending on the `dataType` of the specified asset property. For more information, see [AssetProperty](#) in the *Amazon IoT SiteWise API Reference*.

booleanValue

(Optional) The asset property value is a Boolean value that must be TRUE or FALSE. You can also specify an expression. If you use an expression, the evaluated result should be a Boolean value.

doubleValue

(Optional) The asset property value is a double. You can also specify an expression. If you use an expression, the evaluated result should be a double.

integerValue

(Optional) The asset property value is an integer. You can also specify an expression. If you use an expression, the evaluated result should be an integer.

stringValue

(Optional) The asset property value is a string. You can also specify an expression. If you use an expression, the evaluated result should be a string.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `iotsitewise:BatchPutAssetPropertyValue` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [lotSiteWiseAction](#) in the *Amazon IoT Events API Reference*.

Amazon DynamoDB

DynamoDB action

The Amazon DynamoDB action lets you send data to a DynamoDB table. One column of the DynamoDB table receives all attribute-value pairs in the action payload that you specify. For the list of supported Regions, see [Amazon DynamoDB endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon DynamoDB is a fully managed NoSQL database service that provides fast and predictable performance with seamless scalability. For more information, see [What is DynamoDB?](#) in the *Amazon DynamoDB Developer Guide*.

More information (10)

When you send data to one column of a DynamoDB table, you must specify the following parameters.

tableName

The name of the DynamoDB table that receives the data. The `tableName` value must match the table name of the DynamoDB table. You can also specify an expression.

hashKeyField

The name of the hash key (also called partition key). The `hashKeyField` value must match the partition key of the DynamoDB table. You can also specify an expression.

hashKeyType

(Optional) The data type of the hash key. The value of the hash key type must be `STRING` or `NUMBER`. The default is `STRING`. You can also specify an expression.

hashKeyValue

The value of the hash key. The `hashKeyValue` uses substitution templates. These templates provide data at runtime. You can also specify an expression.

rangeKeyField

(Optional) The name of the range key (also called the sort key). The `rangeKeyField` value must match the sort key of the DynamoDB table. You can also specify an expression.

rangeKeyType

(Optional) The data type of the range key. The value of the hash key type must be `STRING` or `NUMBER`. The default is `STRING`. You can also specify an expression.

rangeKeyValue

(Optional) The value of the range key. The `rangeKeyValue` uses substitution templates. These templates provide data at runtime. You can also specify an expression.

operation

(Optional) The type of operation to perform. You can also specify an expression. The operation value must be one of the following values:

- INSERT - Insert data as a new item into the DynamoDB table. This is the default value.
- UPDATE - Update an existing item of the DynamoDB table with new data.
- DELETE - Delete an existing item from the DynamoDB table.

payloadField

(Optional) The name of the DynamoDB column that receives the action payload. The default name is `payload`. You can also specify an expression.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

If the specified payload type is a string, `DynamoDBAction` sends non-JSON data to the DynamoDB table as binary data. The DynamoDB console displays the data as Base64-encoded text. The `payloadField` value is `payload-field_raw`. You can also specify an expression.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `dynamodb:PutItem` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [DynamoDBAction](#) in the *Amazon IoT Events API Reference*.

Amazon DynamoDB(v2)

DynamoDBv2 action

The Amazon DynamoDB(v2) action lets you write data to a DynamoDB table. A separate column of the DynamoDB table receives one attribute-value pair in the action payload that you specify. For the list of supported Regions, see [Amazon DynamoDB endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon DynamoDB is a fully managed NoSQL database service that provides fast and predictable performance with seamless scalability. For more information, see [What is DynamoDB?](#) in the *Amazon DynamoDB Developer Guide*.

More information (2)

When you send data to multiple columns of a DynamoDB table, you must specify the following parameters.

tableName

The name of the DynamoDB table that receives the data. You can also specify an expression.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Important

The payload type must be JSON. You can also specify an expression.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `dynamodb:PutItem` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [DynamoDBv2Action](#) in the *Amazon IoT Events API Reference*.

Amazon Data Firehose

Firehose action

The Amazon Data Firehose action lets you send data to an Firehose delivery stream. For the list of supported Regions, see [Amazon Data Firehose endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon Data Firehose is a fully managed service for delivering real-time streaming data to destinations such as Amazon Simple Storage Service (Amazon Simple Storage Service), Amazon Redshift, Amazon OpenSearch Service (OpenSearch Service), and Splunk. For more information, see [What is Amazon Data Firehose?](#) in the *Amazon Data Firehose Developer Guide*.

More information (3)

When you send data to an Firehose delivery stream, you must specify the following parameters.

deliveryStreamName

The name of the Firehose delivery stream that receives the data.

separator

(Optional) You can use a character separator to separate continuous data sent to the Firehose delivery stream. The separator value must be '\n' (newline), '\t' (tab), '\r\n' (Windows new line), or ',' (comma).

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `firehose:PutRecord` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [FirehoseAction](#) in the *Amazon IoT Events API Reference*.

Amazon Lambda

Lambda action

The Amazon Lambda action lets you call a Lambda function. For the list of supported Regions, see [Amazon Lambda endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon Lambda is a compute service that lets you run code without provisioning or managing servers. For more information, see [What is Amazon Lambda?](#) in the *Amazon Lambda Developer Guide*.

More information (2)

When you call a Lambda function, you must specify the following parameters.

functionArn

The ARN of the Lambda function to call.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `lambda:InvokeFunction` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [LambdaAction](#) in the *Amazon IoT Events API Reference*.

Amazon Simple Notification Service

SNS action

The Amazon SNS topic publish action lets you publish an Amazon SNS message. For the list of supported Regions, see [Amazon Simple Notification Service endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon Simple Notification Service (Amazon Simple Notification Service) is a web service that coordinates and manages the delivery or sending of messages to subscribing endpoints or clients. For more information, see [What is Amazon SNS?](#) in the *Amazon Simple Notification Service Developer Guide*.

Note

The Amazon SNS topic publish action doesn't support Amazon SNS FIFO (first in, first out) topics. Because the rules engine is a fully distributed service, the messages may not display in a specified order when the Amazon SNS action is initiated.

More information (2)

When you publish an Amazon SNS message, you must specify the following parameters.

targetArn

The ARN of the Amazon SNS target that receives the message.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `sns:Publish` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [SNSTopicPublishAction](#) in the *Amazon IoT Events API Reference*.

Amazon Simple Queue Service

SQS action

The Amazon SQS action lets you send data to an Amazon SQS queue. For the list of supported Regions, see [Amazon Simple Queue Service endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Amazon Simple Queue Service (Amazon SQS) offers a secure, durable, and available hosted queue that lets you integrate and decouple distributed software systems and components. For more information, see [What is Amazon Simple Queue Service](#) in the *Amazon Simple Queue Service Developer Guide*.

Note

The Amazon SQS action doesn't support >Amazon SQS FIFO (first in, first out) topics. Because the rules engine is a fully distributed service, the messages may not display in a specified order when the Amazon SQS action is initiated.

More information (3)

When you send data to an Amazon SQS queue, you must specify the following parameters.

queueUrl

The URL of the Amazon SQS queue that receives the data.

useBase64

(Optional) Amazon IoT Events encodes the data into Base64 text, if you specify TRUE. The default is FALSE.

payload

(Optional) The default payload contains all attribute-value pairs that have the information about the detector model instance and the event triggered the action. You can also customize the payload. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

Note

Make sure that the policy attached to your Amazon IoT Events service role grants the `sqs:SendMessage` permission. For more information, see [Identity and access management for Amazon IoT Events](#).

For more information, see [SNSTopicPublishAction](#) in the *Amazon IoT Events API Reference*.

You can also use Amazon SNS and the Amazon IoT Core rules engine to trigger an Amazon Lambda function. This makes it possible to take actions using other services, such as Amazon Connect, or even a company enterprise resource planning (ERP) application.

Note

To collect and process large streams of data records in real time, you can use other Amazon services, such as [Amazon Kinesis](#). From there, you can complete an initial analysis and then send the results to Amazon IoT Events as an input to a detector.

Expressions to filter, transform, and process event data

Expressions are used to evaluate incoming data, perform calculations, and determine the conditions under which specific actions or state transitions should occur. Amazon IoT Events provides several ways to specify values when you create and update detector models. You can use expressions to specify literal values, or Amazon IoT Events can evaluate the expressions before you specify particular values.

Topics

- [Syntax to filter device data and define actions in Amazon IoT Events](#)
- [Expression examples and usage for Amazon IoT Events](#)

Syntax to filter device data and define actions in Amazon IoT Events

Expressions offer syntax for filtering device data and defining actions. You can use literals, operators, functions, references, and substitution templates in the Amazon IoT Events expressions. By combining these components, you can create powerful and flexible expressions to process IoT data, perform calculations, manipulate strings, and make logical decisions within your detector models.

Literals

- Integer
- Decimal
- String
- Boolean

Operators

Unary

- Not (Boolean): !
- Not (bitwise): ~
- Minus (arithmetic): -

String

- Concatenation: +

Both operands must be strings. String literals must be enclosed in single quotes (').

For example: 'my' + 'string' -> 'mystring'

Arithmetic

- Addition: +

Both operands must be numeric.

- Subtraction: -
- Division: /

The result of the division is a rounded integer value unless at least one of the operands (divisor or dividend) is a decimal value.

- Multiplication: *

Bitwise (Integer)

- OR: |

For example: 13 | 5 -> 13

- AND: &

For example: 13 & 5 -> 5

- XOR: ^

For example: 13 ^ 5 -> 8

- NOT: ~

For example: ~13 -> -14

Boolean

- Less Than: <
- Less Than Or Equal To: <=
- Equal To: ==
- Not Equal To: !=
- Greater Than Or Equal To: >=

- Greater Than: >
- AND: &&
- OR: ||

Note

When a subexpression of || contains undefined data, that subexpression is treated as false.

Parentheses

You can use parentheses to group terms within an expression.

Functions to use in Amazon IoT Events expressions

Amazon IoT Events provides a set of built-in functions to enhance the capabilities of your detector model expressions. These functions enable timer management, type conversion, null checking, trigger type identification, input verification, string manipulation, and bitwise operations. By leveraging these functions, you can create a responsive Amazon IoT Events processing logic, improving the overall effectiveness of your IoT applications.

Built-in Functions

timeout("timer-name")

Evaluates to true if the specified timer has elapsed. Replace "timer-name" with the name of a timer that you defined, in quotation marks. In an event action, you can define a timer and then start the timer, reset it, or clear one that you previously defined. See the field `detectorModelDefinition.states.onInput|onEnter|onExit.events.actions.setTimer.timerName`.

A timer set in one state can be referenced in a different state. You must visit the state in which you created the timer before you enter the state in which the timer is referenced.

For example, a detector model has two states, `TemperatureChecked` and `RecordUpdated`. You created a timer in the `TemperatureChecked` state. You must visit the `TemperatureChecked` state first before you can use the timer in the `RecordUpdated` state.

To ensure accuracy, the minimum time that a timer should be set is 60 seconds.

Note

`timeout()` returns `true` only the first time it's checked following the actual timer expiration and returns `false` thereafter.

convert(*type*, *expression*)

Evaluates to the value of the expression converted to the specified type. The *type* value must be `String`, `Boolean`, or `Decimal`. Use one of these keywords or an expression that evaluates to a string containing the keyword. Only the following conversions succeed and return a valid value:

- Boolean -> string

Returns the string "true" or "false".

- Decimal -> string
- String -> Boolean
- String -> decimal

The string specified must be a valid representation of a decimal number, or `convert()` fails.

If `convert()` doesn't return a valid value, the expression that it's a part of is also invalid. This result is equivalent to `false` and won't trigger the actions or transition to the `nextState` specified as part of the event in which the expression occurs.

isNull(*expression*)

Evaluates to `true` if the expression returns `null`. For example, if the input `MyInput` receives the message `{ "a": null }`, then the following evaluates to `true`, but `isUndefined($input.MyInput.a)` evaluates to `false`.

```
isNull($input.MyInput.a)
```

isUndefined(*expression*)

Evaluates to `true` if the expression is undefined. For example, if the input `MyInput` receives the message `{ "a": null }`, then the following evaluates to `false`, but `isNull($input.MyInput.a)` evaluates to `true`.

```
isUndefined($input.MyInput.a)
```

triggerType("type")

The *type* value can be "Message" or "Timer". Evaluates to `true` if the event condition in which it appears is being evaluated because a timer has expired like in the following example.

```
triggerType("Timer")
```

Or an input message was received.

```
triggerType("Message")
```

currentInput("input")

Evaluates to `true` if the event condition in which it appears is being evaluated because the specified input message was received. For example, if the input Command receives the message { "value": "Abort" }, then the following evaluates to `true`.

```
currentInput("Command")
```

Use this function to verify that the condition is being evaluated because a particular input has been received and a timer hasn't expired, as in the following expression.

```
currentInput("Command") && $input.Command.value == "Abort"
```

String Matching Functions

startsWith(*expression1*, *expression2*)

Evaluates to `true` if the first string expression starts with the second string expression. For example, if input MyInput receives the message { "status": "offline"}, then the following evaluates to `true`.

```
startsWith($input.MyInput.status, "off")
```

Both expressions must evaluate to a string value. If either expression does not evaluate to a string value, then the result of the function is undefined. No conversions are performed.

endsWith(*expression1*, *expression2*)

Evaluates to `true` if the first string expression ends with the second string expression. For example, if input `MyInput` receives the message { `"status": "offline"` }, then the following evaluates to `true`.

```
endsWith($input.MyInput.status, "line")
```

Both expressions must evaluate to a string value. If either expression does not evaluate to a string value, then the result of the function is undefined. No conversions are performed.

contains(*expression1*, *expression2*)

Evaluates to `true` if the first string expression contains the second string expression. For example, if input `MyInput` receives the message { `"status": "offline"` }, then the following evaluates to `true`.

```
contains($input.MyInput.value, "fli")
```

Both expressions must evaluate to a string value. If either expression does not evaluate to a string value, then the result of the function is undefined. No conversions are performed.

Bitwise Integer Manipulation Functions**bitor**(*expression1*, *expression2*)

Evaluates the bitwise OR of the integer expressions (the binary OR operation is performed on the corresponding bits of the integers). For example, if input `MyInput` receives the message { `"value1": 13`, `"value2": 5` }, then the following evaluates to 13.

```
bitor($input.MyInput.value1, $input.MyInput.value2)
```

Both expressions must evaluate to an integer value. If either expression does not evaluate to an integer value, then the result of the function is undefined. No conversions are performed.

bitand(*expression1*, *expression2*)

Evaluates the bitwise AND of the integer expressions (the binary AND operation is performed on the corresponding bits of the integers). For example, if input `MyInput` receives the message { `"value1": 13`, `"value2": 5` }, then the following evaluates to 5.

```
bitand($input.MyInput.value1, $input.MyInput.value2)
```

Both expressions must evaluate to an integer value. If either expression does not evaluate to an integer value, then the result of the function is undefined. No conversions are performed.

bitxor(*expression1*, *expression2*)

Evaluates the bitwise XOR of the integer expressions (the binary XOR operation is performed on the corresponding bits of the integers). For example, if input MyInput receives the message { "value1": 13, "value2": 5 }, then the following evaluates to 8.

```
bitxor($input.MyInput.value1, $input.MyInput.value2)
```

Both expressions must evaluate to an integer value. If either expression does not evaluate to an integer value, then the result of the function is undefined. No conversions are performed.

bitnot(*expression*)

Evaluates the bitwise NOT of the integer expression (the binary NOT operation is performed on the bits of the integer). For example, if input MyInput receives the message { "value": 13 }, then the following evaluates to -14.

```
bitnot($input.MyInput.value)
```

Both expressions must evaluate to an integer value. If either expression does not evaluate to an integer value, then the result of the function is undefined. No conversions are performed.

Amazon IoT Events reference for inputs and variables in expressions

Inputs

`$input.input-name.path-to-data`

`input-name` is an input that you create using the [CreateInput](#) action.

For example, if you have an input named TemperatureInput for which you defined `inputDefinition.attributes.jsonPath` entries, the values might appear in the following available fields.

```
{
```

```
"temperature": 78.5,  
"date": "2018-10-03T16:09:09Z"  
}
```

To reference the value of the `temperature` field, use the following command.

```
$input.TemperatureInput.temperature
```

For fields whose values are arrays, you can reference members of the array using [*n*]. For example, given the following values:

```
{  
  "temperatures": [  
    78.4,  
    77.9,  
    78.8  
  ],  
  "date": "2018-10-03T16:09:09Z"  
}
```

The value `78.8` can be referenced with the following command.

```
$input.TemperatureInput.temperatures[2]
```

Variables

```
$variable.variable-name
```

The *variable-name* is a variable that you defined using the [CreateDetectorModel](#) action.

For example, if you have a variable named `TechnicianID` that you defined using `detectorDefinition.states.onInputEvents.actions.setVariable.variableName`, you can reference the (string) value most recently given to the variable with the following command.

```
$variable.TechnicianID
```

You can set the values of variables only using the `setVariable` action. You can't assign values for variables in an expression. A variable can't be unset. For example, you can't assign it the value `null`.

Note

In references that use identifiers that don't follow the (regular expression) pattern `[a-zA-Z][a-zA-Z0-9_]*`, you must enclose those identifiers in backticks (```). For example, a reference to an input named `MyInput` with a field named `_value` must specify this field as `$input.MyInput.`_value``.

When you use references in expressions, check the following:

- When you use a reference as an operand with one or more operators, make sure that all data types that you reference are compatible.

For example, in the following expression, integer 2 is an operand of both the `==` and `&&` operators. To ensure that the operands are compatible, `$variable.testVariable + 1` and `$variable.testVariable` must reference an integer or decimal.

In addition, integer 1 is an operand of the `+` operator. Therefore, `$variable.testVariable` must reference an integer or decimal.

```
'$variable.testVariable + 1 == 2 && $variable.testVariable'
```

- When you use a reference as an argument passed to a function, make sure that the function supports the data types that you reference.

For example, the following `timeout("time-name")` function requires a string with double quotes as the argument. If you use a reference for the `timer-name` value, you must reference a string with double quotes.

```
timeout("timer-name")
```

Note

For the `convert(type, expression)` function, if you use a reference for the `type` value, the evaluated result of your reference must be `String`, `Decimal`, or `Boolean`.

Amazon IoT Events expressions support integer, decimal, string, and Boolean data types. The following table provides a list of incompatible pairs of types.

Incompatible pairs of types

Integer, string

Integer, Boolean

Decimal, string

Decimal, Boolean

String, Boolean

Substitution templates for Amazon IoT Events expressions

```
'${expression}'
```

The `${}` identifies the string as an interpolated string. The `expression` can be any Amazon IoT Events expression. This includes operators, functions, and references.

For example, you used the [SetVariableAction](#) action to define a variable. The `variableName` is `SensorID`, and the `value` is `10`. You can create the following substitution templates.

Substitution template	Result string
<code>'\${'Sensor ' + \$variable.SensorID}'</code>	"Sensor 10"
<code>'Sensor ' + '\${\$variable.SensorID + 1}'</code>	"Sensor 11"
<code>'Sensor 10: \${\$variable.SensorID == 10}'</code>	"Sensor 10: true"

Substitution template	Result string
<code>'{"sensor\":"\${variable.SensorID + 1}\"}'</code>	<code>"{"sensor\":"11\"}"</code>
<code>'{"sensor\":"\${variable.SensorID + 1}}'</code>	<code>"{"sensor\":"11}"</code>

Expression examples and usage for Amazon IoT Events

You can specify values in a detector model in the following ways:

- Enter supported expressions in the Amazon IoT Events console.
- Pass the expressions to the Amazon IoT Events APIs as parameters.

Expressions support literals, operators, functions, references, and substitution templates.

Important

Your expressions must reference a integer, decimal, string, or Boolean value.

Writing Amazon IoT Events expressions

See the following examples to help you write your Amazon IoT Events expressions:

Literal

For literal values, the expressions must contain single quotes. A Boolean value must be either true or false.

```
'123'      # Integer
'123.12'   # Decimal
'hello'    # String
'true'     # Boolean
```

Reference

For references, you must specify either variables or input values.

- The following input references a decimal number, 10.01.

```
$input.GreenhouseInput.temperature
```

- The following variable references a string, Greenhouse Temperature Table.

```
$variable.TableName
```

Substitution template

For a substitution template, you must use `${}`, and the template must be in single quotes. A substitution template can also contain a combination of literals, operators, functions, references, and substitution templates.

- The evaluated result of the following expression is a string, 50.018 in Fahrenheit.

```
'${$input.GreenhouseInput.temperature * 9 / 5 + 32} in Fahrenheit'
```

- The evaluated result of the following expression is a string, `{"sensor_id": "Sensor_1", "temperature": "50.018"}`.

```
'{"sensor_id": "${$input.GreenhouseInput.sensors[0].sensor1}", "temperature": "${$input.GreenhouseInput.temperature*9/5+32}"'
```

String concatenation

For a string concatenation, you must use `+`. A string concatenation can also contain a combination of literals, operators, functions, references, and substitution templates.

- The evaluated result of the following expression is a string, Greenhouse Temperature Table 2000-01-01.

```
'Greenhouse Temperature Table ' + $input.GreenhouseInput.date
```

Amazon IoT Events detector model examples

This page provides a list of example use cases that demonstrate how to configure various Amazon IoT Events features. The examples range from basic detections like temperature thresholds to more advanced anomaly detection and machine learning scenarios. Each example includes procedures and code snippets to help you set up Amazon IoT Events detections, actions, and integrations. These examples showcase the flexibility of the Amazon IoT Events service and how it can be customized for diverse IoT applications and use cases. Refer to this page when exploring Amazon IoT Events capabilities or if you need guidance implementing a specific detection or automation workflow.

Topics

- [Example: Using HVAC temperature control with Amazon IoT Events](#)
- [Example: A crane detecting conditions using Amazon IoT Events](#)
- [Send commands in response to detected conditions in Amazon IoT Events](#)
- [An Amazon IoT Events detector model for crane monitoring](#)
- [Amazon IoT Events inputs for crane monitoring](#)
- [Send alarm and operational messages with Amazon IoT Events](#)
- [Example: Amazon IoT Events event detection with sensors and applications](#)
- [Example: Device HeartBeat to monitor device connections with Amazon IoT Events](#)
- [Example: An ISA alarm in Amazon IoT Events](#)
- [Example: Build a simple alarm with Amazon IoT Events](#)

Example: Using HVAC temperature control with Amazon IoT Events

Background story

This example implements a temperature control model (a thermostat) with these features:

- One detector model you define that can monitor and control multiple areas. (A detector instance will be created for each area.)
- Each detector instance receives temperature data from multiple sensors placed in each control area.

- You can change the desired temperature (the set point) for each area at any time.
- You can define the operational parameters for each area and change these parameters at any time.
- You can add sensors to or delete sensors from an area at any time.
- You can enable a minimum run for time heating and cooling units to protect them from damage.
- The detectors will reject, and report, anomalous sensor readings.
- You can define emergency temperature set points. If any one sensor reports a temperature above or below the set points you have defined, heating or cooling units will be engaged immediately, and the detector will report that temperature spike.

This example demonstrates the following functional capabilities:

- Create event detector models.
- Create inputs.
- Ingest inputs into a detector model.
- Evaluate trigger conditions.
- Refer to state variables in conditions and set the values of variables depending on conditions.
- Refer to timers in conditions and set timers depending on conditions.
- Take actions that send Amazon SNS and MQTT messages.

Input definitions for an HVAC system in Amazon IoT Events

A `seedTemperatureInput` is used to create a detector instance for an area and define its operational parameters.

Configuring inputs for HVAC systems in Amazon IoT Events is important for effective climate control. This example shows how to set up inputs that capture parameters such as, temperature, humidity, occupancy, and energy consumption data. Learn to define input attributes, configure data sources, and set up preprocessing rules to help your detector models receive accurate and timely information for optimal management and efficiency.

CLI command used:

```
aws iotevents create-input --cli-input-json file://seedInput.json
```

File: seedInput.json

```
{
  "inputName": "seedTemperatureInput",
  "inputDescription": "Temperature seed values.",
  "inputDefinition": {
    "attributes": [
      { "jsonPath": "areaId" },
      { "jsonPath": "desiredTemperature" },
      { "jsonPath": "allowedError" },
      { "jsonPath": "rangeHigh" },
      { "jsonPath": "rangeLow" },
      { "jsonPath": "anomalousHigh" },
      { "jsonPath": "anomalousLow" },
      { "jsonPath": "sensorCount" },
      { "jsonPath": "noDelay" }
    ]
  }
}
```

Response:

```
{
  "inputConfiguration": {
    "status": "ACTIVE",
    "inputArn": "arn:aws:iotevents:us-west-2:123456789012:input/seedTemperatureInput",
    "lastUpdateTime": 1557519620.736,
    "creationTime": 1557519620.736,
    "inputName": "seedTemperatureInput",
    "inputDescription": "Temperature seed values."
  }
}
```

A temperatureInput should be sent by each sensor in each area, as necessary.

CLI command used:

```
aws iotevents create-input --cli-input-json file://temperatureInput.json
```

File: temperatureInput.json

```
{
  "inputName": "temperatureInput",
  "inputDescription": "Temperature sensor unit data.",
  "inputDefinition": {
    "attributes": [
      { "jsonPath": "sensorId" },
      { "jsonPath": "areaId" },
      { "jsonPath": "sensorData.temperature" }
    ]
  }
}
```

Response:

```
{
  "inputConfiguration": {
    "status": "ACTIVE",
    "inputArn": "arn:aws:iotevents:us-west-2:123456789012:input/temperatureInput",
    "lastUpdateTime": 1557519707.399,
    "creationTime": 1557519707.399,
    "inputName": "temperatureInput",
    "inputDescription": "Temperature sensor unit data."
  }
}
```

Detector model definition for an HVAC system using Amazon IoT Events

The `areaDetectorModel` defines how each detector instance works. Each state machine instance will ingest temperature sensor readings, then change state and send control messages depending on these readings.

CLI command used:

```
aws iotevents create-detector-model --cli-input-json file://areaDetectorModel.json
```

File: `areaDetectorModel.json`

```
{
  "detectorModelName": "areaDetectorModel",
  "detectorModelDefinition": {
```

```
"states": [
  {
    "stateName": "start",
    "onEnter": {
      "events": [
        {
          "eventName": "prepare",
          "condition": "true",
          "actions": [
            {
              "setVariable": {
                "variableName": "sensorId",
                "value": "0"
              }
            },
            {
              "setVariable": {
                "variableName": "reportedTemperature",
                "value": "0.1"
              }
            },
            {
              "setVariable": {
                "variableName": "resetMe",
                "value": "false"
              }
            }
          ]
        }
      ]
    },
    "onInput": {
      "transitionEvents": [
        {
          "eventName": "initialize",
          "condition": "$input.seedTemperatureInput.sensorCount > 0",
          "actions": [
            {
              "setVariable": {
                "variableName": "rangeHigh",
                "value": "$input.seedTemperatureInput.rangeHigh"
              }
            }
          ]
        }
      ]
    }
  }
]
```

```
    "setVariable": {
      "variableName": "rangeLow",
      "value": "$input.seedTemperatureInput.rangeLow"
    }
  },
  {
    "setVariable": {
      "variableName": "desiredTemperature",
      "value": "$input.seedTemperatureInput.desiredTemperature"
    }
  },
  {
    "setVariable": {
      "variableName": "averageTemperature",
      "value": "$input.seedTemperatureInput.desiredTemperature"
    }
  },
  {
    "setVariable": {
      "variableName": "allowedError",
      "value": "$input.seedTemperatureInput.allowedError"
    }
  },
  {
    "setVariable": {
      "variableName": "anomalousHigh",
      "value": "$input.seedTemperatureInput.anomalousHigh"
    }
  },
  {
    "setVariable": {
      "variableName": "anomalousLow",
      "value": "$input.seedTemperatureInput.anomalousLow"
    }
  },
  {
    "setVariable": {
      "variableName": "sensorCount",
      "value": "$input.seedTemperatureInput.sensorCount"
    }
  },
  {
    "setVariable": {
      "variableName": "noDelay",
```



```

    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Cooling/Off"
      }
    }
  ]
}
],
},
},

{
  "stateName": "idle",
  "onInput": {
    "events": [
      {
        "eventName": "whatWasInput",
        "condition": "true",
        "actions": [
          {
            "setVariable": {
              "variableName": "sensorId",
              "value": "$input.temperatureInput.sensorId"
            }
          },
          {
            "setVariable": {
              "variableName": "reportedTemperature",
              "value": "$input.temperatureInput.sensorData.temperature"
            }
          }
        ]
      },
      {
        "eventName": "changeDesired",
        "condition": "$input.seedTemperatureInput.desiredTemperature !=
$variable.desiredTemperature",
        "actions": [
          {
            "setVariable": {
              "variableName": "desiredTemperature",
              "value": "$input.seedTemperatureInput.desiredTemperature"
            }
          }
        ]
      }
    ]
  }
}

```



```

    }
  },
  {
    "sns": {
      "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOn"
    }
  },
  {
    "iotTopicPublish": {
      "mqttTopic": "hvac/Cooling/On"
    }
  },
  {
    "setVariable": {
      "variableName": "enteringNewState",
      "value": "true"
    }
  }
],
"nextState": "cooling"
},
{
  "eventName": "lowTemperatureSpike",
  "condition": "$input.temperatureInput.sensorData.temperature <
$variable.rangeLow",
  "actions": [
    {
      "iotTopicPublish": {
        "mqttTopic": "temperatureSensor/spike"
      }
    },
    {
      "sns": {
        "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOn"
      }
    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Heating/On"
      }
    }
  ],
  {
    "setVariable": {

```

```

        "variableName": "enteringNewState",
        "value": "true"
    }
}
],
"nextState": "heating"
},

{
    "eventName": "highTemperatureThreshold",
    "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) >
($variable.desiredTemperature + $variable.allowedError))",
    "actions": [
        {
            "sns": {
                "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOn"
            }
        },
        {
            "iotTopicPublish": {
                "mqttTopic": "hvac/Cooling/On"
            }
        },
        {
            "setVariable": {
                "variableName": "enteringNewState",
                "value": "true"
            }
        }
    ],
    "nextState": "cooling"
},

{
    "eventName": "lowTemperatureThreshold",
    "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) <
($variable.desiredTemperature - $variable.allowedError))",
    "actions": [
        {
            "sns": {
                "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOn"
            }
        }
    ]
}

```

```
    },
    {
      "iotTopicPublish": {
        "mqttTopic": "hvac/Heating/On"
      }
    },
    {
      "setVariable": {
        "variableName": "enteringNewState",
        "value": "true"
      }
    }
  ],
  "nextState": "heating"
}
]
}
},

{
  "stateName": "cooling",
  "onEnter": {
    "events": [
      {
        "eventName": "delay",
        "condition": "!$variable.noDelay && $variable.enteringNewState",
        "actions": [
          {
            "setTimer": {
              "timerName": "coolingTimer",
              "seconds": 180
            }
          },
          {
            "setVariable": {
              "variableName": "goodToGo",
              "value": "false"
            }
          }
        ]
      },
      {
        "eventName": "dontDelay",
```

```
    "condition": "$variable.noDelay == true",
    "actions": [
      {
        "setVariable": {
          "variableName": "goodToGo",
          "value": "true"
        }
      }
    ]
  },
  {
    "eventName": "beenHere",
    "condition": "true",
    "actions": [
      {
        "setVariable": {
          "variableName": "enteringNewState",
          "value": "false"
        }
      }
    ]
  }
],
},
"onInput": {
  "events": [
    {
      "eventName": "whatWasInput",
      "condition": "true",
      "actions": [
        {
          "setVariable": {
            "variableName": "sensorId",
            "value": "$input.temperatureInput.sensorId"
          }
        },
        {
          "setVariable": {
            "variableName": "reportedTemperature",
            "value": "$input.temperatureInput.sensorData.temperature"
          }
        }
      ]
    }
  ]
}
```

```

    },
    {
      "eventName": "changeDesired",
      "condition": "$input.seedTemperatureInput.desiredTemperature !=
$variable.desiredTemperature",
      "actions": [
        {
          "setVariable": {
            "variableName": "desiredTemperature",
            "value": "$input.seedTemperatureInput.desiredTemperature"
          }
        }
      ]
    },
    {
      "eventName": "calculateAverage",
      "condition": "$input.temperatureInput.sensorData.temperature <
$variable.anomalousHigh && $input.temperatureInput.sensorData.temperature >
$variable.anomalousLow",
      "actions": [
        {
          "setVariable": {
            "variableName": "averageTemperature",
            "value": "((( $variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount)"
          }
        }
      ]
    },
    {
      "eventName": "areWeThereYet",
      "condition": "(timeout(\"coolingTimer\"))",
      "actions": [
        {
          "setVariable": {
            "variableName": "goodToGo",
            "value": "true"
          }
        }
      ]
    }
  ],
  "transitionEvents": [
    {

```

```
    "eventName": "anomalousInputArrived",
    "condition": "$input.temperatureInput.sensorData.temperature >=
$variable.anomalousHigh || $input.temperatureInput.sensorData.temperature <=
$variable.anomalousLow",
    "actions": [
      {
        "iotTopicPublish": {
          "mqttTopic": "temperatureSensor/anomaly"
        }
      }
    ],
    "nextState": "cooling"
  },
  {
    "eventName": "highTemperatureSpike",
    "condition": "$input.temperatureInput.sensorData.temperature >
$variable.rangeHigh",
    "actions": [
      {
        "iotTopicPublish": {
          "mqttTopic": "temperatureSensor/spike"
        }
      }
    ],
    "nextState": "cooling"
  },
  {
    "eventName": "lowTemperatureSpike",
    "condition": "$input.temperatureInput.sensorData.temperature <
$variable.rangeLow",
    "actions": [
      {
        "iotTopicPublish": {
          "mqttTopic": "temperatureSensor/spike"
        }
      },
      {
        "sns": {
          "targetArn": "arn:aws:sns:us-west-2:123456789012:cool0ff"
        }
      }
    ],
  }
```

```

        "sns": {
            "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOn"
        }
    },
    {
        "iotTopicPublish": {
            "mqttTopic": "hvac/Cooling/Off"
        }
    },
    {
        "iotTopicPublish": {
            "mqttTopic": "hvac/Heating/On"
        }
    },
    {
        "setVariable": {
            "variableName": "enteringNewState",
            "value": "true"
        }
    }
],
"nextState": "heating"
},
{
    "eventName": "desiredTemperature",
    "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) <=
($variable.desiredTemperature - $variable.allowedError)) && $variable.goodToGo ==
true",
    "actions": [
        {
            "sns": {
                "targetArn": "arn:aws:sns:us-west-2:123456789012:cool0ff"
            }
        },
        {
            "iotTopicPublish": {
                "mqttTopic": "hvac/Cooling/Off"
            }
        }
    ],
    "nextState": "idle"
}
}

```

```
    ]
  }
},

{
  "stateName": "heating",
  "onEnter": {
    "events": [
      {
        "eventName": "delay",
        "condition": "!$variable.noDelay && $variable.enteringNewState",
        "actions": [
          {
            "setTimer": {
              "timerName": "heatingTimer",
              "seconds": 120
            }
          },
          {
            "setVariable": {
              "variableName": "goodToGo",
              "value": "false"
            }
          }
        ]
      },
      {
        "eventName": "dontDelay",
        "condition": "$variable.noDelay == true",
        "actions": [
          {
            "setVariable": {
              "variableName": "goodToGo",
              "value": "true"
            }
          }
        ]
      },
      {
        "eventName": "beenHere",
        "condition": "true",
        "actions": [
          {
```



```

        "eventName": "calculateAverage",
        "condition": "$input.temperatureInput.sensorData.temperature <
$variable.anomalousHigh && $input.temperatureInput.sensorData.temperature >
$variable.anomalousLow",
        "actions": [
            {
                "setVariable": {
                    "variableName": "averageTemperature",
                    "value": "(((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount)"
                }
            }
        ],
    },
    {
        "eventName": "areWeThereYet",
        "condition": "(timeout(\"heatingTimer\"))",
        "actions": [
            {
                "setVariable": {
                    "variableName": "goodToGo",
                    "value": "true"
                }
            }
        ]
    }
],
"transitionEvents": [
    {
        "eventName": "anomalousInputArrived",
        "condition": "$input.temperatureInput.sensorData.temperature >=
$variable.anomalousHigh || $input.temperatureInput.sensorData.temperature <=
$variable.anomalousLow",
        "actions": [
            {
                "iotTopicPublish": {
                    "mqttTopic": "temperatureSensor/anomaly"
                }
            }
        ],
        "nextState": "heating"
    },
    {

```

```

    "eventName": "highTemperatureSpike",
    "condition": "$input.temperatureInput.sensorData.temperature >
$variable.rangeHigh",
    "actions": [
      {
        "iotTopicPublish": {
          "mqttTopic": "temperatureSensor/spike"
        }
      },
      {
        "sns": {
          "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOff"
        }
      },
      {
        "sns": {
          "targetArn": "arn:aws:sns:us-west-2:123456789012:coolOn"
        }
      },
      {
        "iotTopicPublish": {
          "mqttTopic": "hvac/Heating/Off"
        }
      },
      {
        "iotTopicPublish": {
          "mqttTopic": "hvac/Cooling/On"
        }
      },
      {
        "setVariable": {
          "variableName": "enteringNewState",
          "value": "true"
        }
      }
    ],
    "nextState": "cooling"
  },
  {
    "eventName": "lowTemperatureSpike",
    "condition": "$input.temperatureInput.sensorData.temperature <
$variable.rangeLow",
    "actions": [

```

```

        {
            "iotTopicPublish": {
                "mqttTopic": "temperatureSensor/spike"
            }
        }
    ],
    "nextState": "heating"
},

{
    "eventName": "desiredTemperature",
    "condition": "((((($variable.averageTemperature * ($variable.sensorCount
- 1)) + $input.temperatureInput.sensorData.temperature) / $variable.sensorCount) >=
($variable.desiredTemperature + $variable.allowedError)) && $variable.goodToGo ==
true",
    "actions": [
        {
            "sns": {
                "targetArn": "arn:aws:sns:us-west-2:123456789012:heatOff"
            }
        },
        {
            "iotTopicPublish": {
                "mqttTopic": "hvac/Heating/Off"
            }
        }
    ],
    "nextState": "idle"
}
]
}
}

],

"initialStateName": "start"
},
"key": "areaId",
"roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole"
}
}

```

Response:

```
{
  "detectorModelConfiguration": {
    "status": "ACTIVATING",
    "lastUpdateTime": 1557523491.168,
    "roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole",
    "creationTime": 1557523491.168,
    "detectorModelArn": "arn:aws:iotevents:us-west-2:123456789012:detectorModel/
areaDetectorModel",
    "key": "areaId",
    "detectorModelName": "areaDetectorModel",
    "detectorModelVersion": "1"
  }
}
```

BatchPutMessage examples for an HVAC system in Amazon IoT Events

In this example, BatchPutMessage is used to create a detector instance for an area and define the initial operating parameters.

CLI command used:

```
aws iotevents-data batch-put-message --cli-input-json file://seedExample.json --cli-
binary-format raw-in-base64-out
```

File: seedExample.json

```
{
  "messages": [
    {
      "messageId": "00001",
      "inputName": "seedTemperatureInput",
      "payload": "{\"areaId\": \"Area51\", \"desiredTemperature\": 20.0, \"allowedError
\": 0.7, \"rangeHigh\": 30.0, \"rangeLow\": 15.0, \"anomalousHigh\": 60.0,
\"anomalousLow\": 0.0, \"sensorCount\": 10, \"noDelay\": false}"
    }
  ]
}
```

Response:

```
{
  "BatchPutMessageErrorEntries": []
}
```

```
}
```

In this example, `BatchPutMessage` is used to report temperature sensor readings for a single sensor in an area.

CLI command used:

```
aws iotevents-data batch-put-message --cli-input-json file://temperatureExample.json --cli-binary-format raw-in-base64-out
```

File: `temperatureExample.json`

```
{
  "messages": [
    {
      "messageId": "00005",
      "inputName": "temperatureInput",
      "payload": "{\"sensorId\": \"05\", \"areaId\": \"Area51\", \"sensorData\": {\"temperature\": 23.12} }"
    }
  ]
}
```

Response:

```
{
  "BatchPutMessageErrorEntries": []
}
```

In this example, `BatchPutMessage` is used to change the desired temperature for an area.

CLI command used:

```
aws iotevents-data batch-put-message --cli-input-json file://seedSetDesiredTemp.json --cli-binary-format raw-in-base64-out
```

File: `seedSetDesiredTemp.json`

```
{
  "messages": [
    {
      "messageId": "00001",
```

```

    "inputName": "seedTemperatureInput",
    "payload": "{\"areaId\": \"Area51\", \"desiredTemperature\": 23.0}"
  }
]
}

```

Response:

```

{
  "BatchPutMessageErrorEntries": []
}

```

Examples of Amazon SNS messages generated by the Area51 detector instance:

```

Heating system off command> {
  "eventTime":1557520274729,
  "payload":{
    "actionExecutionId":"f3159081-bac3-38a4-96f7-74af0940d0a4",
    "detector":{
      "detectorModelName":"areaDetectorModel",
      "keyValue":"Area51",
      "detectorModelVersion":"1"
    },
    "eventTriggerDetails":{
      "inputName":"seedTemperatureInput",
      "messageId":"00001",
      "triggerType":"Message"
    },
    "state":{
      "stateName":"start",
      "variables":{
        "sensorCount":10,
        "rangeHigh":30.0,
        "resetMe":false,
        "enteringNewState":true,
        "averageTemperature":20.0,
        "rangeLow":15.0,
        "noDelay":false,
        "allowedError":0.7,
        "desiredTemperature":20.0,
        "anomalousHigh":60.0,

```

```

        "reportedTemperature":0.1,
        "anomalousLow":0.0,
        "sensorId":0
    },
    "timers":{}
}
},
"eventName":"resetHeatCool"
}

```

```

Cooling system off command> {
  "eventTime":1557520274729,
  "payload":{
    "actionExecutionId":"98f6a1b5-8f40-3cdb-9256-93afd4d66192",
    "detector":{
      "detectorModelName":"areaDetectorModel",
      "keyValue":"Area51",
      "detectorModelVersion":"1"
    },
    "eventTriggerDetails":{
      "inputName":"seedTemperatureInput",
      "messageId":"00001",
      "triggerType":"Message"
    },
    "state":{
      "stateName":"start",
      "variables":{
        "sensorCount":10,
        "rangeHigh":30.0,
        "resetMe":false,
        "enteringNewState":true,
        "averageTemperature":20.0,
        "rangeLow":15.0,
        "noDelay":false,
        "allowedError":0.7,
        "desiredTemperature":20.0,
        "anomalousHigh":60.0,
        "reportedTemperature":0.1,
        "anomalousLow":0.0,
        "sensorId":0
      },
      "timers":{}
    }
  }
}

```



```
    }
  },
  "eventName": "resetHeatCool"
}
```

In this example, we use the `DescribeDetector` API to get information about the current state of a detector instance.

```
aws iotevents-data describe-detector --detector-model-name areaDetectorModel --key-value Area51
```

Response:

```
{
  "detector": {
    "lastUpdateTime": 1557521572.216,
    "creationTime": 1557520274.405,
    "state": {
      "variables": [
        {
          "name": "resetMe",
          "value": "false"
        },
        {
          "name": "rangeLow",
          "value": "15.0"
        },
        {
          "name": "noDelay",
          "value": "false"
        },
        {
          "name": "desiredTemperature",
          "value": "20.0"
        },
        {
          "name": "anomalousLow",
          "value": "0.0"
        },
        {
          "name": "sensorId",
          "value": "\"01\""
        }
      ]
    }
  }
}
```

```
    {
      "name": "sensorCount",
      "value": "10"
    },
    {
      "name": "rangeHigh",
      "value": "30.0"
    },
    {
      "name": "enteringNewState",
      "value": "false"
    },
    {
      "name": "averageTemperature",
      "value": "19.572"
    },
    {
      "name": "allowedError",
      "value": "0.7"
    },
    {
      "name": "anomalousHigh",
      "value": "60.0"
    },
    {
      "name": "reportedTemperature",
      "value": "15.72"
    },
    {
      "name": "goodToGo",
      "value": "false"
    }
  ],
  "stateName": "idle",
  "timers": [
    {
      "timestamp": 1557520454.0,
      "name": "idleTimer"
    }
  ]
},
"keyValue": "Area51",
"detectorModelName": "areaDetectorModel",
"detectorModelVersion": "1"
```

```
}  
}
```

BatchUpdateDetector example for an HVAC system in Amazon IoT Events

In this example, `BatchUpdateDetector` is used to change operational parameters for a working detector instance.

Efficient HVAC system management often requires batch updates to multiple detectors. This section demonstrates how to use Amazon IoT Events's batch update feature for detectors. Learn to simultaneously modify multiple control parameters, update threshold values, so that you can adjust response actions across a fleet of devices, improving your ability to manage large-scale systems effectively.

CLI command used:

```
aws iotevents-data batch-update-detector --cli-input-json file://areaDM.BUD.json
```

File: `areaDM.BUD.json`

```
{  
  "detectors": [  
    {  
      "messageId": "0001",  
      "detectorModelName": "areaDetectorModel",  
      "keyValue": "Area51",  
      "state": {  
        "stateName": "start",  
        "variables": [  
          {  
            "name": "desiredTemperature",  
            "value": "22"  
          },  
          {  
            "name": "averageTemperature",  
            "value": "22"  
          },  
          {  
            "name": "allowedError",
```

```
    "value": "1.0"
  },
  {
    "name": "rangeHigh",
    "value": "30.0"
  },
  {
    "name": "rangeLow",
    "value": "15.0"
  },
  {
    "name": "anomalousHigh",
    "value": "60.0"
  },
  {
    "name": "anomalousLow",
    "value": "0.0"
  },
  {
    "name": "sensorCount",
    "value": "12"
  },
  {
    "name": "noDelay",
    "value": "true"
  },
  {
    "name": "goodToGo",
    "value": "true"
  },
  {
    "name": "sensorId",
    "value": "0"
  },
  {
    "name": "reportedTemperature",
    "value": "0.1"
  },
  {
    "name": "resetMe",
    "value": "true"
  }
],
"timers": [
```

```
    ]
  }
}
]
```

Response:

```
{
  An error occurred (InvalidRequestException) when calling the BatchUpdateDetector
  operation: Number of variables in the detector exceeds the limit 10
}
```

The Amazon IoT Core rules engine and Amazon IoT Events

The following rules republish Amazon IoT Events MQTT messages as shadow update request messages. We assume that Amazon IoT Core things are defined for a heating unit and a cooling unit for each area that is controlled by the detector model.

In this example, we have defined things named `Area51HeatingUnit` and `Area51CoolingUnit`.

CLI command used:

```
aws iot create-topic-rule --cli-input-json file://ADMShadowCoolOffRule.json
```

File: `ADMShadowCoolOffRule.json`

```
{
  "ruleName": "ADMShadowCoolOff",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Cooling/Off'",
    "description": "areaDetectorModel mqtt topic publish to cooling unit shadow
request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
    "actions": [
      {
        "republish": {
          "topic": "$$aws/things/${payload.detector.keyValue}CoolingUnit/shadow/
update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMShadowRole"
```

```

    }
  }
]
}
}

```

Response: [empty]

CLI command used:

```
aws iot create-topic-rule --cli-input-json file://ADMShadowCoolOnRule.json
```

File: ADMShadowCoolOnRule.json

```

{
  "ruleName": "ADMShadowCoolOn",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Cooling/On'",
    "description": "areaDetectorModel mqtt topic publish to cooling unit shadow request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
    "actions": [
      {
        "republish": {
          "topic": "$$aws/things/${payload.detector.keyValue}CoolingUnit/shadow/update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMShadowRole"
        }
      }
    ]
  }
}

```

Response: [empty]

CLI command used:

```
aws iot create-topic-rule --cli-input-json file://ADMShadowHeatOffRule.json
```

File: ADMShadowHeatOffRule.json

```
{
  "ruleName": "ADMSHadowHeatOff",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Heating/Off'",
    "description": "areaDetectorModel mqtt topic publish to heating unit shadow
request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
    "actions": [
      {
        "republish": {
          "topic": "$$aws/things/${payload.detector.keyValue}HeatingUnit/shadow/
update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMSHadowRole"
        }
      }
    ]
  }
}
```

Response: [empty]

CLI command used:

```
aws iot create-topic-rule --cli-input-json file://ADMSHadowHeatOnRule.json
```

File: ADMSHadowHeatOnRule.json

```
{
  "ruleName": "ADMSHadowHeatOn",
  "topicRulePayload": {
    "sql": "SELECT topic(3) as state.desired.command FROM 'hvac/Heating/On'",
    "description": "areaDetectorModel mqtt topic publish to heating unit shadow
request",
    "ruleDisabled": false,
    "awsIotSqlVersion": "2016-03-23",
    "actions": [
      {
        "republish": {
          "topic": "$$aws/things/${payload.detector.keyValue}HeatingUnit/shadow/
update",
          "roleArn": "arn:aws:iam::123456789012:role/service-role/ADMSHadowRole"
        }
      }
    ]
  }
}
```

```
    }  
  }  
]  
}  
}
```

Response: [empty]

Example: A crane detecting conditions using Amazon IoT Events

An operator of many cranes wants to detect when the machines need maintenance or replacement and trigger appropriate notifications. Each crane has a motor. A motor emits messages (inputs) with information about pressure and temperature. The operator wants two levels of event detectors:

- A crane-level event detector
- A motor-level event detector

Using messages from the motors (that contain metadata with both the `craneId` and the `motorId`), the operator can execute both levels of event detectors using appropriate routing. When event conditions are met, notifications should be sent to appropriate Amazon SNS topics. The operator can configure the detector models so that duplicate notifications are not raised.

This example demonstrates the following functional capabilities:

- Create, Read, Update, Delete (CRUD) of inputs.
- Create, Read, Update, Delete (CRUD) of event detector models and different versions of event detectors.
- Routing one input to multiple event detectors.
- Ingestion of inputs into a detector model.
- Evaluation of trigger conditions and lifecycle events.
- Ability to refer to state variables in conditions and set their values depending on conditions.
- Runtime orchestration with definition, state, trigger evaluator, and actions executor.
- Execution of actions in `ActionsExecutor` with an SNS target.

Send commands in response to detected conditions in Amazon IoT Events

This page provides an example for using Amazon IoT Events commands to set up inputs, create detector models, and send simulated sensor data. The examples demonstrate how to leverage Amazon IoT Events to monitor industrial equipment like motors and cranes.

```
#Create Pressure Input
aws iotevents create-input --cli-input-json file://pressureInput.json
aws iotevents describe-input --input-name PressureInput
aws iotevents update-input --cli-input-json file://pressureInput.json
aws iotevents list-inputs
aws iotevents delete-input --input-name PressureInput

#Create Temperature Input
aws iotevents create-input --cli-input-json file://temperatureInput.json
aws iotevents describe-input --input-name TemperatureInput
aws iotevents update-input --cli-input-json file://temperatureInput.json
aws iotevents list-inputs
aws iotevents delete-input --input-name TemperatureInput

#Create Motor Event Detector using pressure and temperature input
aws iotevents create-detector-model --cli-input-json file://motorDetectorModel.json
aws iotevents describe-detector-model --detector-model-name motorDetectorModel
aws iotevents update-detector-model --cli-input-json file://
updateMotorDetectorModel.json
aws iotevents list-detector-models
aws iotevents list-detector-model-versions --detector-model-name motorDetectorModel
aws iotevents delete-detector-model --detector-model-name motorDetectorModel

#Create Crane Event Detector using temperature input
aws iotevents create-detector-model --cli-input-json file://craneDetectorModel.json
aws iotevents describe-detector-model --detector-model-name craneDetectorModel
aws iotevents update-detector-model --cli-input-json file://
updateCraneDetectorModel.json
aws iotevents list-detector-models
aws iotevents list-detector-model-versions --detector-model-name craneDetectorModel
aws iotevents delete-detector-model --detector-model-name craneDetectorModel

#Replace craneIds
sed -i '' "s/100008/100009/g" messages/*
```

```
#Replace motorIds
sed -i '' "s/2000008/2000009/g" messages/*

#Send HighPressure message
aws iotevents-data batch-put-message --cli-input-json file://messages/
highPressureMessage.json --cli-binary-format raw-in-base64-out

#Send HighTemperature message
aws iotevents-data batch-put-message --cli-input-json file://messages/
highTemperatureMessage.json --cli-binary-format raw-in-base64-out

#Send LowPressure message
aws iotevents-data batch-put-message --cli-input-json file://messages/
lowPressureMessage.json --cli-binary-format raw-in-base64-out

#Send LowTemperature message
aws iotevents-data batch-put-message --cli-input-json file://messages/
lowTemperatureMessage.json --cli-binary-format raw-in-base64-out
```

An Amazon IoT Events detector model for crane monitoring

Monitor your equipment or device fleets for failures or changes in operation, and trigger actions when such events occur. You define detector models in JSON which specify states, rules, and actions. This allows you to monitor inputs like temperature and pressure, track threshold breaches, and send alerts. The examples show detector models for a crane and motor, detecting overheating issues and notifying by Amazon SNS when a threshold is exceeded. You can update models to refine behavior without disrupting monitoring.

File: craneDetectorModel.json

```
{
  "detectorModelName": "craneDetectorModel",
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "Running",
        "onEnter": {
          "events": [
            {
              "eventName": "init",
```

```

        "condition": "true",
        "actions": [
            {
                "setVariable": {
                    "variableName": "craneThresholdBreach",
                    "value": "0"
                }
            }
        ]
    },
    ],
    "onInput": {
        "events": [
            {
                "eventName": "Overheated",
                "condition": "$input.TemperatureInput.temperature > 35",
                "actions": [
                    {
                        "setVariable": {
                            "variableName": "craneThresholdBreach",
                            "value": "$variable.craneThresholdBreach + 1"
                        }
                    }
                ]
            },
            {
                "eventName": "Crane Threshold Breached",
                "condition": "$variable.craneThresholdBreach > 5",
                "actions": [
                    {
                        "sns": {
                            "targetArn": "arn:aws:sns:us-
east-1:123456789012:CraneSNSTopic"
                        }
                    }
                ]
            },
            {
                "eventName": "Underheated",
                "condition": "$input.TemperatureInput.temperature < 25",
                "actions": [
                    {
                        "setVariable": {

```

```

        "variableName": "craneThresholdBreached",
        "value": "0"
      }
    ]
  },
  "initialStateName": "Running"
},
],
"key": "craneid",
"roleArn": "arn:aws:iam::123456789012:role/columboSNSRole"
}

```

To update an existing detector model. File: `updateCraneDetectorModel.json`

```

{
  "detectorModelName": "craneDetectorModel",
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "Running",
        "onEnter": {
          "events": [
            {
              "eventName": "init",
              "condition": "true",
              "actions": [
                {
                  "setVariable": {
                    "variableName": "craneThresholdBreached",
                    "value": "0"
                  }
                },
                {
                  "setVariable": {
                    "variableName": "alarmRaised",
                    "value": "'false'"
                  }
                }
              ]
            }
          ]
        }
      }
    ]
  }
}

```



```

    }
  ]
},
"initialStateName": "Running"
},
"roleArn": "arn:aws:iam::123456789012:role/columboSNSRole"
}

```

File: motorDetectorModel.json

```

{
  "detectorModelName": "motorDetectorModel",
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "Running",
        "onEnter": {
          "events": [
            {
              "eventName": "init",
              "condition": "true",
              "actions": [
                {
                  "setVariable": {
                    "variableName": "motorThresholdBreach",
                    "value": "0"
                  }
                }
              ]
            }
          ]
        },
        "onInput": {
          "events": [
            {
              "eventName": "Overheated And Overpressurized",
              "condition": "$input.PressureInput.pressure > 70 &&
$input.TemperatureInput.temperature > 30",

```

```

        "actions": [
            {
                "setVariable": {
                    "variableName": "motorThresholdBreached",
                    "value": "$variable.motorThresholdBreached + 1"
                }
            }
        ],
    },
    {
        "eventName": "Motor Threshold Breached",
        "condition": "$variable.motorThresholdBreached > 5",
        "actions": [
            {
                "sns": {
                    "targetArn": "arn:aws:sns:us-
east-1:123456789012:MotorSNSTopic"
                }
            }
        ]
    }
]
}
},
],
"initialStateName": "Running"
},
"key": "motorId",
"roleArn": "arn:aws:iam::123456789012:role/columboSNSRole"
}

```

To update an existing detector model. File: `updateMotorDetectorModel.json`

```

{
  "detectorModelName": "motorDetectorModel",
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "Running",
        "onEnter": {
          "events": [
            {
              "eventName": "init",

```

```

        "condition": "true",
        "actions": [
            {
                "setVariable": {
                    "variableName": "motorThresholdBreach",
                    "value": "0"
                }
            }
        ]
    },
    ],
    "onInput": {
        "events": [
            {
                "eventName": "Overheated And Overpressurized",
                "condition": "$input.PressureInput.pressure > 70 &&
$input.TemperatureInput.temperature > 30",
                "actions": [
                    {
                        "setVariable": {
                            "variableName": "motorThresholdBreach",
                            "value": "$variable.motorThresholdBreach + 1"
                        }
                    }
                ]
            },
            {
                "eventName": "Motor Threshold Breached",
                "condition": "$variable.motorThresholdBreach > 5",
                "actions": [
                    {
                        "sns": {
                            "targetArn": "arn:aws:sns:us-
east-1:123456789012:MotorSNSTopic"
                        }
                    }
                ]
            }
        ]
    }
},
    ],
    "initialStateName": "Running"

```



```
  },  
  "roleArn": "arn:aws:iam::123456789012:role/columboSNSRole"  
}
```

Amazon IoT Events inputs for crane monitoring

In this example, we demonstrate how to set up inputs for a crane monitoring system using Amazon IoT Events. It captures pressure and temperature inputs to illustrate how to structure inputs for complex industrial equipment monitoring.

File: `pressureInput.json`

```
{  
  "inputName": "PressureInput",  
  "inputDescription": "this is a pressure input description",  
  "inputDefinition": {  
    "attributes": [  
      {"jsonPath": "pressure"}  
    ]  
  }  
}
```

File: `temperatureInput.json`

```
{  
  "inputName": "TemperatureInput",  
  "inputDescription": "this is temperature input description",  
  "inputDefinition": {  
    "attributes": [  
      {"jsonPath": "temperature"}  
    ]  
  }  
}
```

Send alarm and operational messages with Amazon IoT Events

Effective message handling is important in crane monitoring systems. This section showcases how to configure Amazon IoT Events to process and respond to various message types from crane sensors. Setting up alarms based on a particular message can help you parse, filter, and route status updates to trigger appropriate actions.

File: highPressureMessage.json

```
{
  "messages": [
    {
      "messageId": "1",
      "inputName": "PressureInput",
      "payload": "{\"craneid\": \"100009\", \"pressure\": 80, \"motorid\": \"200009\"}"
    }
  ]
}
```

File: highTemperatureMessage.json

```
{
  "messages": [
    {
      "messageId": "2",
      "inputName": "TemperatureInput",
      "payload": "{\"craneid\": \"100009\", \"temperature\": 40, \"motorid\": \"200009\"}"
    }
  ]
}
```

File: lowPressureMessage.json

```
{
  "messages": [
    {
      "messageId": "1",
      "inputName": "PressureInput",
      "payload": "{\"craneid\": \"100009\", \"pressure\": 20, \"motorid\": \"200009\"}"
    }
  ]
}
```

File: lowTemperatureMessage.json

```
{
  "messages": [
    {
      "messageId": "2",
      "inputName": "TemperatureInput",
      "payload": "{\"craneid\": \"100009\", \"temperature\": 20, \"motorid\": \"200009\"}"
    }
  ]
}
```

Example: Amazon IoT Events event detection with sensors and applications

This detector model is one of the templates available from the Amazon IoT Events console. It's included here for your convenience.

This example demonstrates Amazon IoT Events's application event detection using sensor data. It shows how you can create a detector model that monitors specified events so that you can trigger appropriate actions. You can create multiple sensor inputs, define complex event conditions, and set up graduated response mechanisms.

```
{
  "detectorModelName": "EventDetectionSensorsAndApplications",
  "detectorModelDefinition": {
    "states": [
      {
        "onInput": {
          "transitionEvents": [],
          "events": []
        },
        "stateName": "Device_exception",
        "onEnter": {
          "events": [
            {
              "eventName": "Send_mqtt",
              "actions": [
                {
                  "iotTopicPublish": {
                    "mqttTopic": "Device_stolen"
                  }
                }
              ]
            }
          ]
        }
      }
    ]
  }
}
```

```

        }
      ],
      "condition": "true"
    }
  ],
  },
  "onExit": {
    "events": []
  }
},
{
  "onInput": {
    "transitionEvents": [
      {
        "eventName": "To_in_use",
        "actions": [],
        "condition": "$variable.position !=
$input.AWS_IoTEvents_Blueprints_Tracking_DeviceInput.gps_position",
        "nextState": "Device_in_use"
      }
    ],
    "events": []
  },
  "stateName": "Device_idle",
  "onEnter": {
    "events": [
      {
        "eventName": "Set_position",
        "actions": [
          {
            "setVariable": {
              "variableName": "position",
              "value":
"$input.AWS_IoTEvents_Blueprints_Tracking_DeviceInput.gps_position"
            }
          }
        ],
        "condition": "true"
      }
    ]
  },
  "onExit": {
    "events": []
  }
}

```

```

    },
    {
      "onInput": {
        "transitionEvents": [
          {
            "eventName": "To_exception",
            "actions": [],
            "condition":
"$input.AWS_IoTEvents_Blueprints_Tracking_UserInput.device_id !=
$input.AWS_IoTEvents_Blueprints_Tracking_DeviceInput.device_id",
            "nextState": "Device_exception"
          }
        ],
        "events": []
      },
      "stateName": "Device_in_use",
      "onEnter": {
        "events": []
      },
      "onExit": {
        "events": []
      }
    }
  ],
  "initialStateName": "Device_idle"
}
}

```

Example: Device HeartBeat to monitor device connections with Amazon IoT Events

This detector model is one of the templates available from the Amazon IoT Events console. It's included here for your convenience.

The Defective Heart Beat (DHB) example illustrates how Amazon IoT Events can be used in healthcare monitoring. This example shows how you can create a detector model that analyzes heart rate data, detects irregular patterns, and triggers appropriate responses. Learn to set up inputs, define thresholds, and configure alerts for potential cardiac issues, showcasing Amazon IoT Events's versatility in related healthcare applications.

```
{
```

```

"detectorModelDefinition": {
  "states": [
    {
      "onInput": {
        "transitionEvents": [
          {
            "eventName": "To_normal",
            "actions": [],
            "condition":
"currentInput(\"AWS_IoTEvents_Blueprints_Heartbeat_Input\")",
            "nextState": "Normal"
          }
        ],
        "events": []
      },
      "stateName": "Offline",
      "onEnter": {
        "events": [
          {
            "eventName": "Send_notification",
            "actions": [
              {
                "sns": {
                  "targetArn": "sns-topic-arn"
                }
              }
            ],
            "condition": "true"
          }
        ]
      },
      "onExit": {
        "events": []
      }
    },
    {
      "onInput": {
        "transitionEvents": [
          {
            "eventName": "Go_offline",
            "actions": [],
            "condition": "timeout(\"awake\")",
            "nextState": "Offline"
          }
        ]
      }
    }
  ]
}

```

```

    ],
    "events": [
      {
        "eventName": "Reset_timer",
        "actions": [
          {
            "resetTimer": {
              "timerName": "awake"
            }
          }
        ],
        "condition":
"currentInput(\"AWS_IoTEvents_Blueprints_Heartbeat_Input\")"
      }
    ]
  },
  "stateName": "Normal",
  "onEnter": {
    "events": [
      {
        "eventName": "Create_timer",
        "actions": [
          {
            "setTimer": {
              "seconds": 300,
              "timerName": "awake"
            }
          }
        ],
        "condition":
"$input.AWS_IoTEvents_Blueprints_Heartbeat_Input.value > 0"
      }
    ]
  },
  "onExit": {
    "events": []
  }
},
],
"initialStateName": "Normal"
}
}

```

Example: An ISA alarm in Amazon IoT Events

This detector model is one of the templates available from the Amazon IoT Events console. It's included here for your convenience.

```
{
  "detectorModelName": "AWS_IoTEvents_Blueprints_ISA_Alarm",
  "detectorModelDefinition": {
    "states": [
      {
        "onInput": {
          "transitionEvents": [
            {
              "eventName": "unshelve",
              "actions": [],
              "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unshelve\" &&
$variable.state == \"rtnunack\"",
              "nextState": "RTN_Unacknowledged"
            },
            {
              "eventName": "unshelve",
              "actions": [],
              "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unshelve\" &&
$variable.state == \"ack\"",
              "nextState": "Acknowledged"
            },
            {
              "eventName": "unshelve",
              "actions": [],
              "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unshelve\" &&
$variable.state == \"unack\"",
              "nextState": "Unacknowledged"
            },
            {
              "eventName": "unshelve",
              "actions": [],
              "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unshelve\" &&
$variable.state == \"normal\"",
              "nextState": "Normal"
            }
          ]
        }
      }
    ]
  }
}
```



```

        }
    ],
    "events": []
},
"stateName": "Shelved",
"onEnter": {
    "events": []
},
"onExit": {
    "events": []
}
},
{
    "onInput": {
        "transitionEvents": [
            {
                "eventName": "abnormal_condition",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.value > $variable.higher_threshold ||
$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.value < $variable.lower_threshold",
                "nextState": "Unacknowledged"
            },
            {
                "eventName": "acknowledge",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"acknowledge\"",
                "nextState": "Normal"
            },
            {
                "eventName": "shelve",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"shelve\"",
                "nextState": "Shelved"
            },
            {
                "eventName": "remove_from_service",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"remove\"",
                "nextState": "Out_of_service"
            }
        ]
    }
}

```

```

        {
            "eventName": "suppression",
            "actions": [],
            "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"suppressed\"",
            "nextState": "Suppressed_by_design"
        }
    ],
    "events": []
},
"stateName": "RTN_Unacknowledged",
"onEnter": {
    "events": [
        {
            "eventName": "State Save",
            "actions": [
                {
                    "setVariable": {
                        "variableName": "state",
                        "value": "\"rtnunack\""
                    }
                }
            ],
            "condition": "true"
        }
    ]
},
"onExit": {
    "events": []
}
},
{
    "onInput": {
        "transitionEvents": [
            {
                "eventName": "abnormal_condition",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.value > $variable.higher_threshold ||
$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.value < $variable.lower_threshold",
                "nextState": "Unacknowledged"
            },
            {
                "eventName": "shelve",

```

```

        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"shelve\"",
        "nextState": "Shelved"
    },
    {
        "eventName": "remove_from_service",
        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"remove\"",
        "nextState": "Out_of_service"
    },
    {
        "eventName": "suppression",
        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"suppressed\"",
        "nextState": "Suppressed_by_design"
    }
],
"events": [
    {
        "eventName": "Create Config variables",
        "actions": [
            {
                "setVariable": {
                    "variableName": "lower_threshold",
                    "value":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.lower_threshold"
                }
            },
            {
                "setVariable": {
                    "variableName": "higher_threshold",
                    "value":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.higher_threshold"
                }
            }
        ],
        "condition": "$variable.lower_threshold !=
$variable.lower_threshold"
    }
]
},

```

```

    "stateName": "Normal",
    "onEnter": {
      "events": [
        {
          "eventName": "State Save",
          "actions": [
            {
              "setVariable": {
                "variableName": "state",
                "value": "\"normal\""
              }
            }
          ],
          "condition": "true"
        }
      ],
    },
    "onExit": {
      "events": []
    }
  },
  {
    "onInput": {
      "transitionEvents": [
        {
          "eventName": "acknowledge",
          "actions": [],
          "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"acknowledge\"",
          "nextState": "Acknowledged"
        },
        {
          "eventName": "return_to_normal",
          "actions": [],
          "condition":
"($input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.value <= $variable.higher_threshold
&& $input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.value >=
$variable.lower_threshold)",
          "nextState": "RTN_Unacknowledged"
        },
        {
          "eventName": "shelve",
          "actions": [],

```

```

        "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"shelve\"",
        "nextState": "Shelved"
    },
    {
        "eventName": "remove_from_service",
        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"remove\"",
        "nextState": "Out_of_service"
    },
    {
        "eventName": "suppression",
        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"suppressed\"",
        "nextState": "Suppressed_by_design"
    }
],
"events": []
},
"stateName": "Unacknowledged",
"onEnter": {
    "events": [
        {
            "eventName": "State Save",
            "actions": [
                {
                    "setVariable": {
                        "variableName": "state",
                        "value": "\"unack\""
                    }
                }
            ]
        },
        {
            "condition": "true"
        }
    ]
},
"onExit": {
    "events": []
}
},
{
    "onInput": {

```

```

        "transitionEvents": [
            {
                "eventName": "unsuppression",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unsuppressed\" &&
$variable.state == \"normal\"",
                "nextState": "Normal"
            },
            {
                "eventName": "unsuppression",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unsuppressed\" &&
$variable.state == \"unack\"",
                "nextState": "Unacknowledged"
            },
            {
                "eventName": "unsuppression",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unsuppressed\" &&
$variable.state == \"ack\"",
                "nextState": "Acknowledged"
            },
            {
                "eventName": "unsuppression",
                "actions": [],
                "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"unsuppressed\" &&
$variable.state == \"rtnunack\"",
                "nextState": "RTN_Unacknowledged"
            }
        ],
        "events": [],
    },
    "stateName": "Suppressed_by_design",
    "onEnter": {
        "events": []
    },
    "onExit": {
        "events": []
    }
},

```

```

    {
      "onInput": {
        "transitionEvents": [
          {
            "eventName": "return_to_service",
            "actions": [],
            "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"add\" && $variable.state
== \"rtnunack\"",
            "nextState": "RTN_Unacknowledged"
          },
          {
            "eventName": "return_to_service",
            "actions": [],
            "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"add\" && $variable.state
== \"unack\"",
            "nextState": "Unacknowledged"
          },
          {
            "eventName": "return_to_service",
            "actions": [],
            "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"add\" && $variable.state
== \"ack\"",
            "nextState": "Acknowledged"
          },
          {
            "eventName": "return_to_service",
            "actions": [],
            "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \"add\" && $variable.state
== \"normal\"",
            "nextState": "Normal"
          }
        ],
        "events": []
      },
      "stateName": "Out_of_service",
      "onEnter": {
        "events": []
      },
      "onExit": {
        "events": []
      }
    }

```

```

    }
  },
  {
    "onInput": {
      "transitionEvents": [
        {
          "eventName": "re-alarm",
          "actions": [],
          "condition": "timeout(\\"snooze\\")",
          "nextState": "Unacknowledged"
        },
        {
          "eventName": "return_to_normal",
          "actions": [],
          "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \\"reset\\\"",
          "nextState": "Normal"
        },
        {
          "eventName": "shelve",
          "actions": [],
          "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \\"shelve\\\"",
          "nextState": "Shelved"
        },
        {
          "eventName": "remove_from_service",
          "actions": [],
          "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \\"remove\\\"",
          "nextState": "Out_of_service"
        },
        {
          "eventName": "suppression",
          "actions": [],
          "condition":
"$input.AWS_IoTEvents_Blueprints_ISA_Alarm_Input.command == \\"suppressed\\\"",
          "nextState": "Suppressed_by_design"
        }
      ],
      "events": []
    },
    "stateName": "Acknowledged",
    "onEnter": {

```



```
    "events": [
      {
        "eventName": "Create Timer",
        "actions": [
          {
            "setTimer": {
              "seconds": 60,
              "timerName": "snooze"
            }
          }
        ],
        "condition": "true"
      },
      {
        "eventName": "State Save",
        "actions": [
          {
            "setVariable": {
              "variableName": "state",
              "value": "\"ack\""
            }
          }
        ],
        "condition": "true"
      }
    ]
  },
  "onExit": {
    "events": []
  }
},
"initialStateName": "Normal"
},
"detectorModelDescription": "This detector model is used to detect if a monitored device is in an Alarming State in accordance to the ISA 18.2.",
"roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole",
"key": "alarmId"
}
```

Example: Build a simple alarm with Amazon IoT Events

This detector model is one of the templates available from the Amazon IoT Events console. It's included here for your convenience.

```
{
  "detectorModelDefinition": {
    "states": [
      {
        "onInput": {
          "transitionEvents": [
            {
              "eventName": "not_fixed",
              "actions": [],
              "condition": "timeout(\"snoozeTime\")",
              "nextState": "Alarming"
            },
            {
              "eventName": "reset",
              "actions": [],
              "condition":
"$input.AWS_IoTEvents_Blueprints_Simple_Alarm_Input.command == \"reset\"",
              "nextState": "Normal"
            }
          ],
          "events": [
            {
              "eventName": "DND",
              "actions": [
                {
                  "setVariable": {
                    "variableName": "dnd_active",
                    "value": "1"
                  }
                }
              ],
              "condition":
"$input.AWS_IoTEvents_Blueprints_Simple_Alarm_Input.command == \"dnd\""
            }
          ]
        },
        "stateName": "Snooze",
        "onEnter": {
```

```

    "events": [
      {
        "eventName": "Create Timer",
        "actions": [
          {
            "setTimer": {
              "seconds": 120,
              "timerName": "snoozeTime"
            }
          }
        ],
        "condition": "true"
      }
    ],
    "onExit": {
      "events": []
    }
  },
  {
    "onInput": {
      "transitionEvents": [
        {
          "eventName": "out_of_range",
          "actions": [],
          "condition":
"$input.AWS_IoTEvents_Blueprints_Simple_Alarm_Input.value > $variable.threshold",
          "nextState": "Alarming"
        }
      ],
      "events": [
        {
          "eventName": "Create Config variables",
          "actions": [
            {
              "setVariable": {
                "variableName": "threshold",
                "value":
"$input.AWS_IoTEvents_Blueprints_Simple_Alarm_Input.threshold"
              }
            }
          ],
          "condition": "$variable.threshold != $variable.threshold"
        }
      ]
    }
  }
}

```

```

    ]
  },
  "stateName": "Normal",
  "onEnter": {
    "events": [
      {
        "eventName": "Init",
        "actions": [
          {
            "setVariable": {
              "variableName": "dnd_active",
              "value": "0"
            }
          }
        ],
        "condition": "true"
      }
    ]
  },
  "onExit": {
    "events": []
  }
},
{
  "onInput": {
    "transitionEvents": [
      {
        "eventName": "reset",
        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_Simple_Alarm_Input.command == \"reset\"",
        "nextState": "Normal"
      },
      {
        "eventName": "acknowledge",
        "actions": [],
        "condition":
"$input.AWS_IoTEvents_Blueprints_Simple_Alarm_Input.command == \"acknowledge\"",
        "nextState": "Snooze"
      }
    ],
    "events": [
      {
        "eventName": "Escalated Alarm Notification",

```

```

        "actions": [
            {
                "sns": {
                    "targetArn": "arn:aws:sns:us-
west-2:123456789012:escalatedAlarmNotification"
                }
            },
            ],
        "condition": "timeout(\"unacknowledgeTime\")"
    }
]
},
"stateName": "Alarming",
"onEnter": {
    "events": [
        {
            "eventName": "Alarm Notification",
            "actions": [
                {
                    "sns": {
                        "targetArn": "arn:aws:sns:us-
west-2:123456789012:alarmNotification"
                    }
                },
                {
                    "setTimer": {
                        "seconds": 300,
                        "timerName": "unacknowledgeTime"
                    }
                }
            ],
            "condition": "$variable.dnd_active != 1"
        }
    ]
},
"onExit": {
    "events": []
}
},
],
"initialStateName": "Normal"
},
"detectorModelDescription": "This detector model is used to detect if a monitored
device is in an Alarming State.",

```

```
"roleArn": "arn:aws:iam::123456789012:role/IoTEventsRole",  
"key": "alarmId"  
}
```

Monitoring with alarms in Amazon IoT Events

Amazon IoT Events alarms help you monitor your data for changes. The data can be metrics that you measure for your equipment and processes. You can create alarms that send notifications when a threshold is breached. Alarms help you detect issues, streamline maintenance, and optimize performance of your equipment and processes.

Alarms are instances of alarm models. The alarm model specifies what to detect, when to send notifications, who gets notified, and more. You can also specify one or more [supported actions](#) that occur when the alarm state changes. Amazon IoT Events routes [input attributes](#) derived from your data to the appropriate alarms. If the data that you're monitoring is outside the specified range, the alarm is invoked. You can also acknowledge the alarms or set them to the snooze mode.

Note

The alarm notifications feature isn't available in the China (Beijing) Region.

Working with Amazon IoT SiteWise

You can use Amazon IoT Events alarms to monitor asset properties in Amazon IoT SiteWise. Amazon IoT SiteWise sends asset property values to Amazon IoT Events alarms. Amazon IoT Events sends the alarm state to Amazon IoT SiteWise.

Amazon IoT SiteWise also supports external alarms. You might choose external alarms if you use alarms outside of Amazon IoT SiteWise and have a solution that returns alarm state data. The external alarm contains a measurement property that ingests the alarm state data.

Amazon IoT SiteWise doesn't evaluate the state of external alarms. Additionally, you can't acknowledge or snooze an external alarm when the alarm state changes.

You can use the SiteWise Monitor feature to view the state of external alarms in SiteWise Monitor portals.

For more information, see [Monitoring data with alarms](#) in the *Amazon IoT SiteWise User Guide* and [Monitoring with alarms](#) in the *SiteWise Monitor Application Guide*.

Acknowledge flow

When you create an alarm model, you choose whether to enable acknowledge flow. If you enable acknowledge flow, your team gets notified when the alarm state changes. Your team can acknowledge the alarm and leave a note. For example, you can include the information of the alarm and the actions that you're going to take to address the issue. If the data that you're monitoring is outside the specified range, the alarm is invoked.

Alarms have the following states:

DISABLED

When the alarm is in the DISABLED state, it isn't ready to evaluate data. To enable the alarm, you must change the alarm to the NORMAL state.

NORMAL

When the alarm is in the NORMAL state, it's ready to evaluate data.

ACTIVE

If the alarm is in the ACTIVE state, the alarm is invoked. The data that you're monitoring is outside the specified range.

ACKNOWLEDGED

When the alarm is in the ACKNOWLEDGED state, the alarm was invoked and you acknowledged the alarm.

LATCHED

The alarm was invoked, but you didn't acknowledge the alarm after a period of time. The alarm automatically changes to the NORMAL state.

SNOOZE_DISABLED

When the alarm is in the SNOOZE_DISABLED state, the alarm is disabled for a specified period of time. After the snooze time, the alarm automatically changes to the NORMAL state.

Creating an alarm model in Amazon IoT Events

You can use Amazon IoT Events alarms to monitor your data and get notified when a threshold is breached. Alarms provide parameters that you use to create or configure an alarm model. You

can use the Amazon IoT Events console or Amazon IoT Events API to create or configure the alarm model. When you configure the alarm model, changes take effect as new data arrives.

Requirements

The following requirements apply when you create an alarm model.

- You can create an alarm model to monitor an input attribute in Amazon IoT Events or an asset property in Amazon IoT SiteWise.
 - If you choose to monitor an input attribute in Amazon IoT Events, [Create an input for models in Amazon IoT Events](#) before you create the alarm model.
 - If you choose to monitor an asset property, you must [create an asset model](#) in Amazon IoT SiteWise before you create the alarm model.
- You must have an IAM role that allows your alarm to perform actions and access Amazon resources. For more information, see [Setting up permissions for Amazon IoT Events](#).
- All the Amazon resources that this tutorial uses must be in the same Amazon Region.

Creating an alarm model (console)

The following shows you how to create an alarm model to monitor an Amazon IoT Events attribute in the Amazon IoT Events console.

1. Sign in to the [Amazon IoT Events console](#).
2. In the navigation pane, choose **Alarm models**.
3. On the **Alarm models** page, choose **Create alarm model**.
4. In the **Alarm model details** section, do the following:
 - a. Enter a unique name.
 - b. (Optional) Enter a description.
5. In the **Alarm target** section, do the following:

Important

If you choose **Amazon IoT SiteWise asset property**, you must have created an asset model in Amazon IoT SiteWise.

- a. Choose **Amazon IoT Events input attribute**.
- b. Choose the input.
- c. Choose the input attribute key. This input attribute is used as a key to create the alarm. Amazon IoT Events routes inputs associated with this key to the alarm.

 **Important**

If the input message payload does not contain this input attribute key, or if the key is not in the same JSON path specified in the key, then the message will fail the ingestion in Amazon IoT Events.

6. In the **Threshold definitions** section, you define the input attribute, threshold value, and comparison operator that Amazon IoT Events uses to change the state of the alarm.

- a. For **Input attribute**, choose the attribute that you want to monitor.

Each time that this input attribute receives new data, it's evaluated to determine the state of the alarm.

- b. For **Operator**, choose the comparison operator. The operator compares your input attribute with the threshold value for your attribute.

You can choose from these options:

- **> greater than**
 - **>= greater than or equal to**
 - **< less than**
 - **<= less than or equal to**
 - **= equal to**
 - **!= not equal to**
- c. For threshold **Value**, enter a number or choose an attribute in Amazon IoT Events inputs. Amazon IoT Events compares this value with the value of the input attribute you choose.
 - d. (Optional) For **Severity**, Use a number that your team understands to reflect the severity of this alarm.
7. (Optional) In the **Notification settings** section, configure notification settings for the alarm.

Note

The alarm notifications feature isn't available in the China (Beijing) Region.

You can add up to 10 notifications. For **Notification 1**, do the following:

- a. For **Protocol**, choose from the following options:
 - **Email & text** - The alarm sends an SMS notification and an email notification.
 - **Email** - The alarm sends an email notification.
 - **Text** - The alarm sends an SMS notification.
- b. For **Sender**, specify the email address that can send notifications about this alarm.

To add more email addresses to your sender list, choose **Add sender**.

- c. (Optional) For **Recipient**, choose the recipient.

To add more users to your recipient list, choose **Add new user**. You must add new users to your IAM Identity Center store before you can add them to your alarm model. For more information, see [Manage IAM Identity Center access of alarm recipients in Amazon IoT Events](#).

- d. (Optional) For **Additional custom message**, enter a message that describes what the alarm detects and what actions the recipients should take.
8. In the **Instance** section, you can enable or disable all alarm instances that are created based on this alarm model.
 9. In the **Advanced settings** section, do the following:
 - a. For **Acknowledge flow**, you can enable or disable notifications.
 - If you choose **Enabled**, you receive a notification when the alarm state changes. You must acknowledge the notification before the alarm state can return to normal.
 - If you choose **Disabled**, no action is required. The alarm automatically changes to the normal state when the measurement returns to the specified range.

For more information, see [Acknowledge flow](#).

- b. For **Permissions**, choose one of the following options:

- You can **Create a new role from Amazon policy templates** and Amazon IoT Events automatically creates an IAM role for you.
- You can **Use an existing IAM role** that allows this alarm model to perform actions and access other Amazon resources.

For more information, see [Identity and access management for Amazon IoT Events](#).

- c. For **Additional notification settings**, you can edit your Amazon Lambda function to manage alarm notifications. Choose one of the following options for your Amazon Lambda function:
 - **Create a new Amazon Lambda function** - Amazon IoT Events creates a new Amazon Lambda function for you.
 - **Use an existing Amazon Lambda function** - Use an existing Amazon Lambda function by choosing an Amazon Lambda function name.

For more information about the possible actions, see [Amazon IoT Events working with other Amazon services](#).

- d. (Optional) For **Set state action**, you can add one or more Amazon IoT Events actions to take when the alarm state changes.
10. (Optional) You can add **Tags** to manage your alarms. For more information, see [Tagging your Amazon IoT Events resources](#).
 11. Choose **Create**.

Responding to alarms in Amazon IoT Events

Responding to alarms effectively is an important aspect of managing IoT systems with Amazon IoT Events. Explore various ways to configure and handle alarms, including: setting up notification channels, defining escalation procedures, and implementing automated response actions. Learn to create nuanced alarm conditions, prioritize alerts, and integrate with other Amazon services to build a responsive alarm management system for your IoT applications.

If you enabled [acknowledge flow](#), you receive notifications when the alarm state changes. To respond to the alarm, you can acknowledge, disable, enable, reset, or snooze the alarm.

Console

The following shows you how to respond to an alarm in the Amazon IoT Events console.

1. Sign in to the [Amazon IoT Events console](#).
2. In the navigation pane, choose **Alarm models**.
3. Choose the target alarm model.
4. In the **List of alarms** section, choose the target alarm.
5. You can choose one of the following options from **Actions**:
 - **Acknowledge** - The alarm changes to the ACKNOWLEDGED state.
 - **Disable** - The alarm changes to the DISABLED state.
 - **Enable** - The alarm changes to the NORMAL state.
 - **Reset** - The alarm changes to the NORMAL state.
 - **Snooze**, and then do the following:
 1. Choose the **Snooze length** or enter a **Custom snooze length**.
 2. Choose **Save**.

The alarm changes to the SNOOZE_DISABLED state

For more information about the alarm states, see [Acknowledge flow](#).

API

To respond to one or more alarms, you can use the following Amazon IoT Events API operations:

- [BatchAcknowledgeAlarm](#)
- [BatchDisableAlarm](#)
- [BatchEnableAlarm](#)
- [BatchResetAlarm](#)
- [BatchSnoozeAlarm](#)

Managing alarm notifications in Amazon IoT Events

Amazon IoT Events integrates with Lambda, offering custom event processing capabilities. This section explores how to use Lambda functions within your Amazon IoT Events detector models, allowing you to execute complex logic, interact with external services, and implement sophisticated event handling.

Amazon IoT Events uses a Lambda function to manage alarm notifications. You can use the Lambda function provided by Amazon IoT Events or create a new one.

Note

The alarm notifications feature isn't available in the China (Beijing) Region.

Topics

- [Creating a Lambda function in Amazon IoT Events](#)
- [Using the Lambda function provided by Amazon IoT Events](#)
- [Manage IAM Identity Center access of alarm recipients in Amazon IoT Events](#)

Creating a Lambda function in Amazon IoT Events

Amazon IoT Events provides a Lambda function that enables alarms to send and receive email and SMS notifications.

Requirements

The following requirements apply when you create a Lambda function for alarms:

- If your alarm sends SMS notifications, ensure Amazon SNS is configured to deliver SMS messages.
-
- If your alarm sends email or SMS notifications, you must have an IAM role that allows Amazon Lambda to work with Amazon SES and Amazon SNS.

Example policy:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "ses:GetIdentityVerificationAttributes",
        "ses:SendEmail",
        "ses:VerifyEmailIdentity"
      ],
      "Resource": "*"
    },
    {
      "Effect": "Allow",
      "Action": [
        "sns:Publish",
        "sns:OptInPhoneNumber",
        "sns:CheckIfPhoneNumberIsOptedOut",
        "sms-voice:DescribeOptedOutNumbers"
      ],
      "Resource": "*"
    },
    {
      "Effect": "Deny",
      "Action": "sns:Publish",
      "Resource": "arn:aws-cn:sns:*:*:*"
    },
    {
      "Effect" : "Allow",
      "Action" : [
        "logs:CreateLogGroup",
        "logs:CreateLogStream",
        "logs:PutLogEvents"
      ],
      "Resource" : "*"
    }
  ]
}
```

- You must choose the same Amazon Region for both Amazon IoT Events and Amazon Lambda. For the list of supported Regions, see [Amazon IoT Events endpoints and quotas](#) and [Amazon Lambda endpoints and quotas](#) in the *Amazon Web Services General Reference*.

Deploy a Lambda function for Amazon IoT Events using Amazon CloudFormation

This tutorial uses an Amazon CloudFormation template to deploy a Lambda function. This template automatically creates an IAM role that allows the Lambda function to work with Amazon SES and Amazon SNS.

The following shows you how to use the Amazon Command Line Interface (Amazon CLI) to create a CloudFormation stack.

1. In your device's terminal, run `aws --version` to check if you installed the Amazon CLI. For more information, see [Installing or updating to the latest version of the Amazon CLI](#) in the *Amazon Command Line Interface User Guide*.
2. Run `aws configure list` to check if you configured the Amazon CLI in the Amazon Region that has all your Amazon resources for this tutorial. For more information, see [Set and view configuration settings using commands](#) in the *Amazon Command Line Interface User Guide*.
3. Download the CloudFormation template, [notificationLambda.template.yaml.zip](#).

Note

If you have difficulty downloading the file, the template is also available in the [CloudFormation template](#).

4. Unzip the content and save it locally as `notificationLambda.template.yaml`.
5. Open a terminal on your device and navigate to the directory where you downloaded the `notificationLambda.template.yaml` file.
6. To create a CloudFormation stack, run the following command:

```
aws cloudformation create-stack --stack-name notificationLambda-stack --template-body file://notificationLambda.template.yaml --capabilities CAPABILITY_IAM
```

You might modify this CloudFormation template to customize the Lambda function and its behavior.

Note

Amazon Lambda retries function errors twice. If the function doesn't have enough capacity to handle all incoming requests, events might wait in the queue for hours or days to be sent to the function. You can configure an undelivered-message queue (DLQ) on the function to capture events that weren't successfully processed. For more information, see [Asynchronous invocation](#) in the *Amazon Lambda Developer Guide*.

You can also create or configure the stack in the CloudFormation console. For more information, see [Working with stacks](#), in the *Amazon CloudFormation User Guide*.

Creating a custom Lambda function for Amazon IoT Events

You can create a Lambda function or modify the one provided by Amazon IoT Events.

The following requirements apply when you create a custom Lambda function.

- Add permissions that allow your Lambda function to perform specified actions and access Amazon resources.
- If you use the Lambda function provided by Amazon IoT Events, make sure that you choose the Python 3.7 runtime.

Example Lambda function:

```
import boto3
import json
import logging
import datetime
logger = logging.getLogger()
logger.setLevel(logging.INFO)
ses = boto3.client('ses')
sns = boto3.client('sns')
def check_value(target):
    if target:
        return True
    return False

# Check whether email is verified. Only verified emails are allowed to send emails to
or from.
```

```

def check_email(email):
    if not check_value(email):
        return False
    result = ses.get_identity_verification_attributes(Identities=[email])
    attr = result['VerificationAttributes']
    if (email not in attr or attr[email]['VerificationStatus'] != 'Success'):
        logging.info('Verification email for {} sent. You must have all the emails
verified before sending email.'.format(email))
        ses.verify_email_identity(EmailAddress=email)
        return False
    return True

# Check whether the phone holder has opted out of receiving SMS messages from your
account
def check_phone_number(phone_number):
    try:
        result = sns.check_if_phone_number_is_opted_out(phoneNumber=phone_number)
        if (result['isOptedOut']):
            logger.info('phoneNumber {} is not opt in of receiving SMS messages. Phone
number must be opt in first.'.format(phone_number))
            return False
        return True
    except Exception as e:
        logging.error('Your phone number {} must be in E.164 format in SS0. Exception
thrown: {}'.format(phone_number, e))
        return False

def check_emails(emails):
    result = True
    for email in emails:
        if not check_email(email):
            result = False
    return result

def lambda_handler(event, context):
    logging.info('Received event: ' + json.dumps(event))
    nep = json.loads(event.get('notificationEventPayload'))
    alarm_state = nep['alarmState']
    default_msg = 'Alarm ' + alarm_state['stateName'] + '\n'
    timestamp =
datetime.datetime.utcnow().timestamp(float(nep['stateUpdateTime'])/1000).strftime('%Y-
%m-%d %H:%M:%S')
    alarm_msg = "{} {} {} at {} UTC ".format(nep['alarmModelName'], nep.get('keyValue',
'Singleton'), alarm_state['stateName'], timestamp)

```

```
default_msg += 'Sev: ' + str(nep['severity']) + '\n'
if (alarm_state['ruleEvaluation']):
    property = alarm_state['ruleEvaluation']['simpleRule']['inputProperty']
    default_msg += 'Current Value: ' + str(property) + '\n'
    operator = alarm_state['ruleEvaluation']['simpleRule']['operator']
    threshold = alarm_state['ruleEvaluation']['simpleRule']['threshold']
    alarm_msg += '({} {} {})'.format(str(property), operator, str(threshold))
default_msg += alarm_msg + '\n'

emails = event.get('emailConfigurations', [])
logger.info('Start Sending Emails')
for email in emails:
    from_adr = email.get('from')
    to_adrs = email.get('to', [])
    cc_adrs = email.get('cc', [])
    bcc_adrs = email.get('bcc', [])
    msg = default_msg + '\n' + email.get('additionalMessage', '')
    subject = email.get('subject', alarm_msg)
    fa_ver = check_email(from_adr)
    tas_ver = check_emails(to_adrs)
    ccas_ver = check_emails(cc_adrs)
    bccas_ver = check_emails(bcc_adrs)
    if (fa_ver and tas_ver and ccas_ver and bccas_ver):
        ses.send_email(Source=from_adr,
                       Destination={'ToAddresses': to_adrs, 'CcAddresses': cc_adrs,
'BccAddresses': bcc_adrs},
                       Message={'Subject': {'Data': subject}, 'Body': {'Text': {'Data':
msg}}}))
        logger.info('Emails have been sent')

logger.info('Start Sending SNS message to SMS')
sns_configs = event.get('smsConfigurations', [])
for sns_config in sns_configs:
    sns_msg = default_msg + '\n' + sns_config.get('additionalMessage', '')
    phone_numbers = sns_config.get('phoneNumbers', [])
    sender_id = sns_config.get('senderId')
    for phone_number in phone_numbers:
        if check_phone_number(phone_number):
            if check_value(sender_id):
                sns.publish(PhoneNumber=phone_number, Message=sns_msg,
MessageAttributes={'AWS.SNS.SMS.SenderID':{'DataType': 'String', 'StringValue':
sender_id}})
            else:
                sns.publish(PhoneNumber=phone_number, Message=sns_msg)
```

```
logger.info('SNS messages have been sent')
```

For more information, see [What is Amazon Lambda?](#) in the *Amazon Lambda Developer Guide*.

CloudFormation template

Use the following CloudFormation template to create your Lambda function.

```
AWSTemplateFormatVersion: '2010-09-09'
Description: 'Notification Lambda for Alarm Model'
Resources:
  NotificationLambdaRole:
    Type: AWS::IAM::Role
    Properties:
      AssumeRolePolicyDocument:
        Statement:
          - Effect: Allow
            Principal:
              Service: lambda.amazonaws.com
            Action: sts:AssumeRole
      Path: "/"
      ManagedPolicyArns:
        - 'arn:aws-cn:iam::aws:policy/AWSLambdaExecute'
    Policies:
      - PolicyName: "NotificationLambda"
        PolicyDocument:
          Version: "2012-10-17"
          Statement:
            - Effect: "Allow"
              Action:
                - "ses:GetIdentityVerificationAttributes"
                - "ses:SendEmail"
                - "ses:VerifyEmailIdentity"
              Resource: "*"
            - Effect: "Allow"
              Action:
                - "sns:Publish"
                - "sns:OptInPhoneNumber"
                - "sns:CheckIfPhoneNumberIsOptedOut"
                - "sms-voice:DescribeOptedOutNumbers"
              Resource: "*"
            - Effect: "Deny"
              Action:
                - "sns:Publish"
```

```
Resource: "arn:aws-cn:sns:*:*:*"
NotificationLambdaFunction:
  Type: AWS::Lambda::Function
  Properties:
    Role: !GetAtt NotificationLambdaRole.Arn
    Runtime: python3.7
    Handler: index.lambda_handler
    Timeout: 300
    MemorySize: 3008
    Code:
      ZipFile: |
        import boto3
        import json
        import logging
        import datetime
        logger = logging.getLogger()
        logger.setLevel(logging.INFO)
        ses = boto3.client('ses')
        sns = boto3.client('sns')
        def check_value(target):
            if target:
                return True
            return False

        # Check whether email is verified. Only verified emails are allowed to send
        emails to or from.
        def check_email(email):
            if not check_value(email):
                return False
            result = ses.get_identity_verification_attributes(Identities=[email])
            attr = result['VerificationAttributes']
            if (email not in attr or attr[email]['VerificationStatus'] != 'Success'):
                logging.info('Verification email for {} sent. You must have all the
                emails verified before sending email.'.format(email))
                ses.verify_email_identity(EmailAddress=email)
                return False
            return True

        # Check whether the phone holder has opted out of receiving SMS messages from
        your account
        def check_phone_number(phone_number):
            try:
                result = sns.check_if_phone_number_is_opted_out(phoneNumber=phone_number)
                if (result['isOptedOut']):
```

```

        logger.info('phoneNumber {} is not opt in of receiving SMS messages.
Phone number must be opt in first.'.format(phone_number))
        return False
    return True
except Exception as e:
    logging.error('Your phone number {} must be in E.164 format in SS0.
Exception thrown: {}'.format(phone_number, e))
    return False

def check_emails(emails):
    result = True
    for email in emails:
        if not check_email(email):
            result = False
    return result

def lambda_handler(event, context):
    logging.info('Received event: ' + json.dumps(event))
    nep = json.loads(event.get('notificationEventPayload'))
    alarm_state = nep['alarmState']
    default_msg = 'Alarm ' + alarm_state['stateName'] + '\n'
    timestamp =
datetime.datetime.utcnow().timestamp(float(nep['stateUpdateTime']/1000)).strftime('%Y-
%m-%d %H:%M:%S')
    alarm_msg = "{} {} {} at {} UTC ".format(nep['alarmModelName'],
nep.get('keyValue', 'Singleton'), alarm_state['stateName'], timestamp)
    default_msg += 'Sev: ' + str(nep['severity']) + '\n'
    if (alarm_state['ruleEvaluation']):
        property = alarm_state['ruleEvaluation']['simpleRule']['inputProperty']
        default_msg += 'Current Value: ' + str(property) + '\n'
        operator = alarm_state['ruleEvaluation']['simpleRule']['operator']
        threshold = alarm_state['ruleEvaluation']['simpleRule']['threshold']
        alarm_msg += '({} {} {})'.format(str(property), operator, str(threshold))
    default_msg += alarm_msg + '\n'

    emails = event.get('emailConfigurations', [])
    logger.info('Start Sending Emails')
    for email in emails:
        from_addr = email.get('from')
        to_addrs = email.get('to', [])
        cc_addrs = email.get('cc', [])
        bcc_addrs = email.get('bcc', [])
        msg = default_msg + '\n' + email.get('additionalMessage', '')
        subject = email.get('subject', alarm_msg)

```

```
fa_ver = check_email(from_adr)
tas_ver = check_emails(to_adrs)
ccas_ver = check_emails(cc_adrs)
bccas_ver = check_emails(bcc_adrs)
if (fa_ver and tas_ver and ccas_ver and bccas_ver):
    ses.send_email(Source=from_adr,
                   Destination={'ToAddresses': to_adrs, 'CcAddresses':
cc_adrs, 'BccAddresses': bcc_adrs},
                   Message={'Subject': {'Data': subject}, 'Body': {'Text':
{'Data': msg}}})
    logger.info('Emails have been sent')

logger.info('Start Sending SNS message to SMS')
sns_configs = event.get('smsConfigurations', [])
for sns_config in sns_configs:
    sns_msg = default_msg + '\n' + sns_config.get('additionalMessage', '')
    phone_numbers = sns_config.get('phoneNumbers', [])
    sender_id = sns_config.get('senderId')
    for phone_number in phone_numbers:
        if check_phone_number(phone_number):
            if check_value(sender_id):
                sns.publish(PhoneNumber=phone_number, Message=sns_msg,
MessageAttributes={'AWS.SNS.SMS.SenderID':{'DataType': 'String', 'StringValue':
sender_id}})
            else:
                sns.publish(PhoneNumber=phone_number, Message=sns_msg)
    logger.info('SNS messages have been sent')
```

Using the Lambda function provided by Amazon IoT Events

With alarm notifications, you can use the Lambda function provided by Amazon IoT Events for managing alarm notifications.

The following requirements apply when you use the Lambda function provided by Amazon IoT Events to manage your alarm notifications:

- You must verify the email address that sends the email notifications in Amazon Simple Email Service (Amazon SES). For more information, see [Verifying an email address identity](#), in the *Amazon Simple Email Service Developer Guide*.

If you receive a verification link, click the link to verify your email address. You might also check your spam folder for a verification email.

- If your alarm sends SMS notifications, you must use E.164 international phone number formatting for phone numbers. This format contains `+<country-calling-code><area-code><phone-number>`.

Example phone numbers:

Country	Local phone number	E.164 formatted number
United States	206-555-0100	+12065550100
United Kingdom	020-1234-1234	+442012341234
Lithuania	8+601+12345	+37060112345

To find a country calling code, go to countrycode.org.

The Lambda function provided by Amazon IoT Events checks if you use E.164 formatted phone numbers. However, it doesn't verify the phone numbers. If you ensure that you entered accurate phone numbers but didn't receive SMS notifications, you might contact the phone carriers. The carriers may block the messages.

Manage IAM Identity Center access of alarm recipients in Amazon IoT Events

Amazon IoT Events uses Amazon IAM Identity Center to manage the SSO access of alarms recipients. Implementing IAM Identity Center for Amazon IoT Events notification recipients can enhance security and user experience. To enable the alarm to send notifications to the recipients, you must enable IAM Identity Center and add recipients to your IAM Identity Center store. For more information, see [Add Users](#) in *Amazon IAM Identity Center User Guide*.

Important

- You must choose the same Amazon Region for Amazon IoT Events, Amazon Lambda, and IAM Identity Center.
- Amazon Organizations only supports one IAM Identity Center Region at a time. If you want to make IAM Identity Center available in a different Region, you must first delete

your current IAM Identity Center configuration. For more information, see [IAM Identity Center Region Data](#) in *Amazon IAM Identity Center User Guide*.

Security in Amazon IoT Events

Cloud security at Amazon is the highest priority. As an Amazon customer, you benefit from a data center and network architecture that is built to meet the requirements of the most security-sensitive organizations.

Security is a shared responsibility between Amazon and you. The [shared responsibility model](#) describes this as security *of* the cloud and security *in* the cloud:

- **Security of the cloud** – Amazon is responsible for protecting the infrastructure that runs Amazon services in the Amazon Cloud. Amazon also provides you with services that you can use securely. The effectiveness of our security is regularly tested and verified by third-party auditors as part of the [Amazon compliance programs](#). To learn about the compliance programs that apply to Amazon IoT Events, see [Amazon services in scope by compliance program](#).
- **Security in the cloud** – Your responsibility is determined by the Amazon service that you use. You are also responsible for other factors including the sensitivity of your data, your organization's requirements, and applicable laws and regulations.

This documentation will help you understand how to apply the shared responsibility model when using Amazon IoT Events. The following topics show you how to configure Amazon IoT Events to meet your security and compliance objectives. You'll also learn how to use other Amazon services that can help you to monitor and secure your Amazon IoT Events resources.

Topics

- [Identity and access management for Amazon IoT Events](#)
- [Monitoring Amazon IoT Events to maintain reliability, availability, and performance](#)
- [Compliance validation for Amazon IoT Events](#)
- [Resilience in Amazon IoT Events](#)
- [Infrastructure security in Amazon IoT Events](#)

Identity and access management for Amazon IoT Events

Amazon Identity and Access Management (IAM) is an Amazon service that helps an administrator securely control access to Amazon resources. IAM administrators control who can be *authenticated*

(signed in) and *authorized* (have permissions) to use Amazon IoT Events resources. IAM is an Amazon service that you can use with no additional charge.

Topics

- [Audience](#)
- [Authenticating with identities](#)
- [Managing access using policies](#)
- [More about identity and access management](#)
- [How Amazon IoT Events works with IAM](#)
- [Amazon IoT Events identity-based policy examples](#)
- [Cross-service confused deputy prevention for Amazon IoT Events](#)
- [Troubleshoot Amazon IoT Events identity and access](#)

Audience

How you use Amazon Identity and Access Management (IAM) differs, depending on the work that you do in Amazon IoT Events.

Service user – If you use the Amazon IoT Events service to do your job, then your administrator provides you with the credentials and permissions that you need. As you use more Amazon IoT Events features to do your work, you might need additional permissions. Understanding how access is managed can help you request the right permissions from your administrator. If you cannot access a feature in Amazon IoT Events, see [Troubleshoot Amazon IoT Events identity and access](#).

Service administrator – If you're in charge of Amazon IoT Events resources at your company, you probably have full access to Amazon IoT Events. It's your job to determine which Amazon IoT Events features and resources your service users should access. You must then submit requests to your IAM administrator to change the permissions of your service users. Review the information on this page to understand the basic concepts of IAM. To learn more about how your company can use IAM with Amazon IoT Events, see [How Amazon IoT Events works with IAM](#).

IAM administrator – If you're an IAM administrator, you might want to learn details about how you can write policies to manage access to Amazon IoT Events. To view example Amazon IoT Events identity-based policies that you can use in IAM, see [Amazon IoT Events identity-based policy examples](#).

Authenticating with identities

Authentication is how you sign in to Amazon using your identity credentials. You must be *authenticated* (signed in to Amazon) as the Amazon Web Services account root user, as an IAM user, or by assuming an IAM role.

If you access Amazon programmatically, Amazon provides a software development kit (SDK) and a command line interface (CLI) to cryptographically sign your requests by using your credentials. If you don't use Amazon tools, you must sign requests yourself. For more information about using the recommended method to sign requests yourself, see [Amazon Signature Version 4 for API requests](#) in the *IAM User Guide*.

Regardless of the authentication method that you use, you might be required to provide additional security information. For example, Amazon recommends that you use multi-factor authentication (MFA) to increase the security of your account. To learn more, see [Amazon Multi-factor authentication in IAM](#) in the *IAM User Guide*.

Amazon Web Services account root user

When you create an Amazon Web Services account, you begin with one sign-in identity that has complete access to all Amazon Web Services services and resources in the account. This identity is called the Amazon Web Services account *root user* and is accessed by signing in with the email address and password that you used to create the account. We strongly recommend that you don't use the root user for your everyday tasks. Safeguard your root user credentials and use them to perform the tasks that only the root user can perform. For the complete list of tasks that require you to sign in as the root user, see [Tasks that require root user credentials](#) in the *IAM User Guide*.

IAM users and groups

An [IAM user](#) is an identity within your Amazon Web Services account that has specific permissions for a single person or application. Where possible, we recommend relying on temporary credentials instead of creating IAM users who have long-term credentials such as passwords and access keys. However, if you have specific use cases that require long-term credentials with IAM users, we recommend that you rotate access keys. For more information, see [Rotate access keys regularly for use cases that require long-term credentials](#) in the *IAM User Guide*.

An [IAM group](#) is an identity that specifies a collection of IAM users. You can't sign in as a group. You can use groups to specify permissions for multiple users at a time. Groups make permissions easier to manage for large sets of users. For example, you could have a group named *IAMAdmins* and give that group permissions to administer IAM resources.

Users are different from roles. A user is uniquely associated with one person or application, but a role is intended to be assumable by anyone who needs it. Users have permanent long-term credentials, but roles provide temporary credentials. To learn more, see [Use cases for IAM users](#) in the *IAM User Guide*.

IAM roles

An [IAM role](#) is an identity within your Amazon Web Services account that has specific permissions. It is similar to an IAM user, but is not associated with a specific person. To temporarily assume an IAM role in the Amazon Web Services Management Console, you can [switch from a user to an IAM role \(console\)](#). You can assume a role by calling an Amazon CLI or Amazon API operation or by using a custom URL. For more information about methods for using roles, see [Methods to assume a role](#) in the *IAM User Guide*.

IAM roles with temporary credentials are useful in the following situations:

- **Federated user access** – To assign permissions to a federated identity, you create a role and define permissions for the role. When a federated identity authenticates, the identity is associated with the role and is granted the permissions that are defined by the role. For information about roles for federation, see [Create a role for a third-party identity provider \(federation\)](#) in the *IAM User Guide*.
- **Temporary IAM user permissions** – An IAM user or role can assume an IAM role to temporarily take on different permissions for a specific task.
- **Cross-account access** – You can use an IAM role to allow someone (a trusted principal) in a different account to access resources in your account. Roles are the primary way to grant cross-account access. However, with some Amazon Web Services services, you can attach a policy directly to a resource (instead of using a role as a proxy). To learn the difference between roles and resource-based policies for cross-account access, see [Cross account resource access in IAM](#) in the *IAM User Guide*.
- **Cross-service access** – Some Amazon Web Services services use features in other Amazon Web Services services. For example, when you make a call in a service, it's common for that service to run applications in Amazon EC2 or store objects in Amazon S3. A service might do this using the calling principal's permissions, using a service role, or using a service-linked role.
 - **Forward access sessions (FAS)** – When you use an IAM user or role to perform actions in Amazon, you are considered a principal. When you use some services, you might perform an action that then initiates another action in a different service. FAS uses the permissions of the principal calling an Amazon Web Services service, combined with the requesting Amazon Web

Services service to make requests to downstream services. FAS requests are only made when a service receives a request that requires interactions with other Amazon Web Services services or resources to complete. In this case, you must have permissions to perform both actions. For policy details when making FAS requests, see [Forward access sessions](#).

- **Service role** – A service role is an [IAM role](#) that a service assumes to perform actions on your behalf. An IAM administrator can create, modify, and delete a service role from within IAM. For more information, see [Create a role to delegate permissions to an Amazon Web Services service](#) in the *IAM User Guide*.
- **Service-linked role** – A service-linked role is a type of service role that is linked to an Amazon Web Services service. The service can assume the role to perform an action on your behalf. Service-linked roles appear in your Amazon Web Services account and are owned by the service. An IAM administrator can view, but not edit the permissions for service-linked roles.
- **Applications running on Amazon EC2** – You can use an IAM role to manage temporary credentials for applications that are running on an EC2 instance and making Amazon CLI or Amazon API requests. This is preferable to storing access keys within the EC2 instance. To assign an Amazon role to an EC2 instance and make it available to all of its applications, you create an instance profile that is attached to the instance. An instance profile contains the role and enables programs that are running on the EC2 instance to get temporary credentials. For more information, see [Use an IAM role to grant permissions to applications running on Amazon EC2 instances](#) in the *IAM User Guide*.

Managing access using policies

You control access in Amazon by creating policies and attaching them to Amazon identities or resources. A policy is an object in Amazon that, when associated with an identity or resource, defines their permissions. Amazon evaluates these policies when a principal (user, root user, or role session) makes a request. Permissions in the policies determine whether the request is allowed or denied. Most policies are stored in Amazon as JSON documents. For more information about the structure and contents of JSON policy documents, see [Overview of JSON policies](#) in the *IAM User Guide*.

Administrators can use Amazon JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

By default, users and roles have no permissions. To grant users permission to perform actions on the resources that they need, an IAM administrator can create IAM policies. The administrator can then add the IAM policies to roles, and users can assume the roles.

IAM policies define permissions for an action regardless of the method that you use to perform the operation. For example, suppose that you have a policy that allows the `iam:GetRole` action. A user with that policy can get role information from the Amazon Web Services Management Console, the Amazon CLI, or the Amazon API.

Identity-based policies

Identity-based policies are JSON permissions policy documents that you can attach to an identity, such as an IAM user, group of users, or role. These policies control what actions users and roles can perform, on which resources, and under what conditions. To learn how to create an identity-based policy, see [Define custom IAM permissions with customer managed policies](#) in the *IAM User Guide*.

Identity-based policies can be further categorized as *inline policies* or *managed policies*. Inline policies are embedded directly into a single user, group, or role. Managed policies are standalone policies that you can attach to multiple users, groups, and roles in your Amazon Web Services account. Managed policies include Amazon managed policies and customer managed policies. To learn how to choose between a managed policy or an inline policy, see [Choose between managed policies and inline policies](#) in the *IAM User Guide*.

Other policy types

Amazon supports additional, less-common policy types. These policy types can set the maximum permissions granted to you by the more common policy types.

- **Permissions boundaries** – A permissions boundary is an advanced feature in which you set the maximum permissions that an identity-based policy can grant to an IAM entity (IAM user or role). You can set a permissions boundary for an entity. The resulting permissions are the intersection of an entity's identity-based policies and its permissions boundaries. Resource-based policies that specify the user or role in the `Principal` field are not limited by the permissions boundary. An explicit deny in any of these policies overrides the allow. For more information about permissions boundaries, see [Permissions boundaries for IAM entities](#) in the *IAM User Guide*.
- **Service control policies (SCPs)** – SCPs are JSON policies that specify the maximum permissions for an organization or organizational unit (OU) in Amazon Organizations. Amazon Organizations is a service for grouping and centrally managing multiple Amazon Web Services accounts that your business owns. If you enable all features in an organization, then you can apply service control policies (SCPs) to any or all of your accounts. The SCP limits permissions for entities in member accounts, including each Amazon Web Services account root user. For more information about Organizations and SCPs, see [Service control policies](#) in the *Amazon Organizations User Guide*.

- **Resource control policies (RCPs)** – RCPs are JSON policies that you can use to set the maximum available permissions for resources in your accounts without updating the IAM policies attached to each resource that you own. The RCP limits permissions for resources in member accounts and can impact the effective permissions for identities, including the Amazon Web Services account root user, regardless of whether they belong to your organization. For more information about Organizations and RCPs, including a list of Amazon Web Services services that support RCPs, see [Resource control policies \(RCPs\)](#) in the *Amazon Organizations User Guide*.
- **Session policies** – Session policies are advanced policies that you pass as a parameter when you programmatically create a temporary session for a role or federated user. The resulting session's permissions are the intersection of the user or role's identity-based policies and the session policies. Permissions can also come from a resource-based policy. An explicit deny in any of these policies overrides the allow. For more information, see [Session policies](#) in the *IAM User Guide*.

Multiple policy types

When multiple types of policies apply to a request, the resulting permissions are more complicated to understand. To learn how Amazon determines whether to allow a request when multiple policy types are involved, see [Policy evaluation logic](#) in the *IAM User Guide*.

More about identity and access management

For more information about identity and access management for Amazon IoT Events, continue to the following pages:

- [How Amazon IoT Events works with IAM](#)
- [Troubleshoot Amazon IoT Events identity and access](#)

How Amazon IoT Events works with IAM

Before you use IAM to manage access to Amazon IoT Events, you should understand what IAM features are available to use with Amazon IoT Events. To get a high-level view of how Amazon IoT Events and other Amazon services work with IAM, see [Amazon services that work with IAM](#) in the *IAM User Guide*.

Topics

- [Amazon IoT Events identity-based policies](#)

- [Amazon IoT Events resource-based policies](#)
- [Authorization based on Amazon IoT Events tags](#)
- [Amazon IoT Events IAM roles](#)

Amazon IoT Events identity-based policies

With IAM identity-based policies, you can specify allowed or denied actions and resources as well as the conditions under which actions are allowed or denied. Amazon IoT Events supports specific actions, resources, and condition keys. To learn about all of the elements that you use in a JSON policy, see [IAM JSON policy elements reference](#) in the *IAM User Guide*.

Actions

The `Action` element of an IAM identity-based policy describes the specific action or actions that will be allowed or denied by the policy. Policy actions usually have the same name as the associated Amazon API operation. The action is used in a policy to grant permissions to perform the associated operation.

Policy actions in Amazon IoT Events use the following prefix before the action: `iotevents:`. For example, to grant someone permission to create an Amazon IoT Events input with the Amazon IoT Events `CreateInput` API operation, you include the `iotevents:CreateInput` action in their policy. To grant someone permission to send an input with the Amazon IoT Events `BatchPutMessage` API operation, you include the `iotevents-data:BatchPutMessage` action in their policy. Policy statements must include either an `Action` or `NotAction` element. Amazon IoT Events defines its own set of actions that describe tasks that you can perform with this service.

To specify multiple actions in a single statement, separate them with commas as follows:

```
"Action": [
    "iotevents:action1",
    "iotevents:action2"
```

You can specify multiple actions using wildcards (*). For example, to specify all actions that begin with the word `Describe`, include the following action:

```
"Action": "iotevents:Describe*"
```

To see a list of Amazon IoT Events actions, see [Actions Defined by Amazon IoT Events](#) in the *IAM User Guide*.

Resources

The `Resource` element specifies the object or objects to which the action applies. Statements must include either a `Resource` or a `NotResource` element. You specify a resource using an ARN or using the wildcard (*) to indicate that the statement applies to all resources.

The Amazon IoT Events detector model resource has the following ARN:

```
arn:${Partition}:iotevents:${Region}:${Account}:detectorModel/${detectorModelName}
```

For more information about the format of ARNs, see [Identify Amazon resources with Amazon Resource Names \(ARNs\)](#).

For example, to specify the `Foobar` detector model in your statement, use the following ARN:

```
"Resource": "arn:aws-cn:iotevents:us-east-1:123456789012:detectorModel/Foobar"
```

To specify all instances that belong to a specific account, use the wildcard (*):

```
"Resource": "arn:aws-cn:iotevents:us-east-1:123456789012:detectorModel/*"
```

Some Amazon IoT Events actions, such as those for creating resources, cannot be performed on a specific resource. In those cases, you must use the wildcard (*).

```
"Resource": "*"
```

Some Amazon IoT Events API actions involve multiple resources. For example, `CreateDetectorModel` references inputs in its condition statements, so a user must have permissions to use the input and the detector model. To specify multiple resources in a single statement, separate the ARNs with commas.

```
"Resource": [  
    "resource1",  
    "resource2"
```

To see a list of Amazon IoT Events resource types and their ARNs, see [Resources Defined by Amazon IoT Events](#) in the *IAM User Guide*. To learn with which actions you can specify the ARN of each resource, see [Actions Defined by Amazon IoT Events](#).

Condition keys

The Condition element (or Condition *block*) lets you specify conditions in which a statement is in effect. The Condition element is optional. You can build conditional expressions that use [condition operators](#), such as equals or less than, to match the condition in the policy with values in the request.

If you specify multiple Condition elements in a statement, or multiple keys in a single Condition element, Amazon evaluates them using a logical AND operation. If you specify multiple values for a single condition key, Amazon evaluates the condition using a logical OR operation. All of the conditions must be met before the statement's permissions are granted.

You can also use placeholder variables when you specify conditions. For example, you can grant a user permission to access a resource only if it is tagged with their user name. For more information, see [IAM policy elements: Variables and tags](#) in the *IAM User Guide*.

Amazon IoT Events does not provide any service-specific condition keys, but it does support using some global condition keys. To see all Amazon global condition keys, see [Amazon global condition context keys](#) in the *IAM User Guide*."

Examples

To view examples of Amazon IoT Events identity-based policies, see [Amazon IoT Events identity-based policy examples](#).

Amazon IoT Events resource-based policies

Amazon IoT Events does not support resource-based policies." To view an example of a detailed resource-based policy page, see <https://docs.amazonaws.cn/lambda/latest/dg/access-control-resource-based.html>.

Authorization based on Amazon IoT Events tags

You can attach tags to Amazon IoT Events resources or pass tags in a request to Amazon IoT Events. To control access based on tags, you provide tag information in the [condition element](#)

of a policy using the `iotevents:ResourceTag/key-name`, `aws:RequestTag/key-name`, or `aws:TagKeys` condition keys. For more information about tagging Amazon IoT Events resources, see [Tagging your Amazon IoT Events resources](#).

To view an example identity-based policy for limiting access to a resource based on the tags on that resource, see [View Amazon IoT Events inputs based on tags](#).

Amazon IoT Events IAM roles

An [IAM role](#) is an entity within your Amazon Web Services account that has specific permissions.

Using temporary credentials with Amazon IoT Events

You can use temporary credentials to sign in with federation, assume an IAM role, or to assume a cross-account role. You obtain temporary security credentials by calling Amazon Security Token Service (Amazon STS) API operations such as [AssumeRole](#) or [GetFederationToken](#).

Amazon IoT Events does not support using temporary credentials.

Service-linked roles

[Service-linked roles](#) allow Amazon services to access resources in other services to complete an action on your behalf. Service-linked roles appear in your IAM account and are owned by the service. An IAM administrator can view but not edit the permissions for service-linked roles.

Amazon IoT Events does not support service-linked roles.

Service roles

This feature allows a service to assume a [service role](#) on your behalf. This role allows the service to access resources in other services to complete an action on your behalf. Service roles appear in your IAM account and are owned by the account. This means that an IAM administrator can change the permissions for this role. However, doing so might break the functionality of the service.

Amazon IoT Events supports service roles.

Amazon IoT Events identity-based policy examples

By default, users and roles don't have permission to create or modify Amazon IoT Events resources. They also can't perform tasks using the Amazon Web Services Management Console, Amazon CLI, or Amazon API. An IAM administrator must create IAM policies that grant users

and roles permission to perform specific API operations on the specified resources they need. The administrator must then attach those policies to the users or groups that require those permissions.

To learn how to create an IAM identity-based policy using these example JSON policy documents, see [Creating policies on the JSON tab](#) in the *IAM User Guide*.

Topics

- [Policy best practices](#)
- [Using the Amazon IoT Events console](#)
- [Allow users to view their own permissions in Amazon IoT Events](#)
- [Access one Amazon IoT Events input](#)
- [View Amazon IoT Events inputs based on tags](#)

Policy best practices

Identity-based policies are very powerful. They determine whether someone can create, access, or delete Amazon IoT Events resources in your account. These actions can incur costs for your Amazon Web Services account. When you create or edit identity-based policies, follow these guidelines and recommendations:

- **Get Started Using Amazon Managed Policies** – To start using Amazon IoT Events quickly, use Amazon managed policies to give your employees the permissions they need. These policies are already available in your account and are maintained and updated by Amazon. For more information, see [Get started using permissions with Amazon managed policies](#) in the *IAM User Guide*.
- **Grant Least Privilege** – When you create custom policies, grant only the permissions required to perform a task. Start with a minimum set of permissions and grant additional permissions as necessary. Doing so is more secure than starting with permissions that are too lenient and then trying to tighten them later. For more information, see [Grant least privilege](#) in the *IAM User Guide*.
- **Enable MFA for Sensitive Operations** – For extra security, require users to use multi-factor authentication (MFA) to access sensitive resources or API operations. For more information, see [Using multi-factor authentication \(MFA\) in Amazon](#) in the *IAM User Guide*.
- **Use Policy Conditions for Extra Security** – To the extent that it's practical, define the conditions under which your identity-based policies allow access to a resource. For example, you can write

conditions to specify a range of allowable IP addresses that a request must come from. You can also write conditions to allow requests only within a specified date or time range, or to require the use of SSL or MFA. For more information, see [IAM JSON policy elements: Condition](#) in the *IAM User Guide*.

Using the Amazon IoT Events console

To access the Amazon IoT Events console, you must have a minimum set of permissions. These permissions must allow you to list and view details about the Amazon IoT Events resources in your Amazon Web Services account. If you create an identity-based policy that is more restrictive than the minimum required permissions, the console won't function as intended for entities (users or roles) with that policy.

To ensure that those entities can still use the Amazon IoT Events console, also attach the following Amazon managed policy to the entities. For more information, see [Adding permissions to a user](#) in the *IAM User Guide*:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "iotevents-data:BatchPutMessage",
        "iotevents-data:BatchUpdateDetector",
        "iotevents:CreateDetectorModel",
        "iotevents:CreateInput",
        "iotevents>DeleteDetectorModel",
        "iotevents>DeleteInput",
        "iotevents-data:DescribeDetector",
        "iotevents:DescribeDetectorModel",
        "iotevents:DescribeInput",
        "iotevents:DescribeLoggingOptions",
        "iotevents:ListDetectorModelVersions",
        "iotevents:ListDetectorModels",
        "iotevents-data:ListDetectors",
        "iotevents:ListInputs",
        "iotevents:ListTagsForResource",
        "iotevents:PutLoggingOptions",
        "iotevents:TagResource",
        "iotevents:UntagResource",
      ]
    }
  ]
}
```

```

        "iotevents:UpdateDetectorModel",
        "iotevents:UpdateInput",
        "iotevents:UpdateInputRouting"
    ],
    "Resource": "arn:${Partition}:iotevents:${Region}:${Account}:detectorModel/
${detectorModelName}",
    "Resource": "arn:${Partition}:iotevents:${Region}:${Account}:input/
${inputName}"
    }
]
}

```

You don't need to allow minimum console permissions for users that are making calls only to the Amazon CLI or the Amazon API. Instead, allow access to only the actions that match the API operation that you're trying to perform.

Allow users to view their own permissions in Amazon IoT Events

This example shows how you might create a policy that allows users to view the inline and managed policies that are attached to their user identity. Allowing users to view their own IAM permissions is useful for security awareness and self-service capabilities. This policy includes permissions to complete this action on the console or programmatically using the Amazon CLI or Amazon API.

```

{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "ViewOwnUserInfo",
      "Effect": "Allow",
      "Action": [
        "iam:GetUserPolicy",
        "iam:ListGroupsForUser",
        "iam:ListAttachedUserPolicies",
        "iam:ListUserPolicies",
        "iam:GetUser"
      ],
      "Resource": [
        "arn:aws-cn:iam::*:user/${aws:username}"
      ]
    },
    {

```

```

        "Sid": "NavigateInConsole",
        "Effect": "Allow",
        "Action": [
            "iam:GetGroupPolicy",
            "iam:GetPolicyVersion",
            "iam:GetPolicy",
            "iam:ListAttachedGroupPolicies",
            "iam:ListGroupPolicies",
            "iam:ListPolicyVersions",
            "iam:ListPolicies",
            "iam:ListUsers"
        ],
        "Resource": "*"
    }
]
}

```

Access one Amazon IoT Events input

Granular access control to Amazon IoT Events inputs is important for maintaining security in multi-user or multi-team environments. This section shows how to create IAM policies that grant access to specific Amazon IoT Events inputs while restricting access to others.

In this example, you can grant a user in your Amazon Web Services account access to one of your Amazon IoT Events inputs, `exampleInput`. You also can allow the user to add, update, and delete inputs.

The policy grants the `iotevents:ListInputs`, `iotevents:DescribeInput`, `iotevents>CreateInput`, `iotevents>DeleteInput`, and `iotevents:UpdateInput` permissions to the user. For an example walkthrough for the Amazon Simple Storage Service (Amazon S3) that grants permissions to users and tests them using the console, see [Controlling access to a bucket with user policies](#).

```

{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "ListInputsInConsole",
      "Effect": "Allow",
      "Action": [
        "iotevents:ListInputs"
      ],
    }
  ],
}

```



```

    "Resource": "arn:aws-cn:iotevents:::*"
  },
  {
    "Sid": "ViewSpecificInputInfo",
    "Effect": "Allow",
    "Action": [
      "iotevents:DescribeInput"
    ],
    "Resource": "arn:aws-cn:iotevents:::exampleInput"
  },
  {
    "Sid": "ManageInputs",
    "Effect": "Allow",
    "Action": [
      "iotevents:CreateInput",
      "iotevents>DeleteInput",
      "iotevents:DescribeInput",
      "iotevents:ListInputs",
      "iotevents:UpdateInput"
    ],
    "Resource": "arn:aws-cn:iotevents:::exampleInput/*"
  }
]
}

```

View Amazon IoT Events inputs based on tags

Tags help you organize Amazon IoT Events resources. You can use conditions in your identity-based policy to control access to Amazon IoT Events resources based on tags. This example shows how you might create a policy that allows viewing an *input*. However, permission is granted only if the *input* tag `Owner` has the value of that user's user name. This policy also grants the permissions necessary to complete this action on the console.

```

{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "ListInputsInConsole",
      "Effect": "Allow",
      "Action": "iotevents:ListInputs",
      "Resource": "*"
    },
    {

```

```
    "Sid": "ViewInputsIfOwner",
    "Effect": "Allow",
    "Action": "iotevents:ListInputs",
    "Resource": "arn:aws-cn:iotevents:*:*:input/*",
    "Condition": {
      "StringEquals": {"aws:ResourceTag/Owner": "${aws:username}"}
    }
  ]
}
```

You can attach this policy to the users in your account. If a user named `richard-roe` attempts to view an Amazon IoT Events *input*, the *input* must be tagged `Owner=richard-roe` or `owner=richard-roe`. Otherwise he is denied access. The condition tag key `Owner` matches both `Owner` and `owner` because condition key names are not case-sensitive. For more information, see [IAM JSON policy elements: Condition](#) in the *IAM User Guide*.

Cross-service confused deputy prevention for Amazon IoT Events

Note

- The Amazon IoT Events service only allows you to use roles to start actions in the same account in which a resource was created. This helps prevent a confused deputy attack in Amazon IoT Events.
- This page serves as a reference for you to see how the confused deputy issue works and can be prevented in the event that cross account resources were allowed in the Amazon IoT Events service.

The confused deputy problem is a security issue where an entity that doesn't have permission to perform an action can coerce a more-privileged entity to perform the action. In Amazon, cross-service impersonation can result in the confused deputy problem.

Cross-service impersonation can occur when one service (the *calling service*) calls another service (the *called service*). The calling service can be manipulated to use its permissions to act on another customer's resources in a way it should not otherwise have permission to access. To prevent this, Amazon provides tools that help you protect your data for all services with service principals that have been given access to resources in your account.

We recommend using the [aws:SourceArn](#) and [aws:SourceAccount](#) global condition context keys in resource policies to limit the permissions that Amazon IoT Events gives another service to the resource. If the `aws:SourceArn` value does not contain the account ID, such as an Amazon S3 bucket ARN, you must use both global condition context keys to limit permissions. If you use both global condition context keys and the `aws:SourceArn` value contains the account ID, the `aws:SourceAccount` value and the account in the `aws:SourceArn` value must use the same account ID when used in the same policy statement.

Use `aws:SourceArn` if you want only one resource to be associated with the cross-service access. Use `aws:SourceAccount` if you want to allow any resource in that account to be associated with the cross-service use. The value of `aws:SourceArn` must be the Detector Model or Alarm model associated with the `sts:AssumeRole` request.

The most effective way to protect against the confused deputy problem is to use the `aws:SourceArn` global condition context key with the full ARN of the resource. If you don't know the full ARN of the resource or if you are specifying multiple resources, use the `aws:SourceArn` global context condition key with wildcards (*) for the unknown portions of the ARN. For example, `arn:aws-cn:iotevents:*:123456789012:*`.

The following examples show how you can use the `aws:SourceArn` and `aws:SourceAccount` global condition context keys in Amazon IoT Events to prevent the confused deputy problem.

Topics

- [Example: Secure access to an Amazon IoT Events detector model](#)
- [Example: Secure access to an Amazon IoT Events alarm model](#)
- [Example: Access an Amazon IoT Events resource in a specified region](#)
- [Example: Configure logging options for Amazon IoT Events](#)

Example: Secure access to an Amazon IoT Events detector model

This example demonstrates how to create an IAM policy that securely grants access to a specific detector model in Amazon IoT Events. The policy uses conditions to ensure that only the specified Amazon account and Amazon IoT Events service can assume the role, adding an extra layer of security. In this example, the role can only access the detector model named `WindTurbine01`.

```
{  
  "Version": "2012-10-17",
```

```
"Statement": [  
  {  
    "Effect": "Allow",  
    "Principal": {  
      "Service": [  
        "iotevents.amazonaws.com"  
      ]  
    },  
    "Action": "sts:AssumeRole",  
    "Condition": {  
      "StringEquals": {  
        "aws:SourceAccount": "account_id"  
      },  
      "ArnEquals": {  
        "aws:SourceArn":  
"arn:aws:iotevents:region:account_id:detectorModel/WindTurbine01"  
      }  
    }  
  }  
]
```

Example: Secure access to an Amazon IoT Events alarm model

This example demonstrates how to create an IAM policy that allows Amazon IoT Events to securely access alarm models. The policy uses conditions to ensure that only the specified Amazon account and Amazon IoT Events service can assume the role.

In this example, the role can access any alarm model within the specified Amazon account, as indicated by the * wildcard in the alarm model ARN. The `aws:SourceAccount` and `aws:SourceArn` conditions work together to prevent the confused deputy problem.

```
{  
  "Version": "2012-10-17",  
  "Statement": [  
    {  
      "Effect": "Allow",  
      "Principal": {  
        "Service": [  
          "iotevents.amazonaws.com"  
        ]  
      },  
    }  
  ],  
}
```

```
    "Action": "sts:AssumeRole",
    "Condition": {
      "StringEquals": {
        "aws:SourceAccount": "account_id"
      },
      "ArnEquals": {
        "aws:SourceArn": "arn:aws:iotevents:region:account_id:alarmModel/*"
      }
    }
  }
]
```

Example: Access an Amazon IoT Events resource in a specified region

This example demonstrates how to configure an IAM role to access Amazon IoT Events resources in a specific Amazon region. By using region-specific ARNs in your IAM policies, you can restrict access to Amazon IoT Events resources across different geographical areas. This approach can help maintain security and compliance in multi-region deployments. The region in this example is *us-east-1*.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "Service": [
          "iotevents.amazonaws.com"
        ]
      },
      "Action": "sts:AssumeRole",
      "Condition": {
        "StringEquals": {
          "aws:SourceAccount": "account_id"
        },
        "ArnEquals": {
          "aws:SourceArn": "arn:aws:iotevents:us-east-1:account_id:*"
        }
      }
    }
  ]
}
```

Example: Configure logging options for Amazon IoT Events

Proper logging is important for monitoring, debugging, and auditing your Amazon IoT Events applications. This section provides an overview of logging options available in Amazon IoT Events.

This example demonstrates how to configure an IAM role that allows Amazon IoT Events to log data to CloudWatch Logs. The use of wildcards (*) in the resource ARN allows for comprehensive logging across your Amazon IoT Events infrastructure.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "Service": [
          "iotevents.amazonaws.com"
        ]
      },
      "Action": "sts:AssumeRole",
      "Condition": {
        "StringEquals": {
          "aws:SourceAccount": "account_id"
        },
        "ArnEquals": {
          "aws:SourceArn": "arn:aws:iotevents:region:account_id:*"
        }
      }
    }
  ]
}
```

Troubleshoot Amazon IoT Events identity and access

Use the following information to help you diagnose and fix common issues that you might encounter when working with Amazon IoT Events and IAM.

Topics

- [I am not authorized to perform an action in Amazon IoT Events](#)

- [I am not authorized to perform iam:PassRole](#)
- [I want to allow people outside of my Amazon Web Services account to access my Amazon IoT Events resources](#)

I am not authorized to perform an action in Amazon IoT Events

If the Amazon Web Services Management Console tells you that you're not authorized to perform an action, then you must contact your administrator for assistance. Your administrator is the person that provided you with your user name and password.

The following example error occurs when the `mateojackson` IAM user tries to use the console to view details about a *input* but does not have `iotevents:ListInputs` permissions.

```
User: arn:aws-cn:iam::123456789012:user/mateojackson is not authorized to perform:
iotevents:ListInputs on resource: my-example-input
```

In this case, Mateo asks his administrator to update his policies to allow him to access the *my-example-input* resource using the `iotevents:ListInput` action.

I am not authorized to perform iam:PassRole

If you receive an error that you're not authorized to perform the `iam:PassRole` action, your policies must be updated to allow you to pass a role to Amazon IoT Events.

Some Amazon Web Services services allow you to pass an existing role to that service instead of creating a new service role or service-linked role. To do this, you must have permissions to pass the role to the service.

The following example error occurs when an IAM user named `marymajor` tries to use the console to perform an action in Amazon IoT Events. However, the action requires the service to have permissions that are granted by a service role. Mary does not have permissions to pass the role to the service.

```
User: arn:aws-cn:iam::123456789012:user/marymajor is not authorized to perform:
iam:PassRole
```

In this case, Mary's policies must be updated to allow her to perform the `iam:PassRole` action.

If you need help, contact your Amazon administrator. Your administrator is the person who provided you with your sign-in credentials.

I want to allow people outside of my Amazon Web Services account to access my Amazon IoT Events resources

You can create a role that users in other accounts or people outside of your organization can use to access your resources. You can specify who is trusted to assume the role. For services that support resource-based policies or access control lists (ACLs), you can use those policies to grant people access to your resources.

Consult the following topics to determine your best options:

- To learn whether Amazon IoT Events supports these features, see [How Amazon IoT Events works with IAM](#).
- To learn how to provide access to your resources across Amazon Web Services accounts that you own, see [Providing access to an IAM user in another Amazon Web Services account that you own](#) in the *IAM User Guide*.
- To learn how to provide access to your resources to third-party Amazon Web Services accounts, see [Providing access to Amazon Web Services accounts owned by third parties](#) in the *IAM User Guide*.
- To learn how to provide access through identity federation, see [Providing access to externally authenticated users \(identity federation\)](#) in the *IAM User Guide*.
- To learn the difference between using roles and resource-based policies for cross-account access, see [Cross account resource access in IAM](#) in the *IAM User Guide*.

Monitoring Amazon IoT Events to maintain reliability, availability, and performance

Monitoring is an important part of maintaining the reliability, availability, and performance of Amazon IoT Events and your Amazon solutions. You should collect monitoring data from all parts of your Amazon solution so that you can more easily debug a multi-point failure if one occurs. Before you start monitoring Amazon IoT Events, you should create a monitoring plan that includes answers to the following questions:

- What are your monitoring goals?

- Which resources will you monitor?
- How often will you monitor these resources?
- Which monitoring tools will you use?
- Who will perform the monitoring tasks?
- Who should be notified when something goes wrong?

The next step is to establish a baseline for normal Amazon IoT Events performance in your environment, by measuring performance at various times and under different load conditions. As you monitor Amazon IoT Events, store historical monitoring data so that you can compare it with current performance data, identify normal performance patterns and performance anomalies, and devise methods to address issues.

For example, if you're using Amazon EC2, you can monitor CPU utilization, disk I/O, and network utilization for your instances. When performance falls outside your established baseline, you might need to reconfigure or optimize the instance to reduce CPU utilization, improve disk I/O, or reduce network traffic.

Topics

- [Available tools to monitor Amazon IoT Events](#)
- [Monitoring Amazon IoT Events with Amazon CloudWatch](#)
- [Logging Amazon IoT Events API calls with Amazon CloudTrail](#)

Available tools to monitor Amazon IoT Events

Amazon provides various tools that you can use to monitor Amazon IoT Events. You can configure some of these tools to do the monitoring for you, while some of the tools require manual intervention. We recommend that you automate monitoring tasks as much as possible.

Automated monitoring tools

You can use the following automated monitoring tools to watch Amazon IoT Events and report when something is wrong:

- **Amazon CloudWatch Logs** – Monitor, store, and access your log files from Amazon CloudTrail or other sources. For more information, see [Using Amazon CloudWatch dashboards](#) in the *Amazon CloudWatch User Guide*.

- **Amazon CloudTrail Log Monitoring** – Share log files between accounts, monitor CloudTrail log files in real time by sending them to CloudWatch Logs, write log-processing applications in Java, and validate that your log files have not changed after delivery by CloudTrail. For more information, see [Working with CloudTrail log files](#) in the *Amazon CloudTrail User Guide*.

Manual monitoring tools

Another important part of monitoring Amazon IoT Events involves manually monitoring those items that the CloudWatch alarms don't cover. The Amazon IoT Events, CloudWatch, and other Amazon console dashboards provide an at-a-glance view of the state of your Amazon environment. We recommend that you also check the log files on Amazon IoT Events.

- The Amazon IoT Events console shows:
 - Detector models
 - Detectors
 - Inputs
 - Settings
- The CloudWatch home page shows:
 - Current alarms and status
 - Graphs of alarms and resources
 - Service health status

In addition, you can use CloudWatch to do the following:

- Create [Creating a CloudWatch dashboard](#) to monitor the services you care about
- Graph metric data to troubleshoot issues and discover trends
- Search and browse all your Amazon resource metrics
- Create and edit alarms to be notified of problems

Monitoring Amazon IoT Events with Amazon CloudWatch

When you develop or debug an Amazon IoT Events detector model, you need to know what Amazon IoT Events is doing, and any errors it encounters. Amazon CloudWatch monitors your Amazon resources and the applications you run on Amazon in real time. With CloudWatch, you gain systemwide visibility into resource use, application performance, and operational health. [Enable Amazon CloudWatch logging when developing Amazon IoT Events detector models](#) has

information on how to enable CloudWatch logging for Amazon IoT Events. To generate logs like the one shown below you must set the **Level of verbosity** to 'Debug' and provide one or more **Debug Targets** that is a **Detector Model Name** and an optional **KeyValue**.

The following example shows a CloudWatch DEBUG level log entry generated by Amazon IoT Events.

```
{
  "timestamp": "2019-03-15T15:56:29.412Z",
  "level": "DEBUG",
  "logMessage": "Summary of message evaluation",
  "context": "MessageEvaluation",
  "status": "Success",
  "messageId": "SensorAggregate_2th846h",
  "keyValue": "boiler_1",
  "detectorModelName": "BoilerAlarmDetector",
  "initialState": "high_temp_alarm",
  "initialVariables": {
    "high_temp_count": 1,
    "high_pressure_count": 1
  },
  "finalState": "no_alarm",
  "finalVariables": {
    "high_temp_count": 0,
    "high_pressure_count": 0
  },
  "message": "{ \"temp\": 34.9, \"pressure\": 84.5}",
  "messageType": "CUSTOMER_MESSAGE",
  "conditionEvaluationResults": [
    {
      "result": "True",
      "eventName": "alarm_cleared",
      "state": "high_temp_alarm",
      "lifeCycle": "OnInput",
      "hasTransition": true
    },
    {
      "result": "Skipped",
      "eventName": "alarm_escalated",
      "state": "high_temp_alarm",
      "lifeCycle": "OnInput",
      "hasTransition": true,
      "resultDetails": "Skipped due to transition from alarm_cleared event"
    }
  ]
}
```

```
    },  
    {  
      "result": "True",  
      "eventName": "should_recall_technician",  
      "state": "no_alarm",  
      "lifeCycle": "OnEnter",  
      "hasTransition": true  
    }  
  ]  
}
```

Logging Amazon IoT Events API calls with Amazon CloudTrail

Amazon IoT Events is integrated with Amazon CloudTrail, a service that provides a record of actions taken by a user, role, or an Amazon service in Amazon IoT Events. CloudTrail captures all API calls for Amazon IoT Events as events, including calls from the Amazon IoT Events console and from code calls to the Amazon IoT Events APIs.

If you create a trail, you can enable continuous delivery of CloudTrail events to an Amazon S3 bucket, including events for Amazon IoT Events. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. Using the information collected by CloudTrail, you can determine the request that was made to Amazon IoT Events, the IP address from which the request was made, who made the request, when it was made, and additional details.

To learn more about CloudTrail, see the [Amazon CloudTrail User Guide](#).

Amazon IoT Events information in CloudTrail

CloudTrail is enabled on your Amazon account when you create the account. When activity occurs in Amazon IoT Events, that activity is recorded in a CloudTrail event with other Amazon service events in **Event history**. You can view, search, and download recent events in your Amazon account. For more information, see [Working with CloudTrail Event history](#).

For an ongoing record of events in your Amazon account, including events for Amazon IoT Events, create a trail. A trail enables CloudTrail to deliver log files to an Amazon S3 bucket. By default, when you create a trail in the console, the trail applies to all Amazon Regions. The trail logs events from all Regions in the Amazon partition and delivers the log files to the Amazon S3 bucket that you specify. Additionally, you can configure other Amazon services to further analyze and act on the event data collected in CloudTrail logs. For more information, see:

- [Creating a trail for your Amazon account](#)
- [CloudTrail supported services and integrations](#)
- [Configuring Amazon SNS notifications for CloudTrail](#)
- [Receiving CloudTrail log files from multiple regions](#) and [Receiving CloudTrail log files from multiple accounts](#)

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root or IAM user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another Amazon service.

For more information, see the [CloudTrail userIdentity element](#). Amazon IoT Events actions are documented in the [Amazon IoT Events API reference](#).

Understanding Amazon IoT Events log file entries

A trail is a configuration that enables delivery of events as log files to an Amazon S3 bucket that you specify. Amazon CloudTrail log files contain one or more log entries. An event represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files are not an ordered stack trace of the public API calls, so they don't appear in any specific order.

When CloudTrail logging is enabled in your Amazon account, most API calls made to Amazon IoT Events actions are tracked in CloudTrail log files where they are written with other Amazon service records. CloudTrail determines when to create and write to a new file based on a time period and file size.

Every log entry contains information about who generated the request. The user identity information in the log entry helps you determine the following:

- Whether the request was made with root or IAM user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another Amazon service.

To be notified upon log file delivery, you can configure CloudTrail to publish Amazon SNS notifications when new log files are delivered. For more information, see [Configuring Amazon SNS notifications for CloudTrail](#).

You can also aggregate Amazon IoT Events log files from multiple Amazon Regions and multiple Amazon accounts into a single Amazon S3 bucket.

For more information, see [Receiving CloudTrail log files from multiple regions](#) and [Receiving CloudTrail log files from multiple accounts](#).

Example: DescribeDetector action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the DescribeDetector action.

```
{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/Admin/bertholt-brecht",
    "accountId": "123456789012",
    "accessKeyId": "access-key-id",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-08T18:53:58Z"
      },
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/Admin",
        "accountId": "123456789012",
        "userName": "Admin"
      }
    }
  },
  "eventTime": "2019-02-08T19:02:44Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "DescribeDetector",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-cli/1.15.65 Python/3.7.1 Darwin/16.7.0 boto3/1.10.65",
```

```

"requestParameters": {
  "detectorModelName": "pressureThresholdEventDetector-brecht",
  "keyValue": "1"
},
"responseElements": null,
"requestID": "00f41283-ea0f-4e85-959f-bee37454627a",
"eventID": "5eb0180d-052b-49d9-a289-0eb8d08d4c27",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}

```

Example: CreateDetectorModel action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the CreateDetectorModel action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-Lambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEvents-RoleForIotEvents-ABC123DEF456/IotEvents-Lambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      },
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-ABC123DEF456",
        "accountId": "123456789012",
        "userName": "IotEventsLambda-RoleForIotEvents-ABC123DEF456"
      }
    }
  },
  "eventTime": "2019-02-07T23:54:43Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "CreateDetectorModel",

```

```

"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": {
  "detectorModelName": "myDetectorModel",
  "key": "HIDDEN_DUE_TO_SECURITY_REASONS",
  "roleArn": "arn:aws-cn:iam::123456789012:role/events_action_execution_role"
},
"responseElements": null,
"requestID": "cecfbfa1-e452-4fa6-b86b-89a89f392b66",
"eventID": "8138d46b-50a3-4af0-9c5e-5af5ef75ea55",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}

```

Example: CreateInput action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the CreateInput action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-Lambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-ABC123DEF456/IotEvents-Lambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      }
    },
    "sessionIssuer": {
      "type": "Role",
      "principalId": "AKIAI44QH8DHBEXAMPLE",
      "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-ABC123DEF456",
      "accountId": "123456789012",
      "userName": "IotEventsLambda-RoleForIotEvents-ABC123DEF456"
    }
  }
},
"eventTime": "2019-02-07T23:54:43Z",

```



```

"eventSource": "iotevents.amazonaws.com",
"eventName": "CreateInput",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": {
  "inputName": "batchputmessagedetectorupdated",
  "inputDescription": "batchputmessagedetectorupdated"
},
"responseElements": null,
"requestID": "fb315af4-39e9-4114-94d1-89c9183394c1",
"eventID": "6d8cf67b-2a03-46e6-bbff-e113a7bded1e",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}

```

Example: DeleteDetectorModel action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the DeleteDetectorModel action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      }
    },
    "sessionIssuer": {
      "type": "Role",
      "principalId": "AKIAI44QH8DHBEXAMPLE",
      "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-ABCD123DEF456",
      "accountId": "123456789012",
      "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
    }
  }
}

```

```

    }
  },
  "eventTime": "2019-02-07T23:54:11Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "DeleteDetectorModel",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "requestParameters": {
    "detectorModelName": "myDetectorModel"
  },
  "responseElements": null,
  "requestID": "149064c1-4e24-4160-a5b2-1065e63ee2e4",
  "eventID": "7669db89-dcc0-4c42-904b-f24b764dd808",
  "eventType": "AwsApiCall",
  "recipientAccountId": "123456789012"
}

```

Example: DeleteInput action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the DeleteInput action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      }
    },
    "sessionIssuer": {
      "type": "Role",
      "principalId": "AKIAI44QH8DHBEXAMPLE",
      "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-ABCD123DEF456",
      "accountId": "123456789012",
      "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
    }
  }
}

```

```

    }
  },
  "eventTime": "2019-02-07T23:54:38Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "DeleteInput",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "errorCode": "ResourceNotFoundException",
  "errorMessage": "Input of name: NoSuchInput not found",
  "requestParameters": {
    "inputName": "NoSuchInput"
  },
  "responseElements": null,
  "requestID": "ce6d28ac-5baf-423d-a5c3-afd009c967e3",
  "eventID": "be0ef01d-1c28-48cd-895e-c3ff3172c08e",
  "eventType": "AwsApiCall",
  "recipientAccountId": "123456789012"
}

```

Example: DescribeDetectorModel action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the DescribeDetectorModel action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      }
    },
    "sessionIssuer": {
      "type": "Role",
      "principalId": "AAKIAI44QH8DHBEXAMPLE",

```

```

    "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
    "accountId": "123456789012",
    "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
  }
},
"eventTime": "2019-02-07T23:54:20Z",
"eventSource": "iotevents.amazonaws.com",
"eventName": "DescribeDetectorModel",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": {
  "detectorModelName": "myDetectorModel"
},
"responseElements": null,
"requestID": "18a11622-8193-49a9-85cb-1fa6d3929394",
"eventID": "1ad80ff8-3e2b-4073-ac38-9cb3385beb04",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}

```

Example: DescribeInput action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the DescribeInput action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AAKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      }
    }
  },

```

```

    "sessionIssuer": {
      "type": "Role",
      "principalId": "AKIAI44QH8DHBEXAMPLE",
      "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
      "accountId": "123456789012",
      "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
    }
  },
  "eventTime": "2019-02-07T23:56:09Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "DescribeInput",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "requestParameters": {
    "inputName": "input_createinput"
  },
  "responseElements": null,
  "requestID": "3af641fa-d8af-41c9-ba77-ac9c6260f8b8",
  "eventID": "bc4e6cc0-55f7-45c1-b597-ec99aa14c81a",
  "eventType": "AwsApiCall",
  "recipientAccountId": "123456789012"
}

```

Example: DescribeLoggingOptions action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the DescribeLoggingOptions action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",

```

```

    "creationDate": "2019-02-07T22:22:30Z"
  },
  "sessionIssuer": {
    "type": "Role",
    "principalId": "AKIAI44QH8DHBEXAMPLE",
    "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
    "accountId": "123456789012",
    "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
  }
}
},
"eventTime": "2019-02-07T23:53:23Z",
"eventSource": "iotevents.amazonaws.com",
"eventName": "DescribeLoggingOptions",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": null,
"responseElements": null,
"requestID": "b624b6c5-aa33-41d8-867b-025ec747ee8f",
"eventID": "9c7ce626-25c8-413a-96e7-92b823d6c850",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}

```

Example: ListDetectorModels action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the ListDetectorModels action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",

```

```

    "creationDate": "2019-02-07T22:22:30Z"
  },
  "sessionIssuer": {
    "type": "Role",
    "principalId": "AKIAI44QH8DHBEXAMPLE",
    "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
    "accountId": "123456789012",
    "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
  }
}
},
"eventTime": "2019-02-07T23:53:23Z",
"eventSource": "iotevents.amazonaws.com",
"eventName": "ListDetectorModels",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": {
  "nextToken": "CkZEXRlY3Rvck1vZGVsMl9saXN0ZGV0ZWN0b3Jtb2RlbHN0ZXN0X2VlOWJkZTk1YT",
  "maxResults": 3
},
"responseElements": null,
"requestID": "6d70f262-da95-4bb5-94b4-c08369df75bb",
"eventID": "2d01a25c-d5c7-4233-99fe-ce1b8ec05516",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}

```

Example: ListDetectorModelVersions action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the ListDetectorModelVersions action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",

```

```
"sessionContext": {
  "attributes": {
    "mfaAuthenticated": "false",
    "creationDate": "2019-02-07T22:22:30Z"
  },
  "sessionIssuer": {
    "type": "Role",
    "principalId": "AKIAI44QH8DHBEXAMPLE",
    "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
    "accountId": "123456789012",
    "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
  }
},
"eventTime": "2019-02-07T23:53:33Z",
"eventSource": "iotevents.amazonaws.com",
"eventName": "ListDetectorModelVersions",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": {
  "detectorModelName": "myDetectorModel",
  "maxResults": 2
},
"responseElements": null,
"requestID": "ebeb277-6bd8-44ea-8abd-fbf40ac044ee",
"eventID": "fc6281a2-3fac-4e1e-98e0-ca6560b8b8be",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}
```

Example: ListDetectors action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the ListDetectors action.

```
{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
```



```

    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      },
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
        "accountId": "123456789012",
        "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
      }
    }
  },
  "eventTime": "2019-02-07T23:53:54Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "ListDetectors",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "requestParameters": {
    "detectorModelName": "batchputmessagedetectorinstancecreated",
    "stateName": "HIDDEN_DUE_TO_SECURITY_REASONS"
  },
  "responseElements": null,
  "requestID": "4783666d-1e87-42a8-85f7-22d43068af94",
  "eventID": "0d2b7e9b-afe6-4aef-afd2-a0bb1e9614a9",
  "eventType": "AwsApiCall",
  "recipientAccountId": "123456789012"
}

```

Example: ListInputs action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the ListInputs action.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",

```

```

    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      },
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
        "accountId": "123456789012",
        "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
      }
    }
  },
  "eventTime": "2019-02-07T23:53:57Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "ListInputs",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "requestParameters": {
    "nextToken": "CkhjYW5hcnlfdGVzdF9pbmB1dF9saXN0ZGV0ZWN0b3Jtb2R1bHN0ZXN0ZDU3OGZ",
    "maxResults": 3
  },
  "responseElements": null,
  "requestID": "dd6762a1-1f24-4e63-a986-5ea3938a03da",
  "eventID": "c500f6d8-e271-4366-8f20-da4413752469",
  "eventType": "AwsApiCall",
  "recipientAccountId": "123456789012"
}

```

Example: PutLoggingOptions action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the PutLoggingOptions action.

```
{
```

```
"eventVersion": "1.05",
"userIdentity": {
  "type": "AssumedRole",
  "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
  "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
  "accountId": "123456789012",
  "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
  "sessionContext": {
    "attributes": {
      "mfaAuthenticated": "false",
      "creationDate": "2019-02-07T22:22:30Z"
    },
    "sessionIssuer": {
      "type": "Role",
      "principalId": "AKIAI44QH8DHBEXAMPLE",
      "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
      "accountId": "123456789012",
      "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
    }
  }
},
"eventTime": "2019-02-07T23:56:43Z",
"eventSource": "iotevents.amazonaws.com",
"eventName": "PutLoggingOptions",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.168.0.1",
"userAgent": "aws-internal/3",
"requestParameters": {
  "loggingOptions": {
    "roleArn": "arn:aws-cn:iam::123456789012:role/logging__logging_role",
    "level": "INFO",
    "enabled": false
  }
},
"responseElements": null,
"requestID": "df570e50-fb19-4636-9ec0-e150a94bc52c",
"eventID": "3247f928-26aa-471e-b669-e4a9e6fbc42c",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}
```

Example: UpdateDetectorModel action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the UpdateDetectorModel action.

```
{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      },
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
        "accountId": "123456789012",
        "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
      }
    }
  },
  "eventTime": "2019-02-07T23:55:51Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "UpdateDetectorModel",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "requestParameters": {
    "detectorModelName": "myDetectorModel",
    "roleArn": "arn:aws-cn:iam::123456789012:role/Events_action_execution_role"
  },
  "responseElements": null,
  "requestID": "add29860-c1c5-4091-9917-d2ef13c356cf",
  "eventID": "7baa9a14-6a52-47dc-aea0-3cace05147c3",
  "eventType": "AwsApiCall",
  "recipientAccountId": "123456789012"
}
```

```
}
```

Example: UpdateInput action for CloudTrail

The following example shows a CloudTrail log entry that demonstrates the UpdateInput action.

```
{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:IotEvents-EventsLambda",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456/IotEvents-EventsLambda",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2019-02-07T22:22:30Z"
      },
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/IotEventsLambda-RoleForIotEvents-
ABCD123DEF456",
        "accountId": "123456789012",
        "userName": "IotEventsLambda-RoleForIotEvents-ABCD123DEF456"
      }
    }
  },
  "eventTime": "2019-02-07T23:53:00Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "UpdateInput",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.168.0.1",
  "userAgent": "aws-internal/3",
  "errorCode": "ResourceNotFoundException",
  "errorMessage": "Input of name: NoSuchInput not found",
  "requestParameters": {
    "inputName": "NoSuchInput",
    "inputDescription": "this is a description of an input"
  },
  "responseElements": null,
  "requestID": "58d5d2bb-4110-4c56-896a-ee9156009f41",
}
```

```
"eventID": "c2df241a-fd53-4fd0-936c-ba309e5dc62d",
"eventType": "AwsApiCall",
"recipientAccountId": "123456789012"
}
```

Example: BatchPutMessage action for CloudTrail

Amazon IoT Events can use a CloudTrail integration for data plane API logging. This example adds details on data events through the BatchPutMessage action.

```
{
  "eventVersion": "1.09",
  "userIdentity": {
    "type": "AssumedRole",
    "principalId": "AKIAI44QH8DHBEXAMPLE:PrincipalId",
    "arn": "arn:aws-cn:sts::123456789012:assumed-role/my-iam-role/my-iam-
role-entity",
    "accountId": "123456789012",
    "accessKeyId": "AKIAI44QH8DHBEXAMPLE",
    "sessionContext": {
      "sessionIssuer": {
        "type": "Role",
        "principalId": "AKIAI44QH8DHBEXAMPLE",
        "arn": "arn:aws-cn:iam::123456789012:role/my-iam-role",
        "accountId": "123456789012",
        "userName": "sample_user_name"
      },
      "attributes": {
        "creationDate": "2024-11-22T18:32:41Z",
        "mfaAuthenticated": "false"
      }
    }
  },
  "eventTime": "2024-11-22T18:57:35Z",
  "eventSource": "iotevents.amazonaws.com",
  "eventName": "BatchPutMessage",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "3.239.107.128",
  "userAgent": "aws-internal/3",
  "requestParameters": {
    "messages": [
      {
        "messageId": "e306d827-b2e4-4439-9c86-411d4242a397",
```

```

        "payload": "HIDDEN_DUE_TO_SECURITY_REASONS",
        "inputName": "my_input_name"
    }
  ],
  "responseElements": {
    "batchPutMessageErrorEntries": []
  },
  "requestID": "cefc6b63-9ccf-4e31-9177-4aec8e701bfe",
  "eventID": "b994b52c-6011-4e3c-ad5f-e784e732fde0",
  "readOnly": false,
  "resources": [
    {
      "accountId": "123456789012",
      "type": "AWS::IoTEvents::Input",
      "ARN": "arn:aws-cn:iotevents:us-east-1:123456789012:input/
my_input_name"
    }
  ],
  "eventType": "AwsApiCall",
  "managementEvent": false,
  "recipientAccountId": "123456789012",
  "eventCategory": "Data",
  "tlsDetails": {
    "tlsVersion": "TLSv1.3",
    "cipherSuite": "TLS_AES_128_GCM_SHA256",
    "clientProvidedHostHeader": "iotevents.us-east-1.amazonaws.com"
  }
},

```

Compliance validation for Amazon IoT Events

To learn whether an Amazon Web Services service is within the scope of specific compliance programs, see [Amazon Web Services services in Scope by Compliance Program](#) and choose the compliance program that you are interested in. For general information, see [Amazon Web Services Compliance Programs](#).

You can download third-party audit reports using Amazon Artifact. For more information, see [Downloading Reports in Amazon Artifact](#).

Your compliance responsibility when using Amazon Web Services services is determined by the sensitivity of your data, your company's compliance objectives, and applicable laws and regulations. Amazon provides the following resources to help with compliance:

- [Security & Compliance](#) – These solution implementation guides discuss architectural considerations and provide steps for deploying security and compliance features.
- [Amazon Compliance Resources](#) – This collection of workbooks and guides might apply to your industry and location.
- [Evaluating Resources with Rules](#) in the *Amazon Config Developer Guide* – The Amazon Config service assesses how well your resource configurations comply with internal practices, industry guidelines, and regulations.
- [Amazon Security Hub](#) – This Amazon Web Services service provides a comprehensive view of your security state within Amazon. Security Hub uses security controls to evaluate your Amazon resources and to check your compliance against security industry standards and best practices. For a list of supported services and controls, see [Security Hub controls reference](#).
- [Amazon GuardDuty](#) – This Amazon Web Services service detects potential threats to your Amazon Web Services accounts, workloads, containers, and data by monitoring your environment for suspicious and malicious activities. GuardDuty can help you address various compliance requirements, like PCI DSS, by meeting intrusion detection requirements mandated by certain compliance frameworks.

Resilience in Amazon IoT Events

The Amazon global infrastructure is built around Amazon Regions and Availability Zones. Amazon Regions provide multiple physically separated and isolated Availability Zones, which are connected with low-latency, high-throughput, and highly redundant networking. With Availability Zones, you can design and operate applications and databases that automatically fail over between Availability Zones without interruption. Availability Zones are more highly available, fault tolerant, and scalable than traditional single or multiple data center infrastructures.

For more information about Amazon Regions and Availability Zones, see [Amazon global infrastructure](#).

Infrastructure security in Amazon IoT Events

As a managed service, Amazon IoT Events is protected by Amazon global network security. For information about Amazon security services and how Amazon protects infrastructure, see [Amazon Cloud Security](#). To design your Amazon environment using the best practices for infrastructure security, see [Infrastructure Protection](#) in *Security Pillar Amazon Well-Architected Framework*.

You use Amazon published API calls to access through the network. Clients must support the following:

- Transport Layer Security (TLS). We require TLS 1.2 and recommend TLS 1.3.
- Cipher suites with perfect forward secrecy (PFS) such as DHE (Ephemeral Diffie-Hellman) or ECDHE (Elliptic Curve Ephemeral Diffie-Hellman). Most modern systems such as Java 7 and later support these modes.

Additionally, requests must be signed by using an access key ID and a secret access key that is associated with an IAM principal. Or you can use the [Amazon Security Token Service](#) (Amazon STS) to generate temporary security credentials to sign requests.

Amazon service quotas for Amazon IoT Events resources

The *Amazon Web Services General Reference Guide* provides the default quotas for Amazon IoT Events for an Amazon account. Unless specified, each quota is per Amazon Region. For more information, see [Amazon IoT Events endpoints and quotas](#) and [Amazon Service Quotas](#) in the *Amazon Web Services General Reference Guide*.

To request a service quota increase, submit a support case in the [Support center](#) console. For more information, see [Requesting a quota increase](#) in the *Service Quotas User Guide*.

Note

- All names for detector models and inputs must be unique within an account.
- You can't change names for detector models and inputs after they're created.

Tagging your Amazon IoT Events resources

To help you manage and organize your detector models and inputs you can optionally assign your own metadata to each of these resources in the form of tags. This section describes tags and shows you how to create them.

Tag basics

Tags enable you to categorize your Amazon IoT Events resources in different ways, for example, by purpose, owner, or environment. This is useful when you have many resources of the same type. You can quickly identify a specific resource based on the tags you've assigned to it.

Each tag consists of a key and optional value, both of which you define. For example, you could define a set of tags for your inputs that helps you track the devices that send these inputs by their type. We recommend that you create a set of tag keys that meets your needs for each kind of resource. Using a consistent set of tag keys makes it easier for you to manage your resources.

You can search for and filter resources based on the tags you add or apply, use tags to categorize and track your costs, and also use tags to control access to your resources as described in [Using tags with IAM policies](#) in the *Amazon IoT Developer Guide*.

For ease of use, the Tag Editor in the Amazon Web Services Management Console provides a central, unified way to create and manage your tags. For more information, see [Getting started with Tag Editor](#) in the *Tagging Amazon Resources and Tag Editor User Guide*.

You can also work with tags using the Amazon CLI and the Amazon IoT Events API. You can associate tags with detector models and inputs when you create them by using the "Tags" field in the following commands:

- [CreateDetectorModel](#)
- [CreateInput](#)

You can add, modify, or delete tags for existing resources that support tagging by using the following commands:

- [TagResource](#)
- [ListTagsForResource](#)
- [UntagResource](#)

You can edit tag keys and values, and you can remove tags from a resource at any time. You can set the value of a tag to an empty string, but you can't set the value of a tag to null. If you add a tag that has the same key as an existing tag on that resource, the new value overwrites the old value. If you delete a resource, any tags associated with the resource are also deleted.

For more information, see [Best Practices for Tagging Amazon Resources](#)

Tag restrictions and limitations

The following basic restrictions apply to tags:

- Maximum number of tags per resource – 50
- Maximum key length – 127 Unicode characters in UTF-8
- Maximum value length – 255 Unicode characters in UTF-8
- Tag keys and values are case sensitive.
- Do not use the "aws :" prefix in your tag names or values because it's reserved for Amazon use. You can't edit or delete tag names or values with this prefix. Tags with this prefix don't count against your tags per resource limit.
- If your tagging schema is used across multiple services and resources, remember that other services may have restrictions on allowed characters. Generally, allowed characters are: letters, spaces, and numbers representable in UTF-8, and the following special characters: + - = . _ : / @.

Using tags with IAM policies

You can apply tag-based resource-level permissions in the IAM policies you use for Amazon IoT Events API actions. This gives you better control over what resources a user can create, modify, or use.

You use the `Condition` element (also called the `Condition` block) with the following condition context keys and values in an IAM policy to control user access (permissions) based on a resource's tags:

- Use `aws:ResourceTag/<tag-key>: <tag-value>` to allow or deny user actions on resources with specific tags.
- Use `aws:RequestTag/<tag-key>: <tag-value>` to require that a specific tag be used (or not used) when making an API request to create or modify a resource that allows tags.

- Use `aws:TagKeys: [<tag-key>, ...]` to require that a specific set of tag keys be used (or not used) when making an API request to create or modify a resource that allows tags.

Note

The condition context keys and values in an IAM policy apply only to those Amazon IoT Events actions where an identifier for a resource capable of being tagged is a required parameter.

[Controlling access using tags](#) in the *Amazon Identity and Access Management User Guide* has additional information on using tags. The [IAM JSON policy reference](#) section of that guide has detailed syntax, descriptions, and examples of the elements, variables, and evaluation logic of JSON policies in IAM.

The following example policy applies two tag-based restrictions. A user restricted by this policy:

- Cannot give a resource the tag "env=prod" (in the example, see the line `"aws:RequestTag/env" : "prod"`)
- Cannot modify or access a resource that has an existing tag "env=prod" (in the example, see the line `"aws:ResourceTag/env" : "prod"`).

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Deny",
      "Action": [
        "iotevents:CreateDetectorModel",
        "iotevents:CreateAlarmModel",
        "iotevents:CreateInput",
        "iotevents:TagResource"
      ],
      "Resource": "*",
      "Condition": {
        "StringEquals": {
          "aws:RequestTag/env": "prod"
        }
      }
    }
  ]
}
```

```

    },
    {
      "Effect": "Deny",
      "Action": [
        "iotevents:DescribeDetectorModel",
        "iotevents:DescribeAlarmModel",
        "iotevents:UpdateDetectorModel",
        "iotevents:UpdateAlarmModel",
        "iotevents>DeleteDetectorModel",
        "iotevents>DeleteAlarmModel",
        "iotevents:ListDetectorModelVersions",
        "iotevents:ListAlarmModelVersions",
        "iotevents:UpdateInput",
        "iotevents:DescribeInput",
        "iotevents>DeleteInput",
        "iotevents:ListTagsForResource",
        "iotevents:TagResource",
        "iotevents:UntagResource",
        "iotevents:UpdateInputRouting"
      ],
      "Resource": "*",
      "Condition": {
        "StringLike": {
          "aws:ResourceTag/env": "prod"
        }
      }
    },
    {
      "Effect": "Allow",
      "Action": [
        "iotevents:*"
      ],
      "Resource": "*"
    }
  ]
}

```

You can also specify multiple tag values for a given tag key by enclosing them in a list, as follows.

```

"StringEquals" : {
  "aws:ResourceTag/env" : ["dev", "test"]
}

```

Note

If you allow or deny users access to resources based on tags, you must consider explicitly denying users the ability to add those tags to or remove them from the same resources. Otherwise, it's possible for a user to circumvent your restrictions and gain access to a resource by modifying its tags.

Troubleshooting Amazon IoT Events

This troubleshooting guide provides solutions for common issues you may encounter when using Amazon IoT Events. Browse the topics to identify and resolve problems with detecting events, accessing data, permissions, service integrations, device configurations, and more. With troubleshooting advice for the Amazon IoT Events console, API, CLI, errors, latency, and integrations, this guide aims to quickly resolve your issues so you can build reliable and scalable event-driven applications.

Topics

- [Common Amazon IoT Events issues and solutions](#)
- [Troubleshooting a detector model by running analyses in Amazon IoT Events](#)

Common Amazon IoT Events issues and solutions

See the following section to troubleshoot errors and find possible solutions to resolve issues with Amazon IoT Events.

Errors

- [Detector model creation errors](#)
- [Updates from a deleted detector model](#)
- [Action trigger failure \(when meeting a condition\)](#)
- [Action trigger failure \(when breaching a threshold\)](#)
- [Incorrect state usage](#)
- [Connection message](#)
- [InvalidRequestException message](#)
- [Amazon CloudWatch Logs action.setTimer errors](#)
- [Amazon CloudWatch payload errors](#)
- [Incompatible data types](#)
- [Failed to send message to Amazon IoT Events](#)

Detector model creation errors

I get errors when I attempt to create a detector model.

Solution

When you create a detector model, you must consider the following limitations.

- Only one action is allowed in each `action` field.
- The `condition` is required for `transitionEvents`. It's optional for `OnEnter`, `OnInput`, and `OnExit` events.
- If the `condition` field is empty, the evaluated result of the condition expression is equivalent to `true`.
- The evaluated result of the condition expression should be a Boolean value. If the result isn't a Boolean value, it's equivalent to `false` and doesn't trigger the actions or transition to the `nextState` specified in the event.

For more information, see [Amazon IoT Events detector model restrictions and limitations](#).

Updates from a deleted detector model

I updated or deleted a detector model a few minutes ago but I'm still getting state updates from the old detector model through MQTT messages or SNS alerts.

Solution

If you update, delete, or recreate a detector model (see [UpdateDetectorModel](#)), there is a delay before all detector instances are deleted and the new model is used. During this time, inputs might continue to be processed by the instances of the previous version of the detector model. You might continue to receive alerts defined by the previous detector model. Wait for at least seven minutes before you recheck the update or report an error.

Action trigger failure (when meeting a condition)

The detector fails to trigger an action or transition to a new state when the condition is met.

Solution

Verify that the evaluated result of the detector's conditional expression is a Boolean value. If the result isn't a Boolean value, it's equivalent to `false` and doesn't trigger the action or transition to the `nextState` specified in the event. For more information, see [Conditional expression syntax](#).

Action trigger failure (when breaching a threshold)

The detector doesn't trigger an action or an event transition when the variable in a conditional expression reaches a specified value.

Solution

If you update `setVariable` for `onInput`, `onEnter`, or `onExit`, the new value isn't used when evaluating any condition during the current processing cycle. Instead, the original value is used until the current cycle is complete. You can change this behavior by setting the `evaluationMethod` parameter in the detector model definition. When `evaluationMethod` is set to `SERIAL`, variables are updated and event conditions evaluated in the order that the events are defined. When `evaluationMethod` is set to `BATCH` (the default), variables are updated and events performed only after all event conditions are evaluated.

Incorrect state usage

The detector enters the wrong states when I attempt to send messages to inputs by using `BatchPutMessage`.

Solution

If you use [BatchPutMessage](#) to send multiple messages to inputs, the order in which the messages or inputs are processed isn't guaranteed. To guarantee ordering, send messages one at a time and wait each time for `BatchPutMessage` to acknowledge success.

Connection message

I get a `('Connection aborted.', error(54, 'Connection reset by peer'))` error when I attempt to call or invoke an API.

Solution

Verify that OpenSSL uses TLS 1.1 or a later version to establish the connection. This should be the default under most Linux distributions or Windows version 7 and later. Users of macOS might need to upgrade OpenSSL.

InvalidRequestException message

I get `InvalidRequestException` when I attempt to call `CreateDetectorModel` and `UpdateDetectorModel` APIs.

Solution

Check the following to help resolve the issue. For more information, see [CreateDetectorModel](#) and [UpdateDetectorModel](#).

- Make sure that you don't use both `seconds` and `durationExpression` as the parameters of `SetTimerAction` at the same time.
- Make sure that your string expression for `durationExpression` is valid. The string expression can contain numbers, variables (`$variable.<variable-name>`), or input values (`$input.<input-name>.<path-to-datum>`).

Amazon CloudWatch Logs action.setTimer errors

You can set up Amazon CloudWatch Logs to monitor Amazon IoT Events detector model instances. The following are common errors generated by Amazon IoT Events, when you use `action.setTimer`.

- **Error:** Your duration expression for the timer named `<timer-name>` could not be evaluated to a number.

Solution

Make sure that your string expression for `durationExpression` can be converted to a number. Other data types, such as Boolean, aren't allowed.

- **Error:** The evaluated result of your duration expression for the timer named `<timer-name>` is greater than 31622440. To ensure accuracy, make sure that your duration expression refers to a value between 60-31622400.

Solution

Make sure that the duration of your timer is less than or equal to 31622400 seconds. The evaluated result of the duration is rounded down to the nearest whole number.

- **Error:** The evaluated result of your duration expression for the timer named `<timer-name>` is less than 60. To ensure accuracy, make sure that your duration expression refers to a value between 60-31622400.

Solution

Make sure that the duration of your timer is greater than or equal to 60 seconds. The evaluated result of the duration is rounded down to the nearest whole number.

- **Error:** Your duration expression for the timer named `<timer-name>` could not be evaluated. Check the variable names, input names, and paths to the data to make sure that you refer to the existing variables and inputs.

Solution

Make sure that your string expression refers to the existing variables and inputs. The string expression can contain numbers, variables (`$variable.variable-name`), and input values (`$input.input-name.path-to-datum`).

- **Error:** Failed to set the timer named `<timer-name>`. Check your duration expression, and try again.

Solution

See the [SetTimerAction](#) action to ensure that you specified the correct parameters, and then set the timer again.

For more information, see [Enable Amazon CloudWatch logging when developing Amazon IoT Events detector models](#).

Amazon CloudWatch payload errors

You can set up Amazon CloudWatch Logs to monitor Amazon IoT Events detector model instances. The following are common errors and warnings generated by Amazon IoT Events, when you configure the action payload.

- **Error:** We couldn't evaluate your expression for the action. Make sure that the variable names, input names, and paths to the data refer to the existing variables and input values. Also, verify that the size of the payload is less than 1 KB, the maximum allowed size of a payload.

Solution

Make sure that you enter the correct variable names, input names, and paths to the data. You might also receive this error message if the action payload is larger than 1 KB.

- **Error:** We couldn't parse your content expression for the payload of *<action-type>*. Enter a content expression with the correct syntax.

Solution

The content expression can contain strings (*'string'*), variables (`$variable.variable-name`), input values (`$input.input-name.path-to-datum`), string concatenations, and strings that contain `{}`.

- **Error:** Your payload expression *{expression}* isn't valid. The defined payload type is JSON, so you must specify an expression that Amazon IoT Events would evaluate to a string.

Solution

If the specified payload type is JSON, Amazon IoT Events first checks if the service can evaluate your expression to a string. The evaluated result can't be a Boolean or number. If the validation fails, you might receive this error.

- **Warning:** The action was executed, but we couldn't evaluate your content expression for the action payload to valid JSON. The defined payload type is JSON.

Solution

Make sure that Amazon IoT Events can evaluate your content expression for the action payload to valid JSON, if you define the payload type as JSON. Amazon IoT Events runs the action even if Amazon IoT Events can't evaluate the content expression to valid JSON.

For more information, see [Enable Amazon CloudWatch logging when developing Amazon IoT Events detector models](#).

Incompatible data types

Message: Incompatible data types [<inferred-types>] found for <reference> in the following expression: <expression>

Solution

You might receive this error for one of the following reasons:

- The evaluated results of your references are not compatible with other operands in your expressions.
- The type of the argument passed to a function is not supported.

When you use references in expressions, check the following:

- When you use a reference as an operand with one or more operators, make sure that all data types that you reference are compatible.

For example, in the following expression, integer 2 is an operand of both the == and && operators. To ensure that the operands are compatible, `$variable.testVariable + 1` and `$variable.testVariable` must reference an integer or decimal.

In addition, integer 1 is an operand of the + operator. Therefore, `$variable.testVariable` must reference an integer or decimal.

```
'$variable.testVariable + 1 == 2 && $variable.testVariable'
```

- When you use a reference as an argument passed to a function, make sure that the function supports the data types that you reference.

For example, the following `timeout("time-name")` function requires a string with double quotes as the argument. If you use a reference for the `timer-name` value, you must reference a string with double quotes.

```
timeout("timer-name")
```

Note

For the `convert(type, expression)` function, if you use a reference for the *type* value, the evaluated result of your reference must be `String`, `Decimal`, or `Boolean`.

For more information, see [Amazon IoT Events reference for inputs and variables in expressions](#).

Failed to send message to Amazon IoT Events

Message: Failed to send message to IoT Events

Solution

You might experience this error for the following reasons:

- The input message payload does not contain the `Input attribute Key`.
- The `Input attribute Key` is not in the same JSON path as specified in the input definition.
- The input message does not match with the schema, as defined in the Amazon IoT Events input.

Note

The data ingestion from other services will also experience failure.

Example

For example in Amazon IoT Core, the Amazon IoT rule will fail with the following message `Verify the Input Attribute key`.

To resolve this, ensure that the input payload message schema conforms to the Amazon IoT Events Input definition and the `Input attribute Key` location matches. For more information, see [Create an input for models in Amazon IoT Events](#) to learn how to define Amazon IoT Events Inputs.

Troubleshooting a detector model by running analyses in Amazon IoT Events

Amazon IoT Events can analyze your detector model and generate analysis results without sending input data to your detector model. Amazon IoT Events performs a series of analyses described in this section to check your detector model. This advanced troubleshooting solution also summarizes diagnostic information, including the severity level and location, so that you can quickly find and fix potential issues in your detector model. For more information about diagnostic error types and messages for your detector model, see [Detector model analysis and diagnostic information for Amazon IoT Events](#).

You can use the Amazon IoT Events console, [API](#), [Amazon Command Line Interface \(Amazon CLI\)](#), or [Amazon SDK](#) to view diagnostic error messages from the analysis of your detector model.

Note

- You must fix all errors before you can publish your detector model.
- We recommend that you review warnings and take necessary actions before you use your detector model in production environments. Otherwise, the detector model might not work as expected.
- You can have up to 10 analyses in the RUNNING status at the same time.

To learn how to analyze your detector model, see [Analyze a detector model for Amazon IoT Events \(Console\)](#) or [Analyze a detector model in Amazon IoT Events \(Amazon CLI\)](#).

Topics

- [Detector model analysis and diagnostic information for Amazon IoT Events](#)
- [Analyze a detector model for Amazon IoT Events \(Console\)](#)
- [Analyze a detector model in Amazon IoT Events \(Amazon CLI\)](#)

Detector model analysis and diagnostic information for Amazon IoT Events

Detector model analyses gather the following diagnostic information:

- **Level** – The severity level of the analysis result. Based on the severity level, analysis results fall into three general categories:
 - **Information** (INFO) – An information result tells you about a significant field in your detector model. This type of result usually doesn't require immediate action.
 - **Warning** (WARNING) – A warning result draws special attention to fields that might cause issues for your detector model. We recommend that you review warnings and take necessary actions before you use your detector model in production environments. Otherwise, the detector model might not work as expected.
 - **Error** (ERROR) – An error result notifies you about a problem found in your detector model. Amazon IoT Events automatically performs this set of analyses when you try to publish the detector model. You must fix all errors before you can publish the detector model.
- **Location** – Contains information that you can use to locate the field in your detector model that the analysis result references. A location typically includes the state name, transition event name, event name, and expression (for example, in state `TemperatureCheck` in `onEnter` in event `Init` in action `setVariable`).
- **Type** – The type of the analysis result. Analysis types fall into the following categories:
 - **supported-actions** – Amazon IoT Events can invoke actions when a specified event or transition event is detected. You can define built-in actions to use a timer or set a variable, or send data to other Amazon services. You must specify actions that work with other Amazon services in an Amazon Region where the Amazon services are available.
 - **service-limits** – Service quotas, also known as limits, are the maximum or minimum number of service resources or operations for your Amazon account. Unless otherwise noted, each quota is Region-specific. Depending on your business needs, you can update your detector model to avoid encountering limits or request a quota increase. You can request increases for some quotas, and other quotas can't be increased. For more information, see [Quotas](#).
- **structure** – The detector model must have all required components such as states and follow a structure that Amazon IoT Events supports. A detector model must have at least one state and a condition that evaluates the incoming input data to detect significant events. When an event is detected, the detector model transitions to the next state and can invoke actions. These events are known as transition events. A transition event must direct the next state to enter.
- **expression-syntax** – Amazon IoT Events provides several ways to specify values when you create and update detector models. You can use literals, operators, functions, references, and substitution templates in the expressions. You can use expressions to specify literal values, or Amazon IoT Events can evaluate the expressions before you specify particular values. Your

expression must follow the required syntax. For more information, see [Expressions to filter, transform, and process event data](#).

Detector Model expressions in Amazon IoT Events can reference specific data or a resource.

- **data-type** – Amazon IoT Events supports integer, decimal, string, and Boolean data types. If Amazon IoT Events can automatically convert the data of one data type to another during expression evaluation, these data types are compatible.

Note

- Integer and decimal are the only compatible data types supported by Amazon IoT Events.
 - Amazon IoT Events can't evaluate arithmetic expressions because Amazon IoT Events can't convert an integer to a string.
- **referenced-data** – You must define the data referenced in your detector model before you can use the data. For example, if you want to send data to a DynamoDB table, you must define a variable that references the table name before you can use the variable in an expression (`$variable.TableName`).
 - **referenced-resource** – Resources that the detector model uses must be available. You must define resources before you can use them. For example, you want to create a detector model to monitor the temperature of a greenhouse. You must define an input (`$input.TemperatureInput`) to route incoming temperature data to your detector model before you can use the `$input.TemperatureInput.sensorData.temperature` to reference the temperature.

See the following section to troubleshoot errors and find possible solutions from the analysis of your detector model.

Troubleshoot detector model errors in Amazon IoT Events

The types of errors described above provide diagnostic information about a detector model and correspond to messages that you might retrieve. Use these messages and suggested solutions to troubleshoot errors with your detector model.

Messages and solutions

- [Location](#)

- [supported-actions](#)
- [service-limits](#)
- [structure](#)
- [expression-syntax](#)
- [data-type](#)
- [referenced-data](#)
- [referenced-resource](#)

Location

An analysis result with information about `Location`, corresponds to the following error message:

- **Message** – Contains additional information about the analysis result. This can be an information, warning, or error message.

Solution: You might receive this error message if you specified an action that Amazon IoT Events currently doesn't support. For a list of supported actions, see [Supported actions to receive data and trigger actions in Amazon IoT Events](#).

supported-actions

An analysis result with information about `supported-actions`, corresponds to the following error messages:

- **Message:** Invalid action type present in action definition: *action-definition*.

Solution: You might receive this error message if you specified an action that Amazon IoT Events currently doesn't support. For a list of supported actions, see [Supported actions to receive data and trigger actions in Amazon IoT Events](#).

- **Message:** DetectorModel definition has an *aws-service* action, but the *aws-service* service is not supported in the region *region-name*.

Solution: You might receive this error message if the action that you specified is supported by Amazon IoT Events, but the action isn't available in your current Region. This might occur when you try to send data to an Amazon service that isn't available in the Region. You must also choose the same Region for both Amazon IoT Events and the Amazon services that you're using.

service-limits

An analysis result with information about `service-limits`, corresponds to the following error messages:

- **Message:** Content Expression allowed in payload exceeded the limit *content-expression-size* bytes in event *event-name* in state *state-name*.

Solution: You might receive this error message if the content expression for your action payload is greater than 1024 bytes. The size of the content expression for a payload can be up to 1024 bytes.

- **Message:** Number of states allowed in detector model definition exceeded the limit *states-per-detector-model*.

Solution: You might receive this error message if your detector model has more than 20 states. A detector model can have up to 20 states.

- **Message:** The duration for timer *timer-name* should be at least *minimum-timer-duration* seconds long.

Solution: You might receive this error message if the duration of your timer is less than 60 seconds. We recommend that the duration of a timer is between 60 and 31622400 seconds. If you specify an expression for the duration of your timer, the evaluated result of the duration expression is rounded down to the nearest whole number.

- **Message:** Number of actions allowed per event exceeded the limit *actions-per-event* in detector model definition

Solution: You might receive this error message if the event has more than 10 actions. You can have up to 10 actions for each event in your detector model.

- **Message:** Number of transition events allowed per state exceeded the limit *transition-events-per-state* in detector model definition.

Solution: You might receive this error message if the state has more than 20 transition events. You can have up to 20 transition events for each state in your detector model.

- **Message:** Number of events allowed per state exceeded the limit *events-per-state* in detector model definition

Solution: You might receive this error message if the state has more than 20 events. You can have up to 20 events for each state in your detector model.

- **Message:** The maximum number of detector models that can be associated with a single input may have reached the limit. Input *input-name* is used in *detector-models-per-input* detector model routes.

Solution: You might receive this warning message if you tried to route an input to more than 10 detector models. You can have up to 10 different detector models associated with a single detector model.

structure

An analysis result with information about `structure`, corresponds to the following error messages:

- **Message:** Actions may only have one type defined, but found an action with *number-of-types* types. Please split into separate Actions.

Solution: You might receive this error message if you specified two or more actions in a single field by using API operations to create or update your detector model. You can define an array of Action objects. Make sure that you define each action as a separate object.

- **Message:** The TransitionEvent *transition-event-name* transitions to a non-existent state *state-name*.

Solution: You might receive this error message if Amazon IoT Events couldn't find the next state that your transition event referenced. Make sure that the next state is defined and that you entered the correct state name.

- **Message:** The DetectorModelDefinition had a shared state name: found state *state-name* with *number-of-states* repetitions.

Solution: You might receive this error message if you use the same name for one or more states. Make sure that you give a unique name to each state in your detector model. The state name must have 1-128 characters. Valid characters: a-z, A-Z, 0-9, _ (underscore), and - (hyphen).

- **Message:** The Definition's initialStateName *initial-state-name* did not correspond to a defined State.

Solution: You might receive this error message if the initial state name is incorrect. The detector model remains in the initial (start) state until an input arrives. Once an input arrives, the detector model immediately transitions to the next state. Make sure that the initial state name is the name of a defined state and that you enter the correct name.

- **Message:** Detector Model Definition must use at least one Input in a condition.

Solution: You might receive this error if you didn't specify an input in a condition. You must use at least one input in at least one condition. Otherwise, Amazon IoT Events doesn't evaluate incoming data.

- **Message:** Only one of seconds and durationExpression can be set in SetTimer.

Solution: You might receive this error message if you used both seconds and durationExpression for your timer. Make sure that you use either seconds or durationExpression as the parameters of SetTimerAction. For more information, see [SetTimerAction](#) in the *Amazon IoT Events API Reference*.

- **Message:** An action in your detector model is unreachable. Check the condition that initiates the action.

Solution: If an action in your detector model is unreachable, the event's condition evaluates to false. Check the condition of the event that contains the action, to ensure that it evaluates to true. When the event's condition evaluates to true, the action should become reachable.

- **Message:** An input attribute is being read, but this may be caused by a timer expiration.

Solution: An input attribute's value can be read when either of the following occurs:

- A new input value has been received.
- When a timer in the detector has expired.

To ensure that an input attribute is being evaluated only when the new value for that input is received, include a call to the `triggerType("Message")` function in your condition as follows:

The original condition being evaluated in the detector model:

```
if ($input.HeartBeat.status == "OFFLINE")
```

would become similar to the following:

```
if ( triggerType("MESSAGE") && $input.HeartBeat.status == "OFFLINE")
```

where a call to the `triggerType("Message")` function comes before the initial input provided in the condition. By using this technique, the `triggerType("Message")` function will evaluate to true and satisfy the condition of receiving a new input value. For more information about the

usage of the `triggerType` function, search for `triggerType` in the [Expressions](#) section in the *Amazon IoT Events Developer Guide*

- **Message:** A state in your detector model is unreachable. Check the condition that will cause a transition to the desired state.

Solution: If a state in your detector model is unreachable, a condition that causes an incoming transition to that state evaluates to false. Check that the conditions of the incoming transitions to that unreachable state in your detector model evaluates to true, so the desired state can become reachable.

- **Message:** An expiring timer can cause an unexpected amount of messages to be sent.

Solution: To prevent your detector model from entering into an infinite state of sending an unexpected amount of messages because a timer has expired, consider using a call to the `triggerType("Message")` function, in the conditions of your detector model as follows:

The original condition being evaluated in the detector model:

```
if (timeout("awake"))
```

would be transformed into a condition that looks similar to the following:

```
if (triggerType("MESSAGE") && timeout("awake"))
```

where a call to the `triggerType("Message")` function comes before the initial input provided in the condition.

This change prevents initiating timer actions in your detector, preventing an infinite loop of messages being sent. For more information about how to use timer actions in your detector, see the [Using built-in actions](#) page of the *Amazon IoT Events Developer Guide*

expression-syntax

An analysis result with information about `expression-syntax`, corresponds to the following error messages:

- **Message:** Your payload expression `{expression}` isn't valid. The defined payload type is JSON, so you must specify an expression that Amazon IoT Events would evaluate to a string.

Solution: If the specified payload type is JSON, Amazon IoT Events first checks if the service can evaluate your expression to a string. The evaluated result can't be a Boolean or number. If the validation doesn't succeed, you might receive this error.

- **Message:** `SetVariableAction.value` must be an expression. Failed to parse value '*variable-value*'

Solution: You can use `SetVariableAction` to define a variable with a name and value. The value can be a string, number, or Boolean value. You can also specify an expression for the value. For more information, see [SetVariableAction](#), in the *Amazon IoT Events API Reference*.

- **Message:** We couldn't parse your expression of the attributes (*attribute-name*) for the DynamoDB action. Enter expression with the correct syntax.

Solution: You must use expressions for all parameters in `DynamoDBAction`. substitution templates. For more information, see [DynamoDBAction](#) in the *Amazon IoT Events API Reference*.

- **Message:** We couldn't parse your expression of the `tableName` for the `DynamoDBv2` action. Enter expression with the correct syntax.

Solution: The `tableName` in `DynamoDBv2Action` must be a string. You must use an expression for the `tableName`. The expressions accept literals, operators, functions, references, and substitution templates. For more information, see [DynamoDBv2Action](#) in the *Amazon IoT Events API Reference*.

- **Message:** We couldn't evaluate your expression to valid JSON. The `DynamoDBv2` action only supports the JSON payload type.

Solution: The payload type for `DynamoDBv2` must be JSON. Make sure that Amazon IoT Events can evaluate your content expression for the payload to valid JSON. For more information, see [DynamoDBv2Action](#), in the *Amazon IoT Events API Reference*.

- **Message:** We couldn't parse your content expression for the payload of *action-type*. Enter a content expression with the correct syntax.

Solution: The content expression can contain strings ('*string*'), variables (`$variable.variable-name`), input values (`$input.input-name.path-to-datum`), string concatenations, and strings that contain `${}`.

- **Message:** Customized Payloads must be non-empty.

Solution: You might receive this error message, if you chose **Custom payload** for your action and didn't enter a content expression in the Amazon IoT Events console. If you choose **Custom payload**, you must enter a content expression under **Custom payload**. For more information, see [Payload](#) in the *Amazon IoT Events API Reference*.

- **Message:** Failed to parse duration expression '*duration-expression*' for timer '*timer-name*'.

Solution: The evaluated result of your duration expression for the timer must be a value between 60–31622400. The evaluated result of the duration is rounded down to the nearest whole number.

- **Message:** Failed to parse expression '*expression*' for *action-name*

Solution: You might receive this message if the expression for the specified action has incorrect syntax. Make sure that you enter an expression with the correct syntax. For more information, see [Syntax to filter device data and define actions in Amazon IoT Events](#).

- **Message:** Your *fieldName* for IotSitewiseAction couldn't be parsed. You must use correct syntax in your expression.

Solution: You might receive this error if Amazon IoT Events couldn't parse your *fieldName* for IotSitewiseAction. Make sure the *fieldName* uses an expression that Amazon IoT Events can parse. For more information, see [lotSiteWiseAction](#) in the *Amazon IoT Events API Reference*.

data-type

An analysis result with information about data-type, corresponds to the following error messages:

- **Message:** Duration expression *duration-expression* for timer *timer-name* is not valid, it must return a number.

Solution: You might receive this error message if Amazon IoT Events couldn't evaluate the duration expression for your timer to a number. Make sure that your `durationExpression` can be converted to a number. Other data types, such as Boolean, aren't supported.

- **Message:** Expression *condition-expression* is not a valid condition expression.

Solution: You might receive this error message if Amazon IoT Events couldn't evaluate your *condition-expression* to a Boolean value. The Boolean value must be either TRUE or FALSE. Make sure that your condition expression can be converted to a Boolean value. If the result isn't

a Boolean value, it's equivalent to FALSE and doesn't invoke the actions or transition to the nextState specified in the event.

- **Message:** Incompatible data types [*inferred-types*] found for *reference* in the following expression: *expression*

Solution: Solution: All expressions for the same input attribute or variable in the detector model must reference the same data type.

Use the following information to resolve the issue:

- When you use a reference as an operand with one or more operators, make sure that all data types that you reference are compatible.

For example, in the following expression, integer 2 is an operand of both the == and && operators. To ensure that the operands are compatible, `$variable.testVariable + 1` and `$variable.testVariable` must reference an integer or decimal.

In addition, integer 1 is an operand of the + operator. Therefore, `$variable.testVariable` must reference an integer or decimal.

```
'$variable.testVariable + 1 == 2 && $variable.testVariable'
```

- When you use a reference as an argument passed to a function, make sure that the function supports the data types that you reference.

For example, the following `timeout("time-name")` function requires a string with double quotes as the argument. If you use a reference for the *timer-name* value, you must reference a string with double quotes.

```
timeout("timer-name")
```

Note

For the `convert(type, expression)` function, if you use a reference for the *type* value, the evaluated result of your reference must be String, Decimal, or Boolean.

For more information, see [Amazon IoT Events reference for inputs and variables in expressions](#).

- **Message:** Incompatible data types [*inferred-types*] used with *reference*. This may lead to a runtime error.

Solution: You might receive this warning message if two expressions for the same input attribute or variable reference two data types. Make sure that your expressions for the same input attribute or variable reference the same data type in the detector model.

referenced-data

An analysis result with information about `referenced-data`, corresponds to the following error messages:

- **Message:** Detected broken Timer: timer *timer-name* is used in an expression but is never set.

Solution: You might receive this error message if you use a timer that isn't set. You must set a timer before you use it in an expression. Also, make sure that you enter the correct timer name.

- **Message:** Detected broken Variable: variable *variable-name* is used in an expression but is never set.

Solution: You might receive this error message if you use a variable that isn't set. You must set a variable before you use it in an expression. Also, make sure that you enter the correct variable name.

- **Message:** Detected broken Variable: a variable is used in an expression before being set to a value.

Solution: Each variable must be assigned to a value before it can be evaluated in an expression. Set the value of the variable before every use so its value can be retrieved. Also, make sure that you enter the correct variable name.

referenced-resource

An analysis result with information about `referenced-resource`, corresponds to the following error messages:

- **Message:** Detector Model Definition contains reference to Input that does not exist.

Solution: You might receive this error message if you use expressions to reference an input that doesn't exist. Make sure that your expression references an existing input and enter the correct input name. If you don't have an input, create one first.

- **Message:** Detector Model Definition contains invalid InputName: *input-name*

Solution: You might receive this error message if your detector model contains an invalid input name. Make sure that you enter the correct input name. The input name must have 1-128 characters. Valid characters: a-z, A-Z, 0-9, _ (underscore), and - (hyphen).

Analyze a detector model for Amazon IoT Events (Console)

Amazon IoT Events allows you to monitor and react to IoT data by detecting events and triggering actions with the Amazon IoT Events API. The following steps use the Amazon IoT Events console to analyze a detector model.


Note

After Amazon IoT Events starts analyzing your detector model, you have up to 24 hours to retrieve the analysis results.


A detector model analysis can help you optimize your models, identify potential issues, and ensure they're functioning as intended. For example, on a windfarm, the detector model analysis could reveal if the model correctly identifies potential gear failures based on abnormal vibration patterns. Or, if the model accurately triggers maintenance alerts when wind speeds exceed safe operating thresholds. By refining a model based on the analysis, you can improve predictive maintenance, reduce downtime, and enhance overall energy production efficiency.

To analyze a detector model

1. Sign in to the [Amazon IoT Events console](#).
2. In the navigation pane, choose **Detector models**.
3. Under **Detector models**, choose the target detector model.
4. On your detector model page, choose **Edit**.
5. In the upper-right corner, choose **Run analysis**.



The following is an example analysis result in the Amazon IoT Events console.



Analyze a detector model in Amazon IoT Events (Amazon CLI)

Analyzing your Amazon IoT Events detector models programmatically provides valuable insights into their structure, behavior, and performance. This API-based approach allows for automated analysis, integration with your existing workflows, and the ability to perform bulk operations across multiple detector models. By leveraging the [StartDetectorModelAnalysis](#) API, you can

initiate in-depth examinations of your models, helping you identify potential issues, optimize logic flows, and ensure that your IoT event processing aligns with your business requirements.

The following steps use the Amazon CLI to analyze a detector model.

To analyze a detector model using Amazon CLI

1. Run the following command to start an analysis.

```
aws iotevents start-detector-model-analysis --cli-input-json file://file-name.json
```

Note

Replace *file-name* with the name of the file that contains the detector model definition.

Example Detector model definition

```
{
  "detectorModelDefinition": {
    "states": [
      {
        "stateName": "TemperatureCheck",
        "onInput": {
          "events": [
            {
              "eventName": "Temperature Received",
              "condition":
"isNull($input.TemperatureInput.sensorData.temperature)==false",
              "actions": [
                {
                  "iotTopicPublish": {
                    "mqttTopic": "IoTEvents/Output"
                  }
                }
              ]
            }
          ]
        },
        "transitionEvents": []
      }
    ]
  }
}
```

```
        "onEnter": {
            "events": [
                {
                    "eventName": "Init",
                    "condition": "true",
                    "actions": [
                        {
                            "setVariable": {
                                "variableName": "temperatureChecked",
                                "value": "0"
                            }
                        }
                    ]
                }
            ]
        },
        "onExit": {
            "events": []
        }
    ],
    "initialStateName": "TemperatureCheck"
}
}
```

If you use the Amazon CLI to analyze an existing detector model, choose one of the following to retrieve the detector model definition:

- If you want to use the Amazon IoT Events console, do the following:
 1. In navigation pane, choose **Detector models**.
 2. Under **Detector models**, choose the target detector model.
 3. Choose **Export detector model** from **Action** to download the detector model. The detector model is saved in JSON.
 4. Open the detector model JSON file.
 5. You only need the `detectorModelDefinition` object. Remove the following:
 - The first curly bracket (`{`) at the top of the page
 - The `detectorModel` line
 - The `detectorModelConfiguration` object
 - The last curly bracket (`}`) at the bottom of the page

6. Save the file.
- If you want to use the Amazon CLI, do the following:
 1. Run the following command in a terminal.

```
aws iotevents describe-detector-model --detector-model-name detector-model-name
```

2. Replace *detector-model-name* with the name of your detector model.
3. Copy the `detectorModelDefinition` object to a text editor.
4. Add curly brackets (`{}`) outside of the `detectorModelDefinition`.
5. Save the file in JSON.

Example Example response

```
{  
  "analysisId": "c1133390-14e3-4204-9a66-31efd92a4fed"  
}
```

2. Copy the analysis ID from the output.
3. Run the following command to retrieve the status of the analysis.

```
aws iotevents describe-detector-model-analysis --analysis-id "analysis-id"
```

Note

Replace *analysis-id* with the analysis ID that you copied.

Example Example response

```
{  
  "status": "COMPLETE"  
}
```

The status can be one of the following values:

- **RUNNING** – Amazon IoT Events is analyzing your detector model. This process can take up to one minute to complete.

- COMPLETE – Amazon IoT Events finished analyzing your detector model.
 - FAILED – Amazon IoT Events couldn't analyze your detector model. Try again later.
4. Run the following command to retrieve one or more analysis results of the detector model.

Note

Replace *analysis-id* with the analysis ID that you copied.

```
aws iotevents get-detector-model-analysis-results --analysis-id "analysis-id"
```

Example Example response

```
{
  "analysisResults": [
    {
      "type": "data-type",
      "level": "INFO",
      "message": "Inferred data types [Integer] for
$variable.temperatureChecked",
      "locations": []
    },
    {
      "type": "referenced-resource",
      "level": "ERROR",
      "message": "Detector Model Definition contains reference to Input
'TemperatureInput' that does not exist.",
      "locations": [
        {
          "path": "states[0].onInput.events[0]"
        }
      ]
    }
  ]
}
```

Note

After Amazon IoT Events starts analyzing your detector model, you have up to 24 hours to retrieve the analysis results.

Amazon IoT Events commands

This chapter provides a comprehensive guide to all the API operations available in Amazon IoT Events. It offers detailed explanations, including sample requests, responses, and potential errors for each operation across the supported web services protocols. Understanding these API operations helps you effectively integrate Amazon IoT Events into your IoT applications and automate your event detection and response workflows.

Amazon IoT Events actions

You can use Amazon IoT Events API commands to create, read, update, and delete inputs and detector models, and to list their versions. For more information, see the [actions](#) and [data types](#) that are supported by Amazon IoT Events in the *Amazon IoT Events API Reference*.

The [Amazon IoT Events sections](#) in the *Amazon CLI Command Reference* include the Amazon CLI commands that you can use to administer and manipulate Amazon IoT Events.

Amazon IoT Events data

You can use the Amazon IoT Events Data API commands to send inputs to detectors, list detectors, and view or update a detector's status. For more information, see the [actions](#) and [data types](#) that are supported by Amazon IoT Events Data in the *Amazon IoT Events API Reference*.

The [Amazon IoT Events data sections](#) in the *Amazon CLI Command Reference* includes the Amazon CLI commands that you can use to process Amazon IoT Events data.

Document history for Amazon IoT Events

The following table describes the important changes to the *Amazon IoT Events Developer Guide* after September 17, 2020. For more information about updates to this documentation, you can subscribe to an RSS feed.

Change	Description	Date
Region launch	Amazon IoT Events is now available in the Asia Pacific (Mumbai) region.	September 30, 2021
Region launch	Amazon IoT Events is now available in the Amazon GovCloud (US-West) Region.	September 22, 2021
Troubleshoot a detector model by running analyses	Amazon IoT Events can now analyze your detector model and generate analysis results that you can use to troubleshoot your detector model.	February 23, 2021
Region launch	Launched Amazon IoT Events in China (Beijing).	September 30, 2020
Expression usage	Added examples to show you how to write expressions.	September 22, 2020
Monitoring with alarms	Alarms help you monitor your data for changes. You can create alarms that send notifications when a threshold is breached.	June 1, 2020

Earlier updates

The following table describes important changes to the *Amazon IoT Events Developer Guide* before September 18, 2020.

Change	Description	Date
Added type validation to the Expressions reference	Added type validation information to the Expressions reference.	August 3, 2020
Added Region warning for other services	Added a warning regarding selecting the same region for Amazon IoT Events and other Amazon services.	May 7, 2020
Additions, updates	<ul style="list-style-type: none"> • Payload Customization feature • New event actions: Amazon DynamoDB and Amazon IoT SiteWise 	April 27, 2020
Added built-in functions for detector model conditional expressions	Added built-in functions for detector model conditional expressions.	September 10, 2019
Added detector model examples	Added examples for the detector model.	August 5, 2019
Added new event actions	Added new event actions for: <ul style="list-style-type: none"> • Lambda • Amazon SQS • Kinesis Data Firehose • Amazon IoT Events input 	July 19, 2019
Additions, corrections	<ul style="list-style-type: none"> • Updated description of <code>timeout()</code> function. 	June 11, 2019

Change	Description	Date
	<ul style="list-style-type: none"> Added best practice regarding account inactivity. 	
Updated permissions policy and console debug options	<ul style="list-style-type: none"> Updated the console permissions policy. Updated console debug options page image. 	June 5, 2019
Updates	Amazon IoT Events service open to general availability.	May 30, 2019
Additions, updates	<ul style="list-style-type: none"> Updated security information. Added annotated detector model example. 	May 22, 2019
Added examples and required permissions	Added Amazon SNS payload examples; additions to required permissions for <code>CreateDetectorModel</code> .	May 17, 2019
Added additional security information	Added information to the security section.	May 9, 2019
Limited preview release	Limited preview release of the documentation.	March 28, 2019